

# VMware AirWatch System Settings Reference Manual for SaaS Customers

A comprehensive listing of AirWatch system settings

Workspace ONE UEM v9.6

**Have documentation feedback?** Submit a Documentation Feedback support ticket using the Support Wizard on [support.air-watch.com](https://support.air-watch.com).

Copyright © 2018 VMware, Inc. All rights reserved. This product is protected by copyright and intellectual property laws in the United States and other countries as well as by international treaties. VMware products are covered by one or more patents listed at <http://www.vmware.com/go/patents>.

VMware is a registered trademark or trademark of VMware, Inc. in the United States and other jurisdictions. All other marks and names mentioned herein may be trademarks of their respective companies.

# Table of Contents

- [System on page 5](#)
- [Devices & Users on page 33](#)
- [Apps on page 100](#)
- [Content on page 116](#)
- [Email on page 126](#)

# Chapter 1:

## Overview

System Settings .....	4
SaaS vs. On-Premises .....	4
SKUs and Available Settings .....	4
SaaS Console Administrator Roles .....	4

## System Settings

The settings page enables you to configure all the "behind the scenes" settings that dictate how the Workspace ONE UEM console operates.

Where applicable, you can find references to additional documentation. Some systems settings pages contain mostly legacy settings that are typically not configured or used. These settings are pointed out with a recommendation not to alter them unless instructed to do so by Workspace ONE UEM.

## SaaS vs. On-Premises

There are two versions of this guide – one for SaaS and one for on premises. Ensure you are viewing the correct document that pertains to your Workspace ONE UEM deployment. You are currently reading the SaaS version of the guide. Access these documents on docs.vmware.com.

Note the following distinction between on-premises and SaaS deployments:

- **On-premises** refers to Workspace ONE UEM deployments where your organization hosts all Workspace ONE UEM components and servers on its internal networks. Administrators for on-premises deployments can see additional system settings, and System Administrators can see more still.
- **SaaS** refers to Workspace ONE UEM deployments where certain components, such as the Console and API servers, are hosted in the cloud. UEM console Administrators will be able to see the system settings that correlate to the SKUs their organization has purchased.

## SKUs and Available Settings

While this section covers all of the available Workspace ONE UEM settings, you may or may not see certain sections depending on the SKUs you have purchased. If you do not see a particular section or settings page in your Workspace ONE UEM console then you need to first purchase the SKU for that feature. Please see the Workspace ONE UEM Pricing page (<http://www.air-watch.com/pricing/>) for additional information.

## SaaS Console Administrator Roles

The default administrator role for SaaS Admins is Console Administrator. Depending on your environment, you may see some Admin settings in the system settings menu. However, since not all SaaS admin roles have access to these settings, we have hidden them here. If you want to see more details about a particular Admin settings page that you can see as a SaaS administrator, then please reference the on-premises version of this guide. However, note that you will not see all of the settings that are documented.

# Chapter 2:

## System

### Getting Started

[System / Getting Started on page 7](#)

### Branding

[System / Branding on page 7](#)

### Enterprise Integration

[System / Enterprise Integration / Enterprise Integration Services on page 8](#)

[System / Enterprise Integration / Certificate Authorities on page 8](#)

[System / Enterprise Integration / VMware Enterprise Systems Connector on page 9](#)

[System / Enterprise Integration / Directory Services on page 9](#)

[System / Enterprise Integration / Email \(SMTP\) on page 15](#)

### VMware Tunnel

[System / Enterprise Integration / VMware Tunnel / Configuration on page 16](#)

[System / Enterprise Integration / Tunnel / Network Traffic Rules on page 16](#)

[System / Enterprise Integration / Peer Distribution / Peer Distribution Software Setup on page 17](#)

[System / Enterprise Integration / Third Party Proxies on page 16](#)

[System / Enterprise Integration / SMS on page 17](#)

[System / Enterprise Integration / Pull Service Installers on page 17](#)

[System / Enterprise Integration / Syslog on page 18](#)

[System / Enterprise Integration / Remote Management on page 19](#)

[System / Enterprise Integration / VMware Identity Manager on page 19](#)

### Security

[System / Security / Restricted Actions on page 21](#)

[System / Security / Data Security on page 23](#)

[System / Security / SSL Pinning on page 24](#)

### Help

[System / Help on page 25](#)

**Localization**

[System / Localization / Language Activation on page 25](#)

[System / Localization / Localization Editor on page 25](#)

**Report Subscriptions**

[System / Report Subscriptions on page 25](#)

**Terms of Use**

[System / Terms of Use on page 26](#)

**S/MIME**

[System / S/MIME on page 26](#)

**Advanced**

[System / Advanced / Agent URLs on page 27](#)

**API**

[System / Advanced / API / Event Notifications on page 27](#)

[System / Advanced / API / REST on page 28](#)

[System / Advanced / API / SOAP on page 30](#)

[System / Advanced / Device Root Certificate on page 30](#)

[System / Advanced / Secure Channel Certificate on page 30](#)

[System / Advanced / Service URLs on page 30](#)

[System / Advanced / Site URLs on page 31](#)

[System / Advanced / Query String Authentication on page 31](#)

## System / Getting Started

The Getting Started settings page lets you configure settings related to the Getting Started feature of the Workspace ONE UEM console.

**Note:** This setting is only configurable at a Customer-level organization group.

Setting	Description
<b>Getting Started Workspace ONE Status</b>	Select to Enable or Disable (skip) the Workspace ONE section of the Getting Started wizard.
<b>Getting Started Device Status</b>	Select to Enable or Disable (skip) the Mobile Device Management section of the Getting Started wizard.
<b>Getting Started Content Status</b>	Select to Enable or Disable (skip) the Mobile Content Management section of the Getting Started wizard.
<b>Getting Started Application Status</b>	Select to Enable or Disable (skip) the Mobile Application Management section of the Getting Started wizard.

You can resume or skip any of these sections at any time by navigating to **Getting Started** in the navigation pane of the UEM console.

## System / Branding

The Branding settings page lets you configure settings related to the branding of the Workspace ONE UEM console. Change branding to reflect company colors or visually delineate specific organization groups.

### Branding Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Company Logo</b>	The logo that appears in the top-left of the console, the login splash page, and About Workspace ONE UEM popup. The maximum resolution of the image is 800x300.
<b>Login Page Background</b>	The image that displays on the login page. The suggested resolution of the image is 1024x768.
<b>Self-Service Portal Login Page Background</b>	The image that displays on the self-service portal login splash page. The suggested resolution of the image is 1024x768.
<b>Company Website URL</b>	Selecting the company logo on the Workspace ONE UEM site leads to this URL. If this setting is left blank, selecting the company logo leads to the admin home page.

### Colors

Here you can set the color schemes for the UEM console, with a mockup illustrating your changes.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

### Custom CSS Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
Custom CSS	Insert a cascading style sheet of your own custom design that will override the console defaults.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## System / Enterprise Integration / Enterprise Integration Services

The Enterprise Integration Services settings page is used to configure the EIS component. Note that EIS has been upgraded into the VMware Enterprise Systems Connector and VMware Tunnel components. You will therefore not enable or configure EIS using this page if you are using either of those components. You may see a button to **Transfer Settings**, which lets you migrate your current EIS settings.

## System / Enterprise Integration / Certificate Authorities

The Certificate Authorities (CA) settings page is used to configure integration with various certificate authorities. Rather than configure specific settings, it is here that you actually add a CA and create its request template. Available actions are listed below.

### Certificate Authorities Tab

- Select the **Add** button to add a new CA.
- Select the **Edit** (pencil) icon for an existing CA to edit it.
- Select the **Delete** (X) icon for an existing CA to delete it.

### Request Templates Tab

- Select the **Add** button to add a new request template.
- **Certificate Authority** – Select a CA from the drop-down list to view the request templates associated to it.

- Select the **Edit** (pencil) icon for an existing request template to edit it.
- Select the **Delete** (X) icon for an existing request template to delete it.

## System / Enterprise Integration / VMware Enterprise Systems Connector

The VMware Enterprise Systems Connector settings page is used to configure the VMware Enterprise Systems Connector component. Note that if you already have EIS configured then you will need to disable it by unchecking its check box on the EIS settings page. You may see a button to **Transfer Settings**, which lets you migrate your current EIS settings.

## System / Enterprise Integration / Directory Services

The directory services settings page lets you configure your directory service integration with Workspace ONE UEM. In addition to manually configuring the settings below, you can also select **Launch Setup Wizard** from the bottom of the page.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

### Server Tab

Setting	Description
<b>LDAP</b>	
<b>Directory Type</b>	Select the type of directory service that your organization uses.  <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;"> <p><b>Note:</b> Workspace ONE UEM supports open source LDAP for directory services. For more information, see the following knowledgebase article: <a href="https://support.airwatch.com/resources/115001696028">https://support.airwatch.com/resources/115001696028</a>.</p> </div>
<b>DNS SRV</b>	Allow the Domain Name System Service Record to decide which server in its prioritized list of servers can best support LDAP requests. This feature ensures continuity of services in a high availability environment. The default setting is Disabled.  With this option disabled, Workspace ONE UEM uses your existing directory server, the address of which you enter in the Server setting.  Supported DNS servers: <ul style="list-style-type: none"> <li>• Active Directory integrated Microsoft DNS servers</li> <li>• Standalone Microsoft DNS servers</li> </ul>
<b>Server</b>	Enter the address of your directory server. This setting is only available when <b>Enable DNS SRV</b> is Disabled.

Setting	Description
<b>Encryption Type</b>	Select the type of encryption to use for a directory services communication. The options available are <b>None</b> (unencrypted), <b>SSL</b> , and <b>Start TLS</b> .
<b>Port</b>	<p>Enter the Transmission Control Protocol (TCP) port used to communicate with the domain controller. The default for unencrypted LDAP directory service communication is port 389. Only SaaS environments allow SSL encrypted traffic using port 636. To view a KnowledgeBase article that lists the most up-to-date Workspace ONE UEM SaaS data center IP ranges, refer to <a href="https://support.airwatch.com/articles/115001662168">https://support.airwatch.com/articles/115001662168</a>.</p> <ul style="list-style-type: none"> <li>When you change the <b>Encryption Type</b> setting to <b>SSL</b>, the <b>Port</b> setting automatically changes to 636.</li> <li>When you select the <b>Add Domain</b> button, the <b>Port</b> setting automatically changes to 3268.</li> </ul>
<b>Verify SSL Certificate</b>	This setting is only available when the <b>Encryption Type</b> is <b>SSL</b> or <b>Start TLS</b> . Receive SSL errors by selecting the SSL check box.
<b>Protocol Version</b>	Select the version of the Lightweight Directory Access Protocol (LDAP) that is in use. Active Directory uses LDAP versions 2 or 3. If you are unsure of which Protocol Version to use, try the commonly used value of '3'.
<b>Use Service Account Credentials</b>	Use the App pool credentials from the server on which the VMware Enterprise Systems Connector is installed for authenticating with the domain controller. Enabling this option hides the <b>Bind user name</b> and <b>Bind Password</b> settings.
<b>Bind Authentication Type</b>	<p>Select the type of bind authentication to enable the AirWatch server to communicate with the domain controller.</p> <p>You can select <b>Anonymous</b>, <b>Basic</b>, <b>Digest</b>, <b>Kerberos</b>, <b>NTLM</b>, or <b>GSS-NEGOTIATE</b>. If you are unsure of which Bind Authentication Type to use, try the commonly used GSS-NEGOTIATE. You will know if your selection is not correct when you click <b>Test Connection</b>.</p>
<b>Bind User Name</b>	Enter the credentials used to authenticate with the domain controller. This account (which the entered user name identifies) allows a read-access permission on your directory server and binds the connection when authenticating users. Clear the bind password from the database by selecting the <b>Clear Bind Password</b> check box.
<b>Bind Password</b>	Enter the password for the bind user name to authenticate with the directory server.
<b>Domain /Server</b>	<p>Enter the default domain and server name for any directory-based user accounts. If only one domain is used for all directory user accounts, fill in the text box with the domain. This entry means that users are authenticated without explicitly stating their domain.</p> <p>You can add more domains by selecting the <b>Add Domain</b> option. Make sure that all the domains are in the same forest. In this case, Workspace ONE UEM automatically changes the port setting to 3268 for global catalog. You may choose to change the port setting to 3269 for SSL encrypted traffic, or override it completely by entering a separate port.</p>
<b>Is there a trust relationship between all domains?</b>	<p>This setting is available only when you have more than one domain added.</p> <p>Select <b>Yes</b> if the binding account has permission to access other domains you have added. This added permission means that the binding account can successfully log in from more domains.</p>

The following options are available after selecting the **Advanced** section drop-down.

Setting	Description
<b>Advanced</b>	
<b>Search Subdomains</b>	Enable subdomain searching to find nested users. Leaving this option disabled can make searches faster and avoids network issues. However, users and groups located in subdomains under the base Domain Name (DN) are not identified.
<b>Connection Timeout</b>	Enter the LDAP connection timeout value (in seconds).
<b>Request Timeout</b>	Enter the LDAP query request timeout value (in seconds).
<b>Search without base DN</b>	Enable this option when using a global catalog and when you do not want to require a base DN to search for users and groups.
<b>Use Recursive OID at Enrollment</b>	Verify user group membership at the time of enrollment. As the system runs this feature at enrollment time, your performance may decrease with some directories.
<b>Use Recursive OID For Group Sync</b>	Verify user group membership at the time of Group synchronization.
<b>Object Identifier Data Type</b>	Select the unique identifier that never changes for a user or group. The options available are <b>Binary</b> and <b>String</b> . Typically, the Object Identifier is in a <b>Binary</b> format.
<b>Sort Control</b>	Option to enable sorting. If this option is disabled, it can make searches faster and you can avoid sync timeouts.

### Azure Active Directory

Select **Enabled** for **Use Azure AD for Identity Services** and follow the on-screen steps to setup integration with Azure Active Directory.

### SAML 2.0

The following Security Assertion Markup Language (SAML) options are available after selecting **Use SAML for Authentication**, and are only applicable if you are integrating with a SAML identity provider.

Setting	Description
<b>Enable SAML authentication For</b>	You have the choice of using SAML authentication for <b>Admin</b> , <b>Enrollment</b> , or <b>Self Service Portal</b> . UEM console administrators can select all three, or any combination of two, or select any one of the three components.

Setting	Description
<b>Use new SAML Authentication endpoint</b>	<p>A new SAML authentication endpoint has been created for end-user authentication (device enrollment and login to SSP). This authentication replaces the two dedicated enrollment and SSP endpoints with a single endpoint.</p> <p>While you may choose to keep your existing settings, Workspace ONE UEM suggests updating your SAML settings to take advantage of the new combined endpoint.</p> <p>If you want to use the new endpoint, enable this setting and save the page. Then use the <b>Export Service Provider Settings</b> to export the new metadata file and upload it to your IdP. Doing so establishes trust between the new endpoint and your IdP.</p>
<b>SAML 2.0</b>	
<b>Import Identity Provider Settings</b>	Upload a metadata file obtained from the identity provider. This file must be in Extensible Markup Language (XML) format.
<b>Service Provider (Workspace ONE UEM) ID</b>	Enter the Uniform Resource Identifier (URI) with which Workspace ONE UEM identifies itself to the identity provider. This string must match the ID that has been established as trusted by the identity provider.
<b>Identity Provider ID</b>	Enter the URI that the identity provider uses to identify itself. Workspace ONE UEM checks authentication responses to verify that the identity matches the ID provided here.
<b>REQUEST</b>	
<b>Request Binding Type</b>	Select the binding types of the request. The options include <b>Redirect</b> , <b>POST</b> , and <b>Artifact</b> .
<b>Identify Provider Single Sign On URL</b>	Enter the identity provider's Uniform Resource Locator (URL) that Workspace ONE UEM uses to send requests.
<b>NameID Format</b>	Enter the format in which the identity provider sends a NameID for an authenticated user. This value is not required as Workspace ONE UEM obtains the user name from the FriendlyName "uid" required attribute.
<b>Authentication Request Security</b>	Select from the dropdown whether or not the Service Provider (Workspace ONE UEM) signs the authentication requests. You can select <b>None</b> , <b>Sign Authentication Requests (SHA1)</b> , and <b>Sign Authentication Requests (SHA256)</b> . Consider selecting Sign Authentication Requests (SHA256) for a more secure authentication.
<b>RESPONSE</b>	
<b>Response Binding Type</b>	Select the binding types of the response. The options include <b>Redirect</b> , <b>POST</b> , and <b>Artifact</b> .
<b>Sp Assertion URL</b>	Enter the Workspace ONE UEM URL that the identity provider configures to direct its authentication responses. "Assertions" regarding the authenticated user are included in success responses from the identity provider.
<b>Authentication Response Security</b>	This value specifies whether the IdP signs the response. You can select between <b>None</b> , <b>Validate Response Signatures</b> , and <b>Validate Assertions Signatures</b> . Consider selecting Validate Response Signatures for a more secure authentication.
<b>CERTIFICATE</b>	

Setting	Description
<b>Identity Provider Certificate</b>	Upload the identity provider certificate.
<b>Service Provider (AirWatch) Certificate</b>	Upload the service provider certificate.
<b>Export Service Provider Settings</b> button	Exports the metadata file for uploading to your Identity Provider (IdP). This setting establishes trust between the new SAML endpoint (for enrollment and SSP login) and your IdP.

## User Tab

Setting	Description
<b>User Object Class</b>	Enter the appropriate Object Class. In most cases, this value is "user."
<b>User Search Filter</b>	<p>Enter the search parameter used to associate user accounts with Active Directory accounts. The suggested format is "&lt;LDAPUserIdentifier&gt;={EnrollmentUser}" where &lt;LDAPUserIdentifier&gt; is the parameter used on the directory services server to identify the specific user.</p> <ul style="list-style-type: none"> <li>For AD servers, use "&amp;(objectCategory=person)(sAMAccountName={EnrollmentUser})" exactly.</li> <li>For other LDAP servers, use "CN={EnrollmentUser}" or "UID={EnrollmentUser}"</li> </ul>

## Advanced

Setting	Description
<b>Auto Merge</b>	Enable setting to allow user group updates from your directory service to merge with the associated users and groups in Workspace ONE UEM automatically.
<b>Automatically Set Disabled Users to Inactive</b>	<p>Select Enable to deactivate the associated user in Workspace ONE UEM when that user is disabled in your LDAP directory service (for example, Novell e-Directory).</p> <ul style="list-style-type: none"> <li><b>Value For Disabled Status</b> – Enter a numeric value and select the type of Lightweight Directory Access Protocol (LDAP) attribute used to represent a user’s status. Select “Flag Bit Match” if the user status is designated by a bitwise flag (which is the default for Active Directory).</li> </ul> <p>When “Flag Bit Match” is selected, if any bits from the property match the entered numeric value, then directory service considers the user to be disabled. This setting is only visible when the option <b>Automatically Set Disabled Users to Inactive</b> is checked.</p> <div style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;"> <p><b>Note:</b> If you select this option, then Workspace ONE UEM administrators set as inactive in your directory service are not able to log in to the Workspace ONE UEM console. In addition, enrolled devices assigned to users who are set as inactive in your directory service are automatically unenrolled.</p> </div>

Setting	Description
<b>Enable Custom Attributes</b>	Enable custom attributes. <b>Custom Attributes</b> is a section that appears under the main <b>Attribute – Mapping Value</b> table. You must scroll down to the bottom of the page to see the Custom Attributes.
<b>Attributes</b>	Review and edit the <b>Mapping Values</b> for the listed <b>Attributes</b> , if necessary. These columns show the mapping between Workspace ONE UEM user attributes (left) and your directory service attributes (right). By default these attributes are values most commonly used in Active Directory (AD). Update these mapping values to reflect the values used for your own or other directory service types.  If you add or remove a custom attribute, you should initiate a manual sync afterward by selecting the <b>Sync Attributes</b> button.
<b>Sync Attributes</b> button	Manually sync the attributes mapped here to the user records in Workspace ONE UEM. Attributes sync automatically on the time schedule configured for the Workspace ONE UEM environment.

## Group Tab

Setting	Description
<b>Group Object Class</b>	Enter the appropriate Object Class. In most cases this value should be <b>group</b> .
<b>Organizational Unit Object Class</b>	Enter the appropriate Organizational User Object Class.

## Show Advanced

Setting	Description
<b>Group Search Filter</b>	Enter the search parameter used to associate user groups with directory service accounts.
<b>Auto Sync Default</b>	Select this checkbox to automatically add or remove users in Workspace ONE UEM configured user groups based on their membership in your directory service.
<b>Auto Merge Default</b>	Select this check box to automatically apply sync changes without administrative approval.
<b>Maximum Allowable Changes</b>	Enter the number of maximum allowable group membership changes to be merged into Workspace ONE UEM. Any number of changes detected upon syncing with the directory service database under this number are automatically merged.  If the number of changes exceed this threshold, an administrator must manually approve the changes before they are applied. A single change is defined by a user either leaving or joining a group. A setting of 100 Maximum Allowable Changes means the Console does not need to sync with your directory service as much.
<b>Conditional Group Sync</b>	Enable this option to sync group attributes only after changes occur in Active Directory. Disable this option to sync group attributes regularly, regardless of changes in Active Directory.

Setting	Description
<b>Auto-Update Friendly Name</b>	When enabled, the friendly name is updated with group name changes made in active directory. When disabled, the friendly name can be customized so admins can tell the difference between user groups with identical common names. This can be useful if your implementation includes organizational unit (OU)-based user groups with the same common name.
<b>Attribute</b>	Review and edit the <b>Mapping Value</b> for the listed <b>Attribute</b> , if necessary. These columns show the mapping between Workspace ONE UEM user attributes (left) and your directory service attributes (right). By default these attributes are values most commonly used in AD. Update these mapping values to reflect the values used for your own or other directory service types.

- **Test Connection** – Click this button to test your connection with your directory service endpoint.
- **Launch Setup Wizard** – Click this button to launch the directory service setup wizard, which walks you through configuring DS integration.

## Limitations and Caveats

- No AD passwords are stored in the Workspace ONE UEM database with the exception of the Bind account password used to link directory services into your Workspace ONE UEM environment. That password is stored in encrypted form in the database and is not accessible from the console.  
Unique session keys are used for each sync connection to the Active Directory server.
- In some instances global catalogs are used to manage multiple domains or AD Forests. If you experience delays when searching for or authenticating users, this may be due to a complex directory structure. You can integrate directly with the global catalog to query multiple forests using one Lightweight Directory Access Protocol (LDAP) endpoint for better results.  
To do this, configure the following settings:
  - **Encryption Type** = None
  - **Port** = 3268
  - Verify that your firewall allows for this traffic on port 3268.

## System / Enterprise Integration / Email (SMTP)

The Simple Mail Transfer Protocol (SMTP) is a protocol for sending email messages between servers. Configure the settings on this page if you are using this protocol for sending emails from the Workspace ONE UEM console to the enrolled device users.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Server</b>	Enter the address of the SMTP server.
<b>Enable SSL</b>	Select to enable Secure Socket Layer security for the email communication.

Setting	Description
<b>Port</b>	Enter the port value. The default port for SMTP server is 25.
<b>Requires Credentials</b>	Select to enable basic authentication for sending outgoing mails. Then, enter the Username and Password of an account that has the permission to send outgoing mails in the applicable fields.
<b>Timeout in Seconds</b>	Enter the time (in seconds) that the Workspace ONE server awaits response from the SMTP server after which the session expires.
<b>Sender's Name</b>	Enter the display name for the outgoing mails.
<b>Sender's Email Address</b>	Enter email address for sending outgoing mails.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.
- **Test Connection** – Select this to check if Workspace ONE is able to communicate with the SMTP server that you have entered in the above field.

## System / Enterprise Integration / VMware Tunnel / Configuration

The VMware Tunnel settings page is used to configure the VMware Tunnel component. Note that if you already have EIS configured then you need to disable it by unchecking its check box on the EIS settings page.

## System / Enterprise Integration / Tunnel / Network Traffic Rules

The Network Traffic Rules settings page enables you to create traffic rules to control how the Per App Tunnel works on supported devices. The rules set on this page determine how the VMware Tunnel handles network traffic from configured Per App VPN mobile applications.

Traffic can be blocked from specified domains, tunneled through to your internal network, bypass your internal network, or directed to a proxy.

## System / Enterprise Integration / Third Party Proxies

The Third Party Proxies settings page lets you configure an F5 or standard proxy for VMware Tunnel Per-App Tunnel functionality.

- If adding a proxy for AirWatch App Tunnel, fill out your proxy server's details and applicable authentication mode / certificates.

## System / Enterprise Integration / Peer Distribution / Peer Distribution Software Setup

The Peer Distribution Software Setup settings page is used to download and configure the peer-to-peer server.

## System / Enterprise Integration /CDN/ Akamai

The CDN system settings pages lets on-premises customers enter account information for the available CDN providers. This feature is automatically configured for SaaS customers.

This feature lets end users in different regions download internal applications from the CDN server closest to them, as opposed to an internal file server located remotely. Benefits include increased download speeds for end users and reduced bandwidth for your Workspace ONE servers. This integration requires that you have an account with the applicable CDN provider. The values on this page can be retrieved by logging in to your CDN provider portal, locating the values, and enter them in this page. If you are an on-premises customer who requires additional assistance, contact Workspace ONE UEM Support.

## System / Enterprise Integration / Pull Service Installers

The Pull Service Installers setting page contains links to pull service installers that you can download and run for use in product provisioning. For more information about pull service installers and their function, please refer to one of the many Workspace ONE UEM product provisioning platform guides, which includes QNX, Windows Rugged, Android Rugged, Windows 7 and macOS.

## System / Enterprise Integration / SMS

Complete the fields on this page to enable Workspace ONE UEM to communicate using SMS with mobile devices for purposes such as user or device activation messages.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>SMS</b>	Select to enable Workspace ONE UEM to send short message service (SMS) messages to supported devices.
<b>Gateway Type</b>	Select the SMS Gateway you would like to use. Settings may change based on your selection. Not all settings are documented below.
<b>Nickname</b>	Enter the nickname for the SMS Gateway Account.
<b>Username</b>	Enter the username used to authenticate the sender with the SMS provider.
<b>Password</b>	Enter the password to complete the authentication of the sender with the SMS provider.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means

they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## System / Enterprise Integration / Syslog

The Syslog settings page lets you configure integration with a SIEM tool that leverages the syslog protocol to record system events.

Security Information and Event Management (SIEM) technology gathers information about security alerts generated by network hardware and software components. It centralizes this data and generates reports to help you monitor activity, perform log audits, and respond to incidents. Workspace ONE UEM integrates with your SIEM tools by sending event logs using Syslog.

### General Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Syslog Integration</b>	Enable or disable syslog integration.
<b>Host Name</b>	Enter the URL for the SIEM tool in the <b>Host Name</b> text box.
<b>Protocol</b>	Select the required protocol from available options to send the data . It is to be noted that support for TLS v1.1 is provided.
<b>Port</b>	Enter the port number to communicate with the SIEM tool in the <b>Port</b> text box.
<b>Syslog Facility</b>	Select the facility level for the feature from the <b>Syslog Facility</b> menu. The syslog protocol defines the syslog facility.  The widespread use and manipulation of the syslog protocol can clutter the meaning of the syslog facility. However, it can roughly suggest from what part of a system a message originated and it can help distinguish different classes of messages. Some administrators use the syslog facility in rules to route parts of messages to different log files.
<b>Message Tag</b>	Enter a descriptive tag to identify events from the Workspace ONE UEM console in the <b>Message Tag</b> text box. For example, "AirWatch".
<b>Message Content</b>	Enter the data to include in the transmission in the <b>Message Content</b> text box. This is how the message data gets formatted when sent using syslog to your SIEM tool. Use lookup values to set the content. For secure TCP, New line (CRLF) formatting using <i>Enter</i> , <i>\n</i> , <i>\r</i> does not work and gets automatically converted to <i>tab</i> , <i>\t</i> for secure TCP.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Advanced Tab

Setting	Description
<b>Console Events</b>	Select whether to enable or disable the reporting of Console events.
<b>Select Console Events to Send to Syslog</b>	<p>Visible if you enable Console Events. For each sub-heading, select the specific events that you want to trigger a message to syslog.</p> <p>Use <b>Select All</b> or <b>Clear All</b> to select or unselect all the events all at once. To select or unselect specific events, enable or disable the checkboxes.</p> <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;"> <p><b>Note:</b> On enabling the <b>Console Events</b>, by default, all events under all categories of console events are selected.</p> </div>
<b>Device Events</b>	Select whether to enable or disable the reporting of Device events.
<b>Select Device Events to Send to Syslog</b>	<p>Visible if you enable Device Events. For each sub-heading, select the specific events that you want to trigger a message to syslog.</p> <p>Use <b>Select All</b> or <b>Clear All</b> to select or unselect all the events all at once. To select or unselect specific events, enable or disable the checkboxes.</p> <div style="border: 1px solid #ccc; padding: 5px; margin-top: 10px;"> <p><b>Note:</b> On enabling the <b>Device Events</b>, by default, all events under all categories of device events are selected.</p> </div>

- **Test Connection** – Use the **Test Connection** button to ensure successful communication between the Workspace ONE UEM console and the SIEM tool.

## System / Enterprise Integration / Remote Management

The Remote Management settings page lets you configure the Remote Management Server. This page is only used during the setup of the Remote Management Server.

The Remote Management Setup wizard simplifies the setup process.

## System / Enterprise Integration / VMware Identity Manager

The VMware Identity Manager settings page is used to complete the VMware Identity Manager Configuration and Access Management.

### [Configuration](#)

### [Access Management](#)

## System / Enterprise Integration / VMware Identity Manager/ Configuration

The VMware Identity Manager configuration setting is used to configure directory integration settings between your Workspace ONE UEM instance and your Identity Manager instance. After binding the two together, Identity Manager can make API calls related to your directory service values. Workspace ONE UEM customers must first deploy VMware Enterprise Systems Connector and set up directory service integration within the Workspace ONE UEM console. Then, you can use this settings page to push your directory configuration to Identity Manager. This functionality does not allow for Workspace ONE UEM to receive directory changes from Identity Manager.

For more information about integrating Workspace ONE UEM with Identity Manager and deploying Workspace ONE with single sign-on to devices, see the Workspace ONE Quick Configuration Guide, available at <https://docs.vmware.com/en/VMware-Workspace-ONE/index.html>.

## System / Enterprise Integration / VMware Identity Manager/ Access Management

With Workspace ONE, you can easily control access to your catalog and applications. With VMware Identity Manager, you can configure authentication methods, identity provider instances, default access policy rules, and network ranges.

Every time a user attempts to log in, VMware Identity Manager evaluates the default access policy rules that you have set which determines the rules that must be applied. Authentication methods are always applied in the order that you have listed within the rule. The first identity provider instance that meets the authentication method and network range requirements of the rule is applied. The user authentication request is then forwarded to the identity provider instance for authentication. If the authentication fails, then the next configured authentication method in the rule is applied.

As an administrator, if you click **Access Management** without configuring the integration between the VMware Identity Manager and Workspace ONE UEM, you are prompted to complete the configuration.

Click **Configure** to initiate the configuration. The Access management screen allows you to configure the **Authentication Methods, Identity Providers, and Access Policies** in the VMware Identity Manger.

1. Click **Authentication Methods** to configure user authentication in VMware Identity Manager. For more information, see **Managing Authentication Methods to Apply to Users** in <https://docs.vmware.com/en/VMware-Identity-Manager/index.html>.
2. Click **Identity Providers** to associate the authentication methods to use in the built-in identity provider. For more information, see **Using Built-in Identity Providers** in <https://docs.vmware.com/en/VMware-Identity-Manager/index.html>.
3. Click **Access Policies** to provide secure access to the users apps portal and to start Web and desktop applications. For more information, see **Managing Access Policies** in <https://docs.vmware.com/en/VMware-Identity-Manager/index.html>.

**Note:** Workspace ONE UEM and VMware Identity Manager use password-grant work flow that allows access to VMware Identity Manager from Workspace ONE UEM with single sign-on (SSO). For more information, see [Single Sign-On to VMware Identity Manager from Workspace ONE UEM on page 20](#).

### Single Sign-On to VMware Identity Manager from Workspace ONE UEM

Workspace ONE UEM and VMware Identity Manager use password-grant work flow that allows access to VMware Identity Manager from Workspace ONE UEM with single sign-on (SSO).


The configuration settings are in VMware Identity Manager and not in Workspace ONE UEM. The exception to this process is configurations made in SaaS applications and access policies.

## Requirements

The admin must have administrative roles in both Workspace ONE UEM and VMware Identity Manager.

## Workflow

VMware Identity Manager and Workspace ONE UEM work in the back-end to authenticate the Workspace ONE UEM admin to VMware Identity Manager. Admins authenticate to Workspace ONE UEM with their usernames and passwords. This username and password triggers a request for an access token from VMware. After SSO is established, all configurations made in Workspace ONE UEM are stored in VMware Identity Manager.



## System / Security / Restricted Actions

The Restricted Actions settings page lets you configure security-minded settings related to the actions that administrators can perform in the Workspace ONE UEM console.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

## Send Message to All

- **Enabled** – Enable this setting to allow a System Administrator to send a message to all devices in your deployment from the Device List View.

## Password Protect Admins

You can require that certain actions require admins to enter a PIN. For each action you choose to protect, select the appropriate **Password Protect Actions** button for **Enabled** or **Disabled** as appropriate. This requirement provides you with granular control over which actions you want to make more secure.

**Note:** Some actions always require a PIN and as a result cannot be disabled. Denoted by \* below.

You can set the maximum number of failed attempts the system accepts before automatically logging out the session. If you reach the set number of attempts, you need to log into the Workspace ONE UEM console and set a new security PIN.

Setting	Description
<b>Admin Account Delete</b>	Prevents the deletion of an admin user account in <b>Accounts &gt; Administrators &gt; List View</b> .
<b>*Regenerate VMware Enterprise Systems Connector Certificate</b>	Prevents the regeneration of the VMware Enterprise Systems Connector certificate in <b>Groups &amp; Settings &gt; All Settings &gt; System &gt; Enterprise Integration &gt; VMware Enterprise Systems Connector</b> .
<b>*APNs Certificate Change</b>	Prevents the disabling of APNs for MDM in <b>Groups &amp; Settings &gt; All Settings &gt; Devices &amp; Users &gt; Apple &gt; APNs For MDM</b> .
<b>Application Delete/Deactivate/Retire</b>	Prevents the deletion, deactivation, or retirement of an application in <b>Apps &amp; Books &gt; Applications &gt; List View</b> .
<b>Content Delete/Deactivate</b>	Prevents the deletion or deactivation of a content file in <b>Content &gt; List View</b> .
<b>*Data Encryption Toggle</b>	Prevents the Encryption of user information setting in <b>Groups &amp; Settings &gt; All Settings &gt; System &gt; Security &gt; Data Security</b> .
<b>Device Delete</b>	Prevents the deletion of a device in <b>Devices &gt; List View</b> . Admin security PIN is still required for bulk actions even when this setting is disabled.
<b>*Device Wipe</b>	Prevents any attempt to perform a device wipe from the Device List View or Device Details screens.
<b>Enterprise Reset</b>	Prevents any attempt to perform an enterprise reset on a device from the <b>Devices Details</b> page of a Windows Rugged, Rugged Android, or QNX device.
<b>Enterprise Wipe</b>	Prevents any attempt to perform an enterprise wipe on a device from the <b>Devices Details</b> page of a device.
<b>Enterprise Wipe (Based on User Group Membership Toggle)</b>	Prevents any attempt to perform an enterprise wipe on a device when it is removed from a user group. This is an optional setting that you can configure under <b>Groups &amp; Settings &gt; All Settings &gt; Devices &amp; Users &gt; General &gt; Enrollment</b> on the <b>Restrictions</b> tab. If you <b>Restrict Enrollment to Configured Groups</b> on this tab, you then have the added option of performing an enterprise wipe a device when it is removed from a group.
<b>*Organization Group Delete</b>	Prevents any attempt to delete the current organization group from <b>Groups &amp; Settings &gt; Groups &gt; Organization Groups &gt; Organization Group Details</b> .
<b>Profile Delete/Deactivate</b>	Prevents any attempt to delete or deactivate a profile from <b>Devices &gt; Profiles &amp; Resources &gt; Profiles</b> .
<b>Provisioning Product Delete</b>	Prevents any attempt to delete a provisioning product from <b>Devices &gt; Staging &amp; Provisioning &gt; Products List View</b> .
<b>Revoke Certificate</b>	Prevents any attempt to revoke a certificate from <b>Devices &gt; Certificates &gt; List View</b> .
<b>*Secure Channel Certificate Clear</b>	Protects from any attempt to clear an existing secure channel certificate from <b>Groups &amp; Settings &gt; All Settings &gt; System &gt; Advanced &gt; Secure Channel Certificate</b> .
<b>User Account Delete</b>	Prevents any attempt to delete a user account from <b>Accounts &gt; Users &gt; List View</b> .
<b>Change in Privacy Settings</b>	Prevents any attempt to alter the privacy settings in <b>Groups &amp; Settings &gt; All Settings &gt; Devices &amp; Users &gt; General &gt; Privacy</b> .

Setting	Description
<b>Delete Telecom Plan</b>	Prevents the deletion of a telecom plan in <b>Telecom &gt; Plan List</b> .
<b>Override Job Log Level</b>	Prevents attempts to override the currently-selected job log level from <b>Groups &amp; Settings &gt; Admin &gt; Diagnostics &gt; Logging</b> . Overriding the Job Log Level is useful when a device or group of devices is having an issue. In this case, the admin can override those device settings by forcing an elevated log level to Verbose, which logs the maximum level of console activity, making it ideal for troubleshooting.
<b>*App Scan Vendor Reset/Toggle</b>	Prevents the resetting (and subsequent wiping) of your app scan integration settings. This action is performed in <b>Groups &amp; Settings &gt; All Settings &gt; Apps &gt; App Scan</b> .
<b>Shut Down</b>	Prevents any attempt to shut down the device in <b>Devices &gt; List View &gt; Device Details</b> .
<b>Maximum invalid PIN attempts</b>	Defines the maximum number of invalid attempts at entering a PIN before the console locks down. This setting must be between 1 and 5.

## Required Notes for Action

You can also require admins to enter notes using the **Require Notes** check box and explain their reasoning when performing these actions.

Setting	Description
<b>Lock Device</b>	Require a note for any attempt to lock a device from <b>Device List View</b> or <b>Device Details</b> .
<b>Lock SSO</b>	Require a note for any attempt to lock an SSO session from <b>Device List View</b> or <b>Device Details</b> .
<b>Device Wipe</b>	Require a note for any attempt to perform a device wipe from <b>Device List View</b> or <b>Device Details</b> .
<b>Enterprise Reset</b>	Require a note for any attempt to enterprise reset a device from the <b>Device Details</b> page of a Windows Rugged or Rugged Android device.
<b>Enterprise Wipe</b>	Require a note for any attempt to perform an enterprise wipe from <b>Device Details</b> .
<b>Override Job Log Level</b>	Require a note before attempts to override the default job log level from <b>Groups &amp; Settings &gt; Admin &gt; Diagnostics &gt; Logging</b> .
<b>Reboot Device</b>	Require a note before a reboot attempt from <b>Devices &gt; List View &gt; Device Details</b> .
<b>Shut Down</b>	Require a note before a shut down attempt from <b>Devices &gt; List View &gt; Device Details</b> .

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## System / Security / Data Security

The Data Security settings page lets you encrypt user information to further secure your user data, which includes an end user's first name, last name, email, and phone number. Enabling this feature limits some Workspace ONE UEM functionality, such as search, sort and filter. Consider the implications carefully before enabling this feature.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Encrypt User Information</b>	Select <b>Enabled</b> and then select each user data field you would like to encrypt. Encrypting a field means it will not display in other parts of the Workspace ONE UEM console. However, doing so also disables search, sort and filter on the items selected.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## System / Security / SSL Pinning

The SSL Pinning settings page is where you can add domains of Workspace ONE UEM Device Services and auxiliary components, which can help prevent man-in-the-middle (MITM) attacks by enabling an additional layer of trust between the listed hosts and devices. The certificates and domains you add here serve as a trusted form of validation that functions in addition to the standard certificate check a device performs against a Workspace ONE UEM component server. When devices establish sessions with your Workspace ONE UEM component servers, they also check the certificate against this stored certificate to guard against MITM attacks.

When you first navigate to this page, the Device Services site URL displays. However, no certificate data is present until you upload a certificate.

**Important:** The SSL pinning feature is only functional if it is used in conjunction with a Workspace ONE UEM application that supports certificate pinning.

Setting	Description
<b>On/Off</b>	Enable or disable pinning using this switch. If you turn pinning from on to off, it terminates all pinning at the current organization group and all the child organization groups underneath it.
<b>Upload (under Device Services)</b>	Select this button in the Device Services section of the page to add the Hostname and upload the certificate used for validation. If you have load-balanced Device Services servers, you also need to upload the certificates for each server. You will not see this button if you already have a device services certificate populated.
<b>Sync</b>	After uploading your Device Services certificate, you need to select <b>Sync</b> to initiate pinning. After, the sync status changes to a green color to indicate pinning was successful and the page should display your synced pin list.

Setting	Description
<b>Add Host (under auxiliary)</b>	Select to add auxiliary components other than Device Services that you also want to enable pinning for. On the Add Pinned Host dialog, enter the following: <ul style="list-style-type: none"> <li>• <b>Host</b> – Enter the fully qualified domain name of the host.</li> <li>• <b>Required</b> – Select to require the certificate pin to be pinned at all child organization groups and prevent it from being disabled or modified by child organization group administrators.</li> </ul>
<b>Upload (under auxiliary)</b>	Select to upload the certificate used for validation for each of your auxiliary components.

## System / Help

The Help settings page lets you configure the help settings for the Workspace ONE UEM console.

Setting	Description
<b>Enable Help</b>	Enable or disable the help icon to access help in the upper right corner of the UEM console.
<b>Help Skin Name</b>	The name of the help skin name. This value should be left as-is.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## System / Localization / Language Activation

The Language Activation page allows administrators to offer localized interaction with the Workspace ONE UEM console through the use of globalized message templates, EULAs and more. This allows administrators to offer a tailored, global experience to all of their users, regardless of language preference or location. Enable the desired languages, then assign it as the default locale of an organization group for all users to see content in that language by default.

## System / Localization / Localization Editor

The **Localization Editor** allows administrators to personalize UI text in the system to match internal word choice or regional preferences for all users.

Use the Override option to ensure that corporate language, such as specific technical operations or company structure, are displayed instead of default values in the Workspace ONE UEM console.

## System / Report Subscriptions

The **Report Subscriptions** system setting is simply a listing of the Reports you can subscribe to through the Hub. Navigate to the Report Listing using **Hub > Reports & Analytics > Reports > List View**.

When you select the **Subscribe** button  on one or more reports in the listing, you elect to receive this report daily, weekly, monthly, or just a single occurrence. You may also optionally include other email addresses in the subscription. Once you have subscribed to one or more reports in the **Hub**, you will be able to view these reports listed in **System > Reports & Alerts > Report Subscriptions**. You are also able to edit the subscription details such as:

- Organization Groups
- Date
- Recurrence
- Role
- User
- Optional Email Addresses
- Distribution List

## System / Terms of Use

The Terms of Use settings page lets you configure terms of use for the Workspace ONE UEM console, enrollment, and apps.

Ensure that all users with managed devices agree to the policy by defining and enforce terms of use (TOU). If necessary, users must accept the TOU before proceeding with enrollment, installing apps, or accessing the UEM console. The UEM console allows you to customize fully and assign a unique TOU to each organization group and child organization group.

## System / S/MIME

S/MIME (Secure Multi-Purpose Internet Mail Extensions) is a secure method of sending email. This protocol allows to encrypt emails and digitally sign them, thus allowing the receiver to be certain that the message received is exact and has been sent by a specific sender.



For more information about S/MIME encryption, see the following KB article: <https://support.airwatch.com/articles/115001675728>.

Configure the below settings to enable S/MIME and deploy it on devices through profiles.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Retain S/MIME Certificate</b>	Select to retain and enable S/MIME certificate deployment through the profile.
<b>Temporary S/MIME Retention Period (hours)</b>	Enter time (in hours) to retain the S/MIME certificate only for a limited duration.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## System / Advanced / Agent URLs

This page is used to specify your AirWatch Agent schema and default URLs referenced during the enrollment process to obtain the Agent. These settings typically do not need to be modified.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

### Public Store URLs

Setting	Description
<b>iOS Public App Store URL</b>	App Store URL that is used when downloading the iOS Agent during the enrollment process.
<b>Android Public App Store URL</b>	Google Play store URL that is used when downloading the Android Agent during the enrollment process.

### Agent Schema

Setting	Description
<b>iOS Agent Schema</b>	Handler used to identify the iOS Agent that will be opened during enrollment.
<b>Android Agent Schema</b>	Handler used to identify the Android Agent that will be opened during enrollment.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## System / Advanced / API / Event Notifications

The Event Notification setting page is used to configure the settings for event notifications to capture specific device-related events in real time. Workspace ONE UEM event notifications use HTTP URLs and the basic user method of authentication. Workspace ONE UEM supports notifications for specific events using Webhooks/Event Notification.

Webhooks are HTTP callbacks, sent to the URL of the user's choosing whenever the specified event occurs. The user provides the URL as the callback destination after subscribing to the particular event. Additionally, because callbacks are returned to the specified URL every time an applicable event occurs, the user does not need to regularly poll the server for event information.

Event notification are configured for the following events:

- Device Enrollment – Agent and Workspace
- Device Unenrolled Enterprise Wipe
- Device Wipe
- Device Compliance Status Change
- Device Compromised Status Change
- Device Attribute Change
  - Asset Number
  - Device Friendly Name
  - Organization Group
  - User Email Address
  - Ownership
  - Operating System
  - Phone Number
  - Device MCC

For more information on detailed configuration part, refer to **VMware AirWatch API Event Notification Guide**, available on docs.vmware.com.

## System / Advanced / API / REST

APIs require authentication to integrate with Workspace ONE UEM. Prior to authentication, API access must be enabled in the Workspace ONE UEM console. This page is used to configure the settings required for REST APIs.

### General Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Enable API Access</b>	Select Enable API Access for APIs to integrate with Workspace ONE UEM. APIs get authenticated (either basic authentication or directory authentication) to integrate Workspace ONE UEM only if this check box is enabled.

Setting	Description
<b>Add</b>	<p>Select <b>Add</b> to add/or generate multiple API keys.</p> <ul style="list-style-type: none"> <li>• <b>Service</b> – Enter one or multiple service(s) and generate their own independent API keys.</li> <li>• <b>Account Type</b> – Select the type of the account. To access Personal Content APIs (MCM APIs), select the Account type as <b>Enrollment User</b>.</li> <li>• <b>Description</b> – Enter short description for the service and generated API key.</li> <li>• <b>Whitelisted Domains</b> – Enter domains that can interact with Workspace ONE UEM APIs via API key.</li> </ul>

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Authentication Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Basic</b>	Select basic access for authentication using basic credentials (username and password). Credentials only exist in Workspace ONE UEM and do not necessarily match the existing corporate credentials. It requires no technical integration and no enterprise infrastructure.
<b>Certificates</b>	Certificate-based API authentication is utilized to provide the API access to the admin users. Utilizing this method, a self-signed, user-level API certificate must be generated from the Workspace ONE UEM console.
<b>Directory</b>	Select directory access of authentication if you want to integrate user and admin accounts of Workspace ONE UEM with existing corporate accounts. End users now authenticate with existing corporate credentials.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Advanced Tab

Setting	Description
<b>Server Throttling</b>	<p>Set the server bandwidth throttling (calls per minute). When server reaches the specified throttling limit, it offloads new requests and does not respond to them. The maximum value available is 50,000.</p> <p>If you set the calls-per-minute to 0, no API calls will connect.</p>
<b>Daily Quota</b>	<p>Set the number of API calls to be sent per day. The maximum value available is 2,000,000,000 (2 billion).</p> <p>If you set the calls-per-day to 0, no API calls will connect.</p>

## System / Advanced / API / SOAP

This page is used to configure the settings required for SOAP APIs.

Setting	Description
<b>Subject</b>	Enter the name of the individual , computer, device, or certificate authority to whom the certificate is issued.
<b>Thumbprint</b>	The thumbprint of API certificate.
<b>Date Issued</b>	The date certificate was last created.
<b>Clear Client Certificate</b>	Click to clear the existing certificate and its data.
<b>Export Client Certificate</b>	Click to download and store the certificate in <b>.P12</b> format.

## System / Advanced / Device Root Certificate

The Device Root Certificate settings page contains information for the certificate of the same name, which is used to authenticate SDK-enabled apps that require certificate-based authentication.

## System / Advanced / Secure Channel Certificate

The Secure Channel Certificate settings page lets you configure options related to the certificate of the same name.

For SaaS customers, the Secure Channel Certificate is configured by Workspace ONE UEM, so you do not need to install it from this page. You can configure the settings for blocking non-secure channel device access.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

### Block Non-Secure Channel Device Access

Select a check box next to each of the platforms with which you want to enforce communication with the Workspace ONE UEM console over a secure channel.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## System / Advanced / Service URLs

The **Service URLs** settings page is the place you define your Identity Management Provider (IdM) to Workspace ONE UEM.

The IdM describes the management of individual identities, their authentication, authorization, roles and privileges within or across system and enterprise boundaries with the goal of increasing security and productivity while decreasing cost, downtime, and repetitive tasks.

There can only be one IdM per organization group and when the **Override** setting is enabled, the Identity Management Provider for each nested OG in your Workspace ONE UEM deployment can be unique. This means you may have several IdMs to keep track of.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

## Identity Management Provider

Setting	Description
<b>Name</b>	Enter the name of the Identity Management Provider. This field is required.
<b>URL</b>	Enter the URL of the Identity Management Provider. This field is required.
<b>Username</b>	Enter the username with which the Identity Management Provider can identify you.
<b>Password</b>	Enter the password with which the Identity Management Provider will authenticate you.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## System / Advanced / Site URLs

The Site URLs settings page lists the endpoints of the various components that comprise the Workspace ONE UEM solution.

Typically, the settings on this page never change, and you should not alter them unless instructed to do so by Workspace ONE UEM.

Certain functionality, such as the Remote Tunnel Server for rugged devices and App Wrapping for your internal apps, can be enabled on this page.

## System / Advanced / Query String Authentication

The **Query String Authentication** system settings page lets you configure the settings that allow Workspace ONE UEM to communicate with the query string authentication provider. A query string authentication provider is a non-SAML service that allows users to log in to a web portal and from there select a web service or application and automatically be authenticated and signed in without having to re-enter their credentials.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Enable Query String Authentication</b>	Select to enable the feature.
<b>Parameter Name</b>	<p>Enter the query string parameter name in the Parameter Name field. This must be a single value – multiple parameter names are not supported. This is the value that Workspace ONE UEM uses to recognize the login request.</p> <p>This parameter name comes from your query string authentication provider. Consult your authentication provider for instructions on retrieving this information.</p>
<b>Session Validation URL</b>	Enter the URL of the query string authentication provider instance. It is used for session validation and administrator account details retrieval. If needed, you can include a port number for network traffic as part of the URL.

An example of the login request to the Workspace ONE UEM console would be:

`https://acme.mdm.com/login?<Parameter>=<session_ID>`, where `acme.mdm.com` is the URL of your UEM console, `<Parameter>` is the parameter name, and `<session_ID>` is the session ID passed from the query string authentication provider to Workspace ONE UEM for authentication.

# Chapter 3:

## Devices & Users

### General

- [Devices & Users / General / Enrollment on page 36](#)
- [Devices & Users / General / Friendly Name on page 44](#)
- [Devices & Users / General / Lookup Fields on page 44](#)
- [Devices & Users / General / Message Templates on page 45](#)
- [Devices & Users / General / Notifications on page 45](#)
- [Devices & Users / General / Privacy on page 46](#)
- [Devices & Users / General / Shared Device on page 47](#)
- [Devices & Users / General / Advanced on page 49](#)

### Android

- [Devices & Users / Android / Agent Settings on page 50](#)
- [Devices & Users / Android / Auto-Enrollment on page 55](#)
- [Devices & Users / Android / Android EMM Registration on page 56](#)
- [Devices & Users / Android / Service Applications on page 56](#)
- [Devices & Users / Android / Security on page 57](#)

### Apple

- [Devices & Users / Apple / APNs for MDM on page 58](#)

#### Apple iOS

- [Devices & Users / Apple / Apple iOS / APNs for Applications on page 58](#)
- [Devices & Users / Apple / Apple iOS / Agent Settings on page 58](#)
- [Devices & Users / Apple / Apple iOS / Managed Settings on page 60](#)

#### Apple macOS

- [Devices & Users / Apple / Apple macOS / Agent Application on page 61](#)
- [Devices & Users / Apple / Apple macOS / Agent Settings on page 62](#)
- [Devices & Users / Apple / Apple macOS / Software Management on page 63](#)
- [Devices & Users / Apple / AppleCare on page 64](#)

[Devices & Users / Apple / Automated Enrollment on page 64](#)

[Devices & Users / Apple / Device Enrollment Program on page 66](#)

[Devices & Users / Apple / MDM Sample Schedule on page 65](#)

[Devices & Users / Apple / Profiles on page 67](#)

[Devices & Users / Apple / SCEP on page 67](#)

[Devices & Users / Apple / Install Fonts on page 68](#)

[Devices & Users / Apple / Education on page 68](#)

[Devices & Users / Apple / VPP Managed Distribution on page 110](#)

## **QNX**

[Devices & Users / QNX / Agent Settings on page 72](#)

## **Tizen**

[Devices & Users / Tizen / Agent Settings on page 74](#)

## **Chrome OS**

[Devices & Users / Chrome OS / Agent Settings on page 75](#)

## **Windows**

[Devices & Users / Windows / Windows Auto-Discovery on page 75](#)

### **Windows Rugged**

[Devices & Users / Windows / Windows Rugged / Agent Application on page 76](#)

[Devices & Users / Windows / Windows Rugged / Agent Settings on page 77](#)

[Devices & Users / Windows / Windows Rugged / Power on Password on page 80](#)

[Devices & Users / Windows / Windows Rugged / Metrics on page 81](#)

[Devices & Users / Windows / Windows Rugged / Advanced on page 81](#)

### **Windows Phone**

[Devices & Users / Windows / Windows Phone / Agent Application on page 81](#)

[Devices & Users / Windows / Windows Phone / Agent Settings on page 82](#)

[Devices & Users / Windows / Windows Phone / Company Hub Settings on page 83](#)

[Devices & Users / Windows / Windows Phone / MDM Sample Schedule on page 84](#)

[Devices & Users / Windows / Windows Phone / Windows Health Attestation on page 85](#)

### **Windows 7**

[Devices & Users / Windows / Windows 7 / Agent Application on page 86](#)

[Devices & Users / Windows / Windows 7 / Agent Settings on page 87](#)

### **Windows Desktop**

[Devices & Users / Windows / Windows Desktop / General on page 88](#)

[Devices & Users / Windows / Windows Desktop / Agent Application on page 89](#)

[Devices & Users / Windows / Windows Desktop / Agent Settings on page 89](#)

[Devices & Users / Windows / Windows Desktop / App Deployments on page 91](#)

[Devices & Users / Windows / Windows Desktop / Enterprise Apps on page 92](#)

[Devices & Users / Windows / Windows Desktop / Windows Sample Schedule on page 92](#)

[Devices & Users / Windows / Windows Desktop / Windows Health Attestation on page 93](#)

[Devices & Users / Windows / Windows Desktop / Staging & Provisioning on page 95](#)

## Peripherals

[Devices & Users / Peripherals / Server on page 95](#)

[Devices & Users / Peripherals / Sample Schedule on page 95](#)

## Advanced

[Devices & Users / Advanced / Bulk Management on page 95](#)

[Devices & Users / Advanced / Custom Fields on page 96](#)

[Devices & Users / Advanced / Device Groups on page 97](#)

[Devices & Users / Advanced / Area on page 97](#)

[Devices & Users / Advanced / Tags on page 97](#)

[Devices & Users / Advanced / User Migration on page 98](#)

[Devices & Users / Advanced / User Categories on page 97](#)

[Devices & Users / Advanced / Unmanaged Wipe Protection on page 1](#)

[Devices & Users / Advanced / Managed Device Wipe Protection on page 98](#)

[Devices & Users / Advanced / Profile Options on page 99](#)

## Devices & Users / General / Enrollment

The Enrollment settings page lets you configure several options related to device and user enrollment. It is divided into several tabs, which are detailed below.

### Authentication Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Add Email Domain</b>	This button is used for setting up the Auto-Discovery Service to register email domains to your environment.
<b>Authentication Mode(s)</b>	Select the allowed authentication types, which include: <ul style="list-style-type: none"> <li>• <b>Basic</b> – Basic user accounts (ones you create manually in the UEM console) can enroll.</li> <li>• <b>Directory</b> – Directory user accounts (ones that you have imported or allowed using directory service integration) can enroll. Workspace ONE Direct Enrollment supports Directory users with or without SAML.</li> <li>• <b>Authentication Proxy</b> – Allows users to enroll using Authentication Proxy user accounts. Users authenticate to a web endpoint.</li> </ul>
<b>Devices Enrollment Mode</b>	Select the preferred device enrollment mode, which includes: <ul style="list-style-type: none"> <li>• <b>Open Enrollment</b> – Essentially allows anyone meeting the other enrollment criteria (authentication mode, restrictions, and so on) to enroll. Workspace ONE Direct Enrollment supports open enrollment.</li> <li>• <b>Registered Devices Only</b> – Only allowed users to enroll using devices you or they have registered. Device registration is the process of adding corporate devices to the UEM console before they are enrolled. For more information on registering devices, refer to the Enrollment section of the <b>VMware Workspace ONE UEM Mobile Device Management Guide</b>. Workspace ONE Direct Enrollment supports allowing only registered devices to enroll but only if registration tokens are not required.</li> </ul>
<b>Require Registration Token</b>	Visible only when <b>Registered Devices Only</b> is selected.  If you restrict enrollment to registered devices only, you also have the option of requiring a registration token to be used for enrollment. This increases security by confirming that a particular user is authorized to enroll. You can send an email or SMS message with the enrollment token attached to users with Workspace ONE UEM accounts.
<b>Require Agent Enrollment for iOS</b>	Select this check box to require iOS device users to download and install the Agent before they can enroll.

Setting	Description
<b>Require Agent Enrollment for macOS</b>	Select this check box to require macOS device users to download and install the Agent before they can enroll.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Terms of Use Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Require Enrollment Terms of Use Acceptance</b>	Require that end users accept an end user license agreement (terms of service) at some point during the enrollment process. Terms of use is fully supported by Workspace ONE Direct Enrollment.
<b>Add New Enrollment Terms of Use</b>	Click this button to open the Terms of Use dialog, where you can quickly create a custom enrollment terms of use message.  For more information on creating an enrollment terms of use, see the Terms of Use section of the <b>VMware AirWatch Mobile Device Management Guide</b> , available on docs.vmware.com.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Grouping Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Group ID Assignment Mode</b>	<p>Workspace ONE Direct Enrollment supports all assignment modes.</p> <ul style="list-style-type: none"> <li>• <b>Default</b> – Select this option if users are provided with Group IDs for enrollment. The Group ID used determines what organization group the user is assigned to.</li> <li>• <b>Prompt User to Select Group ID</b> – Enable this option to allow directory service users to select a Group ID from a list upon enrollment. The <b>Group ID Assignment</b> section lists available organization groups and their associated Group IDs. This listing does not require you to perform group assignment mapping, but does mean users have the potential to select an incorrect Group ID.</li> <li>• <b>Automatically Select Based on User Group</b> – This option only applies if you are integrating with user groups. Enable this option to ensure that users are automatically assigned to organization groups based on their directory service group assignments.</li> </ul> <p>The <b>Group Assignment Settings</b> section lists all the organization groups for the environment and their associated directory service user groups.</p> <p>Select the <b>Edit Group Assignment</b> button to modify the organization group/user group associations and set the rank of precedence each group has.</p> <p>For example, you have three groups, Executive, Sales, and Global, which are ranked in order of job role. Everyone is a member of Global, so if you were to rank that user group first, it puts all your users into a single organization group.</p> <p>Instead, if you rank Executives first, you ensure the small number of people belonging to that group are placed in their own organization group. Then rank Sales second, and you ensure that all Sales employees are placed in an organization group specific to sales. Rank Global last and anyone not already assigned to a group is placed in a separate organization group.</p>

#### Default

Setting	Description
<b>Default Device Ownership</b>	<p>Select the default Device Ownership of devices enrollment into the current organization group.</p> <p>Workspace ONE Direct Enrollment supports setting a default device ownership.</p>
<b>Default Role</b>	<p>Select the default roles assigned to users at the current organization group, which can affect access to the Self-Service Portal.</p> <p>Workspace ONE Direct Enrollment supports setting a default role.</p>
<b>Default Action for Inactive Users</b>	<p>Select the default action that impacts Active Directory users if their devices become inactive.</p> <p>Workspace ONE Direct Enrollment supports setting a default action for inactive users.</p>

### User Group Sync

Setting	Description
<b>Sync User Groups in Real Time for Workspace ONE</b>	<p>Workspace ONE can sync user groups for a given user as they register with the UEM console. Enabled by default, this feature is most effective when user groups are being used with great frequency for app assignment, profile assignment, policy assignment, or user mapping.</p> <p>This feature is CPU-intensive so unless your use case is similar to the above, disable this setting for improved performance and to prevent latency issues while launching the Workspace ONE application.</p>

### User Role Mapping

Setting	Description
<b>Enable Directory Group-Based Mapping</b>	<p>Select this box to enable ranked assignments that link a directory user group to a specific Workspace ONE UEM role. Users belonging to a particular group are assigned the associated roles. If they belong to more than one group, they take the highest ranked pairing.</p> <p>You can edit the order in which role-infused user groups are ranked by selecting the <b>Edit assignment</b> button.</p> <p>Workspace ONE Direct Enrollment supports directory group-based mapping.</p>

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

### Restrictions Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

## Enrollment Restrictions

Setting	Description
<b>User Access Control</b>	<p>All user access control options are supported by Workspace ONE Direct Enrollment.</p> <p><b>Restrict Enrollment to Known Users</b> – Enable to restrict enrollment only to users that already exist in the UEM console. This applies to directory users you manually added to the UEM console one by one or through batch import. It can also be used to lock down enrollment after an initial deployment that allowed anyone to enroll. This enables you to selectively allow users to enroll.</p> <p>Disable this option to allow all directory users who do not already exist in the UEM console to enroll into Workspace ONE UEM. User accounts are automatically created during enrollment.</p> <p><b>Restrict Enrollment to Configured Groups</b> – Enable to restrict enrollment and only allow users belonging to All Groups or Selected Groups (if you have integrated with user groups) to enroll devices. You should not select this option if you have not integrated with your directory services user groups.</p> <p>Disable this option to allow all directory users to create new Workspace ONE UEM user accounts during enrollment. In addition, you can select the <b>Enterprise Wipe devices of users that are removed from configured groups</b> option to automatically enterprise wipe any devices <b>not</b> belonging to any user group (if <b>All Groups</b> is selected) or a particular user group (if <b>Selected Groups</b> is selected).</p> <p>One option for integrating with user groups is to create an "MDM Approved" directory service group, import it to Workspace ONE UEM, then add existing directory service user groups to the "MDM Approved" group as they become eligible for Workspace ONE UEM.</p>
<b>Set limit for maximum enrolled devices at this OG and below</b>	<p>Enable and <b>Enter Device Limit</b> to limit the number of devices allowed to enroll in the current organization group (OG).</p> <p>Setting a maximum enrolled devices is supported by Workspace ONE Direct Enrollment.</p>

## Policy Settings

- **Add Policy** – Click this button to add an enrollment restriction policy, which lets you define allowed ownership types, enrollment types, device limits, and more.

Setting	Description
<b>Enrollment Restriction Policy Name</b>	Enter a name for your enrollment restriction policy.
<b>Organization Group</b>	Choose an organization group from the drop-down field. This is the OG to which your new enrollment restriction policy applies.
<b>Policy Type</b>	Select the type of enrollment restriction policy, which can be either <b>Organization Group Default</b> to apply to the selected organization group, or <b>User Group Policy</b> for specific User Groups through Group Assignment Settings on the <b>Restrictions</b> tab.

Setting	Description
<b>Allowed Ownership Types</b>	Choose whether to permit or prevent <b>Corporate - Dedicated, Corporate - Shared, and Employee Owned</b> devices. Workspace ONE Direct Enrollment only supports the ownership types Corporate Dedicated and Employee Owned.
<b>Allowed Enrollment Types</b>	Choose whether to permit or prevent the enrollment of devices using <b>MDM (AirWatch Agent)</b> and <b>AirWatch Container</b> (for iOS/Android) apps.
<b>Device Limit per User</b>	Select <b>Unlimited</b> to allow users to enroll as many devices as they want. Setting a device limit per user is supported by Workspace ONE Direct Enrollment. Uncheck this box to enter values for the <b>Device Limit Per User</b> section, to define the maximum number of devices per ownership type. <ul style="list-style-type: none"> <li>○ <b>Maximum Devices Per User</b></li> <li>○ <b>Corporate Max Devices</b></li> <li>○ <b>Shared Max Devices</b></li> <li>○ <b>Employee Owned Max Devices</b></li> </ul>
<b>Allowed Device Types</b>	Select the <b>Limit enrollment to specific platforms, models or operating systems</b> checkbox to add additional device-specific restrictions. This option is supported by Workspace ONE Direct Enrollment.
<b>Device Level Restrictions Mode</b>	This field is only available if <b>Limit enrollment to specific platforms, models or operating systems</b> is selected in the <b>Allowed Device Types</b> field. Determine the kind of device limitations you should have. <ul style="list-style-type: none"> <li>○ <b>Only allow listed device types (Whitelist)</b> – Select this option to explicitly allow only devices matching the parameters you enter and to block everything else.</li> <li>○ <b>Block listed device types (Blacklist)</b> – Select this option to explicitly block devices matching the parameters you enter and to allow everything else.</li> </ul> <p>For either device-level restrictions mode, select <b>Add Device Restriction</b> to choose a <b>Platform, Model, Manufacturer</b> (specific to Android devices), <b>Operating System</b>, or <b>Enterprise Version</b>. You may also add a <b>Device Limit</b> per defined device restriction. You may add multiple device restrictions.</p> <p>You can also block specific devices based on their IMEI, Serial Number or UDID by navigating to <b>Devices &gt; Lifecycle &gt; Enrollment Status</b> and selecting <b>Add</b>. This is an effective way to block a single device and prevent it from re-enrolling without affecting other users' devices. Preventing re-enrollment is also available as an option when performing an Enterprise Wipe.</p> <p>This option is supported by Workspace ONE Direct Enrollment.</p>

### Management Requirements for Workspace ONE

**Require MDM for Workspace ONE** - Enable this feature and set the applicable devices to receive an MDM profile and to get managed when they enroll through Workspace ONE.

## Group Assignment Settings

- **Edit Group Policies** – This button enables you to configure ranked assignments that link a directory user group to a specific Workspace ONE UEM enrollment restriction policy. Users belonging to a particular group must adhere to the associated restriction policy. If they belong to more than one group they will take the highest ranked pairing.
- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Optional Prompt Tab

The optional prompt settings let you configure various prompts that you set to display or not display during device enrollment. These optional prompts are web-based and are therefore cross-platform unless otherwise specified.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Prompt for Device Ownership Type</b>	<p>You can prompt the end user to select their device ownership type. Otherwise, configure a default device ownership type for the current organization group.</p> <p>Workspace ONE Direct Enrollment supports prompting for device ownership type.</p>
<b>Display Welcome Message</b>	<p>You can display a welcome message for your users early in the device enrollment process. You can configure both the header and the body of this welcome message by navigating to <b>System &gt; Localization &gt; Localization Editor</b>. Next, select the labels 'EnrollmentWelcomeMessageHeader' and 'EnrollmentWelcomeMessageBody' respectively.</p>
<b>Display MDM Installation Message</b>	<p>You can display a message for your users during the device enrollment process. You can configure both the header and the body of this MDM installation message by navigating to <b>System &gt; Localization &gt; Localization Editor</b>. Next, select the labels 'EnrollmentMdmInstallationMessageHeader' and 'EnrollmentMdmInstallationMessageBody' respectively.</p> <p>If you opt to customize your own header and body messages using the Localization Editor, you must opt to 'Override' in the <b>Current Setting</b> option. Doing so ensures that your customizations are used instead of the default messages.</p> <p>In addition to making one-off localization changes, you can also make localization changes in bulk by uploading an edited comma-separated values (CSV) file. Download this localization template CSV file by navigating to <b>System &gt; Localization &gt; Localization Editor</b> and select the <b>Modify</b> button. Edit the file per your preferences to affect bulk localization changes and upload it using the same screen.</p>
<b>Enable Enrollment Email Prompt</b>	<p>You can prompt the user to enter their email credentials during enrollment.</p> <p>The Enrollment Email Prompt requests the email address from the end user to populate that option in the user record automatically. This data is beneficial to organizations deploying email to devices using the {EmailAddress} lookup value.</p>

Setting	Description
<b>Enable Device Asset Number Prompt</b>	You can prompt the user to enter the device asset number during enrollment. Workspace ONE Direct Enrollment supports enrollment email prompts but only when <b>Prompt for Device Ownership Type</b> is enabled and only for Corporate Owned devices.
<b>Display Enrollment Transition Messages (Android Only)</b>	You can display or hide enrollment messages on Android devices.
<b>Enable TLS Mutual Auth for Windows</b>	You can force Windows Phone and Windows Devices to use endpoints secured by TLS Mutual Authentication which requires an extra setup and configuration. Contact Support for assistance.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Customization Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Use specific Message Template for each Platform</b>	Select this check box to use different enrollment message templates for the different platforms.  This option is supported by Workspace ONE Direct Enrollment.
<b>Enrollment Support Email</b>	Enter the contact email for MDM support which will be displayed to users during enrollment.
<b>Enrollment Support Phone</b>	Enter the contact phone number for MDM support which will be displayed to users during enrollment.
<b>Post-Enrollment Landing URL (iOS Only)</b>	Enter the URL of the webpage you want end users redirected to after they enroll their devices. This field can be blank.  This option is supported by Workspace ONE Direct Enrollment.
<b>MDM Profile Message (iOS Only)</b>	Enter the message you would like your users to see during the install MDM prompt. This field is optional and can be left blank.  This option is supported by Workspace ONE Direct Enrollment.
<b>Use Custom MDM Applications</b>	Configure MDM Apps by adding them as managed applications and assigning them to MDM application groups.  This option is supported by Workspace ONE Direct Enrollment.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / General / Friendly Name

The Friendly Name settings page lets you configure options related to device friendly names. The format you configure here is how devices will appear in the Workspace ONE UEM console.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Enable Custom Friendly Name</b>	Select this check box to enable the configuration of a custom device friendly name string.
<b>Device Friendly Name Format</b>	Enter the friendly name format using the lookup values provided in the insert lookup value list by selecting the plus icon.
<b>Set Device Name to Friendly Name</b>	Check this box to automatically set the device's actual Device Name to match the Friendly Name format you configured. Applicable only to supervised devices with iOS 8 or greater.

## Windows Rugged

Setting	Description
<b>Windows Mobile Friendly Name (Athena Agent Only)</b>	Enable to set the device friendly name for devices running the legacy Athena agent.
<b>Use Registry Entry for Friendly Name (AirWatch 4.0 Agent Only)</b>	Enable to use the Registry Entry instead of friendly names for devices using the AirWatch Agent v4.0+ for Windows Rugged. You must enter quotes (") around the registry path for this option to work. For example, "HKEY_LOCAL_MACHINE\System\Device Info\Asset Number" or "HKLM\System\Device Info\Asset Number".

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / General / Lookup Fields

The **Lookup Fields** settings page lets on-premises customers create custom lookup fields from existing pre-created standard lookup fields. These lookup fields can then be used throughout the Workspace ONE UEM console.

For example, you can configure a custom lookup field that consists of a user's initials. In this example, you would choose 'EmailUserName' for the **Standard Lookup Field**, then give it a **Name** like 'Initials', choose 'Regex Lookup' for the **Custom Type** and in **Regular Expression**, enter the regular expression code that extracts the first letters of the first and last names of your users. Depending on what the 'EmailUserName' field looks like, it might be (@"(\b[a-zA-Z])[a-zA-Z]\* ?").

All fields are required.

Setting	Description
<b>Standard Lookup Field</b>	Select from a list of pre-defined fields primarily used to identify either a user or a device.
<b>Name</b>	Enter the name of the customization.
<b>Description</b>	Enter a useful description of the customization to ease searching and record keeping.
<b>Allow Inheritance</b>	Allow your search to include inherited child organization groups.
<b>Custom Type</b>	Choose the mechanism of this customization, typically a regular expression (Regex).
<b>Regular Expression</b>	This field only appears when 'Regex' is chosen from the <b>Custom Type</b> field. A regular expression is a sequence of characters that forms a search pattern, mainly for use in pattern matching with strings, or string matching, i.e. "find and replace"-like operations.
<b>On Match</b>	Choose how the system should react when it discovers a match.



For a full list of standard lookup fields, see the following Knowledge Base article:  
<https://support.workspaceone.com/articles/115001663908>.

## Devices & Users / General / Message Templates

The Message Templates settings page lets you create and manage message templates for use within other areas of the Workspace ONE UEM console. You can create several types of message template, including those for enrollment, applications, compliance, and so on.

- Select **Add** to display the Add / Edit Message Template dialog.
- Select the **Edit**, **Delete**, or **View** icons for any given message template to take action on it.

## Devices & Users / General / Notifications

The Notifications settings page enables you to utilize Lifecycle Notifications, which can be configured to supply enrollment and unenrollment confirmation emails.

This optional setting can be configured by navigating to **Devices > Lifecycle > Settings > Notifications** and entering the following options for the following sections.

- **Device Unenrolled** – Send an email notification when a device unenrolls.
- **Device Enrolled Successfully** – Send an email notification when a device enrolls successfully.
- **Device Blocked by Enrollment Restriction** – Send an email notification if an enrollment restriction blocks a device, which can be configured by navigating to **Groups & Settings > All Settings > Devices & Users > General > Enrollment** and selecting the **Restrictions** tab.

Setting	Description
<b>Send Email To</b>	<ul style="list-style-type: none"> <li>• <b>None</b> – Send no confirmation email upon a successful device block, enrollment, or unenrollment.</li> <li>• <b>User</b> – Send a confirmation email to the device user informing them of the successful device block, enrollment, or unenrollment. <ul style="list-style-type: none"> <li>◦ <b>CC</b> – Send the same confirmation email to a single email address or multiple, comma-separated email addresses.</li> <li>◦ <b>Message Template</b> – Select the desired message template from the drop-down listing. You can add a new message template or edit an existing template by selecting the "Click here..." hyperlink that takes you to the <b>Devices &amp; Users &gt; General &gt; Message Templates</b> settings page.</li> </ul> </li> <li>• <b>Administrator</b> – Send a confirmation email to the Workspace ONE UEM administrator informing them of the successful device block, enrollment, or unenrollment. <ul style="list-style-type: none"> <li>◦ <b>To</b> – Send the same confirmation email to a single email address or multiple, comma-separated email addresses.</li> </ul> </li> </ul>

## Devices & Users / General / Privacy

The Privacy settings page lets you define how device and user information are handled in the Workspace ONE UEM console. This is particularly useful in bring your own device (BYOD) deployments.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.
- Select whether to **Collect and Display** (in the Console), **Collect and Do Not Display**, or **Do Not Collect** for the listed data.
- For the remote commands you want administrators to be able to perform, select whether to **Allow**, **Allow With User Permission**, or **Prevent**.

### Commands

For **Commands**, select whether the remote action will be available on **Corporate-Dedicated**, **Corporate-Shared**, **Employee Owned**, or **Unassigned** to devices.

These commands are available for Android and/or Windows Phone devices. The asterisk beside the command denotes which device.

## User Information

For **User Information**, select whether to **Display** or **Do Not Display** in the UEM console information for **First Name, Last Name, Phone Number, and Email Accounts**.

If a field is set to **Do Not Display**, then it displays as "Private" wherever it appears in the UEM console. This means you are not be able to search for fields you set to **Do Not Display**.

## Do Not Disturb

**Do Not Disturb Mode** – **Enable** or **Disable** this mode.

Do Not Disturb (DND) provides a clean and automated way to halt profile, content and application changes on enrolled devices for a set window of time directly from the UEM console. Integral MDM commands such as device wipe, enterprise wipe, and clear passcode still function when DND is enabled and the device is in DND mode.

DND mode is particularly useful for devices that are used or displayed in front of customers or guests. Admin messages, app updates and content changes may confuse end-users or disrupt demos and walkthroughs, so the ability to pause any changes allows uninterrupted usage. Once the Do Not Disturb period ends, all queued updates and commands are pushed down to the device automatically.



For more information about using Do Not Disturb Mode, see the following VMware Knowledge Base article: <https://support.air-watch.com/articles/115001662448>.

## User Friendly Privacy Notice

Enable this option to display a user-friendly privacy notice to your end-users after they enroll a device.

- Select to **Enable** or **Disable** the **User Friendly Privacy Notice** on the device.
  - When **Enabled**, you may choose **Yes** (display a privacy notice) or **No** (do not display a privacy notice) for each ownership level: **Employee Owned, Corporate - Dedicated, Corporate - Shared, and Unknown**. You must create a privacy notice before you assign ownership types to receive the notice.
- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / General / Shared Device

The Shared Device settings page lets you configure settings related to the shared device (multi-user) functionality of Workspace ONE UEM.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

## Grouping

Setting	Description
<b>Group Assignment Mode</b>	<p>Configure devices in one of three ways:</p> <ul style="list-style-type: none"> <li>• Select <b>Prompt User for Organization Group</b> to have the end user enter a Group ID for an organization group upon login. With this method, you have the flexibility to provide access to the settings, applications, and content of the organization group entered. Using this approach, an end user is not restricted to accessing only the settings, applications, and content for the organization group to which they are enrolled.</li> <li>• Select <b>Fixed Organization Group</b> to limit your managed devices to settings and content applicable to a single organization group. Each end user who logs in to a device has access to the same settings, applications, and content. This method can be beneficial in a retail use case where employees use shared devices for similar purposes such as checking inventory.</li> <li>• Select <b>User Group Organization Group</b> to enable features based on both user groups and organization groups across your hierarchy. When an end user logs in to a device, they have access to specific settings, applications, and content based on their assigned role within the hierarchy. For example, an end user is a member of the 'Sales' user group, and that user group is mapped to the 'Standard Access' organization group. When that end user logs in to the device, the device is configured with the settings, applications, and content available to the 'Standard Access' organization group.</li> </ul> <p>You can map user groups to organization groups on the UEM console. Navigate to <b>Groups &amp; Settings &gt; All Settings &gt; Devices &amp; Users &gt; General &gt; Enrollment</b>. Select the <b>Grouping</b> tab and fill in the required details.</p>
<b>Always Prompt for Terms of Use</b>	Prompts the end users to accept your <b>Terms of Use</b> agreement before they log in to a device.

## Security

Setting	Description
<b>Require Shared Device Passcode</b>	Require users to create a Shared Device passcode in the Self-Service Portal to check out devices. This passcode is different from a Single Sign On passcode or a device-level passcode.
<b>Require Special Characters</b>	Require special characters in the shared device passcode, which includes characters such as @, %, &, and so forth.
<b>Shared Device Passcode Minimum Length</b>	Set the minimum character length of the shared passcode.

Setting	Description
<b>Shared Device Passcode Expiration Time (days)</b>	Set the length of time (in days) the shared passcode expires.
<b>Keep Shared device Passcode for minimum time (days)</b>	Set the minimum amount of time (in days) the shared device passcode must be changed.
<b>Prompt users to change their Shared Device Passcode x (days) before expiration</b>	<b>(For iOS devices only)</b> Set the number of days the user is reminded to change their shared device passcode before it expires. For best results, set a value less than the difference between the Expiration Time and minimum time you can keep the Shared Device Passcode.
<b>Passcode History</b>	Set the number of passcodes that are remembered by the system, providing a more secure environment by preventing the user from reusing old passcodes.
<b>Auto Log out Enabled</b>	Configure an automatic log out after a specific time period.
<b>Auto Log out After</b>	Set the length of time that must elapse before the <b>Auto Log out</b> function activates in <b>Minutes, Hours, or Days</b> .
<b>Enable Single App Mode</b>	Select this check box to configure Single App Mode, which locks the device into a single application when an end user logs in to the device. To check out a device in Single App Mode, end users log in using their credentials. When the device is checked in again, it returns to Single App Mode. Enabling Single App Mode also disables the Home button on the device.  <b>Note:</b> Single App Mode applies only to Supervised iOS devices.
<b>Clear Device Passcode on Logout (Android Only)</b>	This setting controls whether the current device passcode is cleared when the user logs out (checks in) a multi-user shared device.
<b>Clear App Data on Logout (Android Only)</b>	Select this checkbox to clear the app data when the user logs out of a shared device (checks it in).

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / General / Advanced

The Advanced settings page under Devices & Users lets you configure settings related to how the Workspace ONE™ UEM console identifies and reports device activity.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Device Inactivity Timeout</b>	Enter the amount of time in minutes that a device not seen by the console will be identified as inactive.
<b>Display Expected Devices</b>	Enabling this option includes unenrolled devices in the device listing.
<b>Certificate Revocation Grace Period (hours)</b>	Enter the amount of time in hours after the discovery that a required certificate is missing from a device that the system shall wait before actually revoking the certificate. Given the vagaries of wireless technology and network bandwidth performance, this field is designed to prevent <i>false negatives</i> or times when a certificate is falsely identified as not existing on a device.
<b>Enrollment Session Timeout (min)</b>	Enter the amount of time in minutes that the system will force an enrollment restart after a user's enrollment session begins without completing.
<b>Device Assignment Rules</b>	Enables the use and assignment of IP address ranges as a grouping mechanism or device identifier.
<b>Enable Auth Proxy Body Response</b>	Legacy architecture designed to mimic the functionality of VMware Enterprise Systems Connector (VMware Enterprise Systems Connector) or EIS (Enterprise Integration Service).

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Android / Agent Settings

The Android Agent Settings page lets you configure various options that affect the Android Agent mobile app. Adjusting these intervals can impact battery life, with smaller values equating to more frequent pings and greater power consumption.

To access the Agent Settings navigate to **Groups & Settings > All Settings > Devices & Users > Android > Agent Settings**.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

## General

Setting	Description
<b>Heartbeat Interval (min)</b>	Enter the heartbeat time interval, which is how frequently the Agent checks in with the Workspace ONE UEM server. Reports beacon data to the Workspace ONE UEM console. The primary purpose of this report is to show compromised device status. However, beacon data also includes GPS, IP address and other minor data, such as model and OS version.
<b>Data Sample Interval (min)</b>	Enter the data sample time interval, which is how frequently the Agent collects data from the device. Collects interrogator data and reports all data collected by the Agent, including Telecom and Network data, as well as the battery, power and memory status.
<b>Data Transmit Interval (min)</b>	Enter the data transmit time interval, which is how frequently the Agent sends data to the Workspace ONE UEM server. Reports interrogator data to the Workspace ONE UEM console. This value should always be greater than the Data Sample Interval value.
<b>Profile Refresh Interval (min)</b>	Enter the profile refresh time interval, which is how frequently the device profile list for the device is refreshed on the Workspace ONE UEM server. Checks in with the Workspace ONE UEM console for profile updates or new profiles.
<b>Require Google Account</b>	Require a Google Account to leverage Google Cloud Messaging (GCM) to send remote commands to devices. Only deselect this option if you are utilizing AWCM.
<b>Require Phone Number</b>	Enable an additional prompt during enrollment. This phone number is recorded in Workspace ONE UEM to serve as a backup contact number in case devices are lost, turned off or do not have access to Internet.
<b>Block User Unenrollment</b>	Select this option to ensure end users cannot unenroll their devices.

## Application List

The Application List detects specific, blacklisted apps that are installed on a device, or detect all apps that are not whitelisted. You can either specifically prohibit certain apps, such as social media or entertainment apps, or specifically permit only the apps you specify, such as internal applications for business use.

Setting	Description
<b>Application List Interval (min)</b>	Enter the frequency at which the AirWatch Agent checks the application list.

## Internal Applications

Setting	Description
<b>Install Options</b>	Select how end users will be prompted to install new internal applications. You can provide a <b>Direct Prompt</b> , a <b>Status Bar Notification</b> , or opt to have <b>No Notification</b> .

## Samsung Knox

For more information about these settings or Samsung Knox in general, refer to the **VMware AirWatch Containerization with Samsung Knox Guide**.

Setting	Description
<b>Enable Containers</b>	Select <b>Enabled</b> to allow profile creation for Samsung Knox Containers and to allow the Android Agent to create application containers for Samsung Knox devices.
<b>Knox License Key</b>	Enter your Samsung Knox License Key.
<b>Enable Audit Logging</b>	<p>Select <b>Enabled</b> to turn on audit logging and the related settings below.</p> <p>The Workspace ONE UEM console has the ability to monitor errors that might prevent successful creation of the Knox container. The log provides the cause of the error and what needs to be resolved for successful Knox deployment.</p> <p>The audit logs are sent to the UEM console from the Knox enabled devices and stored in the Device Details page. The <b>Transmits Logs Automatically</b> setting determines the threshold at which the log file is reported to the device details.</p>
<b>Logging Level</b>	<p>Determines how severe an error has to be in order for it to be sent to the log file. The logging levels are listed in order of severity where notice is the least severe and alert is the highest.</p> <ul style="list-style-type: none"> <li>• <b>Alert</b></li> <li>• <b>Critical</b></li> <li>• <b>Error</b></li> <li>• <b>Warning</b></li> <li>• <b>Notice</b></li> </ul>
<b>Critical Log Size</b>	Enter a percentage (up to 70 percent) to define the critical log size. When the log file passes this percentage, a critical log size alert is sent to the admin.
<b>Maximum Log Size</b>	Enter a percentage (up to 90 percent) to define the maximum log size. When the log file passes this percentage, a maximum log size alert is sent to the admin.
<b>Full Log size</b>	Set to 97 percent by default. When the log file reaches this percentage, a full log size alert is sent to the admin and immediate action is required.
<b>Transmits Logs Automatically</b>	<p>Determines when the audit logs are to be transmitted to the console to notify the admins of errors.</p> <ul style="list-style-type: none"> <li>• <b>Never</b> – The log file will never be sent transmitted to the console.</li> <li>• <b>Critical</b> – The log file needs be at critical size to be transmitted to the console.</li> <li>• <b>Maximum</b> – The log file needs be at maximum size to be transmitted to the console.</li> <li>• <b>Full</b> – The log file needs be at full size to be transmitted to the console.</li> </ul>

## Location

Setting	Description
<b>Collect Location Data</b>	Select whether to collect location data from devices. Location is determined based on a device's Wi-Fi network. When it is available, it is reported to the Workspace ONE UEM console according to the Data Transmit Interval.
<b>Force GPS On</b>	Prevent the user from turning off GPS for certain devices.
<b>GPS Time Poll Interval (min)</b>	Enter the interval, in minutes, for which a time sample gets signaled. The minimum time is five minutes.

## Telecom

Enable specific Telecom settings like Call Logs, SMS Logs and Cellular Data Usage to allow logging and tracking of device use.

Setting	Description
<b>Enable Call Logs</b>	Collects information from incoming and outgoing phone calls made devices registered with Workspace ONE UEM.
<b>Enable SMS Logs</b>	Reports that log any incoming and outgoing SMS messages to devices.
<b>Enable Cellular Data Usage</b>	Allows the Workspace ONE UEM console to create reports which details data usage.

## Suspicious Activity Logs

When Suspicious Activity Log settings are enabled, devices will log every Bluetooth and USB connection that occurs except Bluetooth headsets and USB charging. To access Suspicious Activity Logs, Syslog settings must be correctly configured.

Setting	Description
<b>Bluetooth Connections</b>	Logs all bluetooth connections made except for Bluetooth headsets.
<b>USB Connections</b>	Logs all USB connections made except for USB charging ad USB headsets.

You must also enable Privacy and Location settings under **Devices & Users > General > Privacy** under the GPS section.

## AirWatch Cloud Messaging

AirWatch Cloud Messaging (AWCM) provides an internal communication solution for the entire Workspace ONE UEM solution as a comprehensive replacement for Google Cloud Messaging (GCM).

Setting	Description
<b>Use AWCM Instead of C2DM As Push Notification Service</b>	Set to <b>Enabled</b> to enable AWCM.

Setting	Description
<b>AWCM Client Deployment Type.</b>	Set to Always Running if you want the system and device have a constant and ongoing line of communication.
<b>AWCM Client Timeout Value (Mins)</b>	Determines how much idle time can pass before the client responds to the AWCM server.

## Remote Management

Remote Management allows you to directly control a device for troubleshooting or to ensure a device is properly provisioned.

Setting	Description
<b>Download Remote Control Cab</b>	Select this link to download the cabinet (CAB) installer file for Workspace ONE UEM Remote Management.
<b>Seek Permission</b>	<p>Enable Seek Permission if you want to prompt the end user to accept or decline the remote management request from the admin.</p> <ul style="list-style-type: none"> <li>Enter a <b>Seek Permission Message</b> that the end user sees when a remote request is sent.</li> <li>Enter the <b>Yes Caption</b> message for the accept button the end user sees on the Seek Permission request.</li> <li>Enter the <b>No Caption</b> message for the decline button the end user sees on the Seek Permission request.</li> </ul>
<b>Advanced</b>	
<b>Remote Management Port</b>	<p>Enter the port used to communicate between the Remote Management Agent and the Tunnel Agent on the end-user device.</p> <p>This port is responsible for caching the different frames on the device for use with the screen sharing function. The default port is 7775. Consider leaving the default setting unless port 7775 is in use for other uses in your organization.</p>
<b>Device Log Level</b>	Set the Device Log Level to control the verbosity of the remote management application on the device.
<b>Log Folder Path</b>	Define the Log Folder Path where the application saves the remote management log file on the device.
<b>Display Tray Icon</b>	Enable Display Tray Icon to show the remote management applet on the device.
<b>Max Sessions</b>	Enter the maximum number of concurrent sessions allowed on a device.
<b>Number of Retries</b>	Enter the number of retries allowed before communication attempts stop.
<b>Retry Frequency (Seconds)</b>	Enter the amount of time between attempts to communicate.

Setting	Description
<b>Heartbeat Interval (Seconds)</b>	Enter the amount of time (in seconds) that passes between status updates that are sent from the device.
<b>Connection Loss Retry Frequency (Seconds)</b>	Enter the amount of time (in seconds) that passes between attempts to reestablish the connection.

## Product Provisioning

- **Job Log Level** – A job occurs whenever files/actions are performed as part of product provisioning. With this setting, you can set the level of the job log level to meet your organization's logging level needs.

## SDK Profile

Enterprises can integrate any existing company specific apps with the use of an AirWatch Software Development Kit (SDK). Select which SDK profile to deploy to your devices by using the SDK Profile V2 option in the agent settings.

- **SDK Profile V2** – Select the profile that will provide the AirWatch Agent with the SDK settings configured for that organization group.
- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Android / Auto-Enrollment

Auto enrollment is only available for Intel devices are apart of the Intel World's Ahead Program. Currently, no other OEM will support this process. Please refer to the Android Device Enrollment section of the Android Platform Guide for information on enrolling all other devices.

The **Auto-Enrollment** settings page is used to enable automatic enrollment for Android devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Enable Auto-Enrollment</b>	Select <b>Enabled</b> to turn on auto-enrollment features for devices.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Android / Android EMM Registration

The Android settings page lets you configure the various options for integrating with Android prior to enrolling Android devices. Android configuration uses a wizard to help you set up the integration for devices.

### Configuration

The **Configuration** page shows Google Admin Console Settings and Google API settings after successful Android EMM registration.

### Enrollment Settings

Setting	Description
<b>Work Managed Enrollment Type</b>	Choose if devices should be associated with the enrollment user or device. When using paid apps, User Based is preferred for optimal license allocation and most BYOD use cases. For scenarios where a single user will not be associated with the device (such as Kiosks), Device Based is preferred.

### Enrollment Restrictions

Setting	Description
<b>Define the enrollment method for this Organization Group</b>	Select whether to <b>Always use Android</b> , or <b>Always Use Android (Legacy)</b> , <b>Define assignment group that use Android</b> . If you select <b>Define Assignment Group that use Android</b> , all unassigned devices default to use Android (Legacy).
<b>Assignment Groups</b>	Select a smart group from the drop-down menu. When a smart group(s) is selected, devices or users that do not belong to that group(s) will go through Android legacy enrollment (device administrator). Devices that belong to smart group will enroll in Work Profile or Work Managed assuming they support these enrollment modes

## Devices & Users / Android / Service Applications

Service Applications are apps downloaded in conjunction with the AirWatch Agent depending on a certain functionality needed by the customer. The two service apps deployed are the 'AirWatch Launcher' and 'Telecom Sampler'. This section will detail how to deploy these settings.

To access the Service Application settings navigate to: **Groups & Settings > All Settings > Devices & Users > Android > Service Applications**.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Require Service App</b>	Select to ensure end users get the Service App.
<b>Push Service App from Play Store</b>	Select to install the OEM service through the Google Play Store before or during enrollment. Pushing the Service App simplifies enrollment for your end users by removing the need to accept "unknown sources" during the enrollment process.
<b>Download Folder</b>	Provide a location for the file download. This option only appears if <b>Push Service App from Play Store</b> is disabled.
<b>Always use the Latest Version of Telecom Sampler</b>	Select to use latest or de-select to choose a specific <b>Telecom Sampler Version</b> .
<b>Telecom Sampler Version</b>	Select the desired Telecom Sampler version.
<b>Always use the Latest Version of AirWatch Launcher</b>	Select to use latest or de-select to choose a specific <b>AirWatch Launcher Version</b> .
<b>AirWatch Launcher Version</b>	Select the desired Launcher version.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Android / Security

The Security page adds additional security settings for Android devices to protect sensitive data from unauthorized access to the device database.

As part of the enrollment process, end users will create a passphrase code, which generates a key used to access the device database. When Key Encryption With User Input is enabled on the Security page and someone tries to access the database without that passphrase, access is denied. To enable this feature, Single Sign On must be enabled through the AirWatch SDK.

The passphrase requirements can be set to allow the end user to only enter the passphrase during enrollment for a one-time prompt by enabling **Allow Remember Authentication**.

**Important:** If you enable Allow Remember Authentication, this stores the user key on the device but renders the sensitive data vulnerable to unauthorized access.

**Note:** In order for the Agent for Android to share an application passcode or SSO session with other SDK apps, you must enable **Key Encryption with User Input**.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Key Encryption with User Input</b>	Allows the Agent to encrypt the sensitive data with a user-derived key. Enable this only when required.
<b>Allow Remember Authentication</b>	Enable to save the user-derived key on the device so it does not need to be entered each time.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / APNs for MDM

The APNs for MDM settings page lets you generate or upload your Apple Push Notification service (APNs) certificate, which is required to manage Apple devices. If you do not already have one, you can generate a new one on this page. If you do have one, you can upload it here.

 For more information, please see the **Generating and Renewing an APNs Certificate for Workspace ONE UEM** KB article: <https://support.air-watch.com/articles/115001662728>.

## Devices & Users / Apple / Apple iOS / APNs for Applications

The APNs for Applications page displays the APNs certificates that correspond to Workspace ONE UEM apps on the app store. These are required for sending push notifications to apps, and in most cases these are settings you should not alter unless instructed.

 For more information, please see the **Generating and Renewing an APNs Certificate for Workspace ONE UEM** KB article: <https://support.air-watch.com/articles/115001662728>.

## Devices & Users / Apple / Apple iOS / Agent Settings

The iOS Agent Settings page lets you configure various options that affect the iOS Agent mobile app.

### General Tab

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>General</b>	
<b>Disable Un-Enroll in Agent</b>	This setting disables the user's ability to unenroll from Workspace ONE UEM MDM using the Agent. This setting is only available in the AirWatch Agent v4.9.2 and higher.
<b>Background App Refresh</b>	<p>This setting tells the AirWatch Agent the maximum allowed time interval to refresh app content. Some applications run for a brief period before reaching a suspended state. Background App Refresh is a feature in iOS where the application itself wakes from this suspended state. During this refresh, the AirWatch Agent reports information, such as compromised detection, hardware details, GPS, iBeacon, and telecom, to the UEM console. The frequency at which the Agent refreshes is controlled by the OS and only completed during efficient times, such as when the device is plugged into a power source, frequency of use, or connected to Wi-Fi.</p> <p>To take advantage of the Background App Refresh feature, this setting must be enabled in the UEM console, the AirWatch Agent cannot be killed on the device, and Background App Refresh must be enabled on the device for the AirWatch Agent under <b>Settings &gt; General &gt; Background App Refresh</b>.</p>
<b>Minimum Refresh Interval</b>	Select the minimum amount of time that must pass before the device attempts to refresh app content.
<b>Transmit on Wi-Fi only</b>	Enable background refresh to occur over Wi-Fi connections only.
<b>Area</b>	
<b>Collect Location Data</b>	This setting enables the AirWatch Agent to collect GPS data from devices. Whether or not data is actually collected depends on the privacy settings set in <b>Devices &gt; Device Settings &gt; General &gt; Privacy</b> .
<b>Detect iBeacon Region</b>	This setting enables the AirWatch Agent to listen to iBeacon information in regions where the device is located.
<b>Telecom</b>	
<b>Collect Cellular Data Usage</b>	This setting enables the AirWatch Agent to collect cellular data use from devices. Whether or not data is actually collected depends on the privacy settings set in <b>Devices &gt; Device Settings &gt; General &gt; Privacy</b> .
<b>Self Service Setting</b>	
<b>Self Service Enabled</b>	This setting allows users to view their user account status, device compliance status, and assigned compliance policies from within the AirWatch Agent. If enabled, users can see if their devices are compliant.
 For more information about enabling users to sync their devices to check for compliance status, see the following Workspace ONE UEM Knowledge Base article: <a href="https://support.air-watch.com/articles/115001662408">https://support.air-watch.com/articles/115001662408</a> .	

Setting	Description
<b>SDK Profile</b>	
<b>SDK Profile (Legacy)</b>	This setting specifies the SDK profile you want to apply to the AirWatch Agent. SDK profiles can be used to enforce geofencing, create custom branding for the Agent and more.
SDK Profile V2	This setting specifies the SDK V2 profile you want to apply to the AirWatch Agent. SDK profiles can be used to enforce geofencing, create custom branding for the Agent and more.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Notification Tab

These notification settings ensure the AirWatch Agent can send push notifications.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

### Notification (iOS Only)

Use this tab to configure notifications that are sent to devices from the UEM console.

Setting	Description
<b>Application Type</b>	Choose to configure the AirWatch Agent either as a system app or an internal Workspace ONE UEM app to set system preferences. By default, the application type is set as System.
<b>Application Name</b>	Select an internal application from the drop-down menu. Ensure the Application Name appears the same way as it is does on the Internal List View page on the Apps & Books tab in the UEM console. Only internal applications with APNs certificates that were uploaded at the time the application was uploaded to the Console are seen here.
<b>Bundle ID</b>	This field is populated based on the selections above. This Bundle ID matches the application bundle ID that has been uploaded internally or selected from the drop-down menu.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / Apple iOS / Managed Settings

The iOS Managed Settings page lets you configure a few additional settings related to the AirWatch Agent and managing iOS devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

## Default Managed Settings

Setting	Description
<b>Apply Default Settings To</b>	Select which ownership types you want each of the default managed settings below to apply to.
<b>Voice Roaming</b>	Select the checkbox to allow voice roaming.
<b>Data Roaming</b>	Select the checkbox to allow data roaming.
<b>Personal Hotspot</b>	Select the checkbox to allow personal hotspot functionality.
<b>Activation Lock</b>	Select the checkbox to allow activation lock functionality.

## Default Wallpaper

Setting	Description
<b>Apply Default Settings To</b>	Select the ownership type(s) to which the following default managed settings are applied.
<b>Lock Screen Image</b>	Upload a lock screen image that displays when an end user locks their device.
<b>Home Screen Image</b>	Upload the home screen image that displays on the device.

## Organization Information

Send notifications or other MDM prompts with customized organization information.

Setting	Description
<b>Organization Name</b>	Enter the name of the organization.
<b>Organization Phone Number</b>	Enter the organization phone number.
<b>Organization Email</b>	Enter the organization email address.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / Apple macOS / Agent Application

The macOS Agent Application settings page lets you configure various options that affect the macOS Agent application.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Fully Qualified Path on local server to the Agent files for MAC devices</b>	This is the default location where the AirWatch Agent is stored on the local server. Only change this if needed.  If the file path is incorrectly defined, end users cannot download the Agent post-enrollment.
<b>Download Mac Agent Post Enrollment</b>	Select this checkbox to allow the agent to be downloaded post-enrollment by side-loading or from a web browser.
<b>Download Agent</b>	Use this button to download the latest version of the AirWatch Agent from the server.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / Apple macOS / Agent Settings

The macOS Agent Settings page lets you configure various options that affect the macOS Agent application. Use these settings to determine how often to collect data from devices, to allow passcode enforcement through Agent message prompts, to allow AirWatch Cloud Messaging so that devices receive push notifications and information about updates when available, and to choose how and when to allow updates.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>General</b>	
<b>Check-in Interval</b>	Enter the time interval for device check-in.
<b>Data Sample Interval</b>	Enter the time interval for sample data to be collected prior to transmission.
<b>Data Transmit Interval</b>	Enter the time interval for the device to automatically transmit data to Workspace ONE UEM.
<b>Administrative Passcode</b>	Enter a passcode to be applied to the app that the end user must enter to access Agent settings.
<b>Enable Agent Uninstall</b>	Select this check box to allow un-installation from the AirWatch Agent's main menu.

Setting	Description
<b>Location</b>	
<b>Collect Location Data</b>	Select this check box to enable Workspace ONE UEM to collect GPS information from the device when available.  If <b>Collect Location Data</b> is enabled, the end user receives a prompt to enable location services for <b>AirWatchid</b> . The alert persists until the user enables location services.
<b>Password Enforcement</b>	
<b>Enforce Passcode</b>	Select this check box to enforce passcode policy adherence on the device.
<b>AirWatch Cloud Messaging</b>	
<b>Use AWCM</b>	Select this check box to enable AWCM communication to the AirWatch Agent and device.
<b>Agent Updates</b>	
<b>Enable Automatic Updates</b>	Select this check box to enable automatic updates to the AirWatch Agent when a new version is available.
<b>Upgrade Silently</b>	Select this check box to run silent updates without interruption. If this check box is not selected, users will receive a prompt to begin the upgrade process.
<b>Remote Management</b>	
<b>Seek Permission</b>	Enable Seek Permission if you want to prompt the end user to accept or decline the remote management request from the admin. When you enable this setting, more options appear. <ul style="list-style-type: none"> <li>• Enter a <b>Seek Permission Message</b> that the end user will see when a remote request is sent.</li> <li>• Enter the <b>Yes Caption</b> message for the accept button the end user will see on the Seek Permission request.</li> <li>• Enter the <b>No Caption</b> message for the decline button the end user will see on the Seek Permission request.</li> </ul>

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / Apple macOS / Software Management

Use the macOS Software Distribution method to initiate the software management lifecycle for macOS applications.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Enable **Software Management**. At this point, make sure that you verify if the **File Storage** is enabled. If there is no file storage enabled, you are requested to enable it.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / AppleCare

Use the Apple Care settings page to manage options related to Workspace ONE UEM integration with AppleCare.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>GSX User ID</b>	Enter the account user ID.
<b>GSX Password</b>	Enter the account password.
<b>Sold-to Account Number</b>	Enter the 10-digit service account number. This account number can be found in the GSX portal at the bottom of the web page.
<b>Time Zone</b>	Use the drop-down menu to select the appropriate time zone.
<b>Language</b>	Use the drop-down menu to choose a language.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / Automated Enrollment

The Automated Enrollment settings page lets you create and export an MDM profile that you can then import into Apple Configurator when staging devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Enable Automated Enrollment</b>	Select this check box to display the staging settings you can configure.
<b>Platform</b>	Select which Apple platform this profile will be used for.

Setting	Description
<b>Staging Mode</b>	<p>Select the appropriate <b>Staging Mode</b> depending on how the device is going to be used and how the device must enroll. You can choose to pre-register devices and enroll using Apple Configurator. By pre-registering devices and selecting the None or Single User mode, you can pre-assign the end user for each device. However, you cannot pre-register Multi User devices.</p> <ul style="list-style-type: none"> <li>• <b>None</b> – Does not stage device for other users. For non-registered devices, all devices will be enrolled under the Default Enrollment User. In this case, only non-staging users are available as default staging user options.</li> </ul> <div style="border: 1px solid #ccc; padding: 10px; margin: 10px 0;"> <p><b>Important:</b> If you do not pre-register your devices and select <b>None</b> and specify a default enrollment user, then all devices that receive the .mobileconfig file will be enrolled to that user. To ensure devices are enrolled to distinct users, pre-register them to specific users or create a staging user account and select <b>Single User</b> as your <b>Staging Mode</b>.</p> </div> <ul style="list-style-type: none"> <li>• <b>Single User</b> – Stages device for a single, known or unknown user. Only staging users are available as Default Enrollment User options. When end users open the AirWatch Agent, they must enter credentials to fully enroll the staged device. At that time, the device details will update in the UEM console and the device is associated with that end user.</li> <li>• <b>Multi User</b> – Places device into Shared Device Mode. This stages the device for multiple, known or unknown users. Only staging users are available as Default Enrollment User options. When end users open the AirWatch Agent, they must enter credentials to check out the device for use.</li> </ul>
<b>Default Staging User</b>	Set a Default Staging user if you are using either the None or Single User staging modes.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / MDM Sample Schedule

The Apple MDM Sample Schedule settings page lets you configure the time intervals at which certain data samples from Apple devices are sent to the UEM console server.

 For more information about the settings on this page, refer to the following Workspace ONE UEM Knowledge Base article: <https://support.workspaceone.com/articles/115011401308>.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Device Information Sample</b>	Enter the frequency by which device information is refreshed on the Workspace ONE UEM server.
<b>Application List Sample</b>	Enter the frequency by which the application list is refreshed on the Workspace ONE UEM server.
<b>Certificate List Sample</b>	Enter the frequency by which the certificate list is refreshed on the Workspace ONE UEM server.
<b>Profile List Sample</b>	Enter the frequency by which the profile list is refreshed on the server.
<b>Provisioning Profile List Sample</b>	Enter the frequency by which the provisioning profile list is refreshed on the server. (iOS only)
<b>Restriction List Sample</b>	Enter the frequency by which the restrictions list is refreshed on the server. (iOS only)
<b>Security Information Sample</b>	Enter the frequency by which the security information is refreshed on the server.
<b>Managed App List Sample</b>	Enter the frequency by which the managed app list is refreshed on the server. (iOS only)
<b>Agent Sample</b>	Enter the frequency by which the scheduler determines how often a silent APNs is sent to the device to poll for compromised detection, data usage, and GPS, if these Agent settings are enabled for the device. This requires the AirWatch Agent 4.9 or higher and is only for iOS 7 or higher devices. (Reference macOS Agent Settings for information on macOS scheduling.)
<b>Non-Compliant Device Sample</b>	Enter the frequency by which Workspace ONE UEM queries non-compliant devices, to decrease the delay between when an end user takes actions to make their device compliant and when Workspace ONE UEM detects that action.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / Device Enrollment Program

The Device Enrollment Program settings page lets you configure DEP-based enrollment within Workspace ONE UEM. DEP settings can be configured at any Organization Group. A wizard displays when you initially configure the DEP Profile, which walks you through the setup process.

The specific steps are not mentioned here because they are included as part of a separate guide.

## Devices & Users / Apple / Profiles

The Apple profile page allows you to define security profile properties for your MDM profiles. You can optionally select to sign and encrypt profiles here. You can configure these settings during your initial set-up.

 For more information about SSL signing certificates, see the following Workspace ONE UEM Knowledge Base article: <https://support.workspaceone.com/articles/115001662348>.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Encrypt Profiles</b>	Select this checkbox to encrypt all MDM and device profiles that are installed on the devices.
<b>Sign Profiles (Requires Server SSL Certificate)</b>	Select this checkbox to sign MDM and device profiles with a SSL certificate that is used to establish trust with the device services server.
<b>Prompt devices to update MDM profile for iOS 5 Permissions</b>	This is a legacy setting used to provide compatibility with iOS 5. This checkbox does not need to be selected unless you are working with an iOS 5 device.
<b>Signing Certificate</b>	Use the <b>Upload</b> button to upload a third-party SSL certificate to sign the profile. The SSL certificate should be the same one used on the device services end point.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / SCEP

Use this page to configure settings for SCEP certificate enrollment on iOS devices. Select SCEP settings to retrieve a SCEP certificate instead of a self-signed enrollment certificate.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Use in Enrollment</b>	Select this checkbox to retrieve a SCEP certificate during enrollment instead of a regular enrollment certificate.
<b>SCEP Certificate Authority</b>	Select the certificate. If one is not available, go to <b>Groups and Settings &gt; All settings &gt; System &gt; Enterprise Integration &gt; Certificate Authorities</b> and follow the prompts to add a certificate.

Setting	Description
<b>SCEP Certificate Template</b>	Select the certificate template. If one is not available, go to <b>Groups and Settings &gt; All settings &gt; System &gt; Enterprise Integration &gt; Certificate Authorities &gt; Request Templates</b> and follow the prompts to add a certificate template.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Apple / Install Fonts

With the iOS Install Fonts settings, you can add fonts that you want to install on device.

Available to macOS Yosemite and devices running iOS 7 and higher, the UEM console provides a means to upload fonts and install them onto devices. Installing specific fonts allows users to view and read text that is not supported by standard means.

Compatible font file types include .ttf or .otf. There is no limit to the number of fonts you are can install on devices and you can remove a font at any time.

Drag a supported font file type (.ttf or .otf) onto the screen and select **Save**.

## Devices & Users / Apple / Education

The Apple Education page can be used to enable Apple Education functionality, which then allows for integration with Apple School Manager.

**Note:** This is functionality is only available to those with Workspace ONE UEM administrator roles and above.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	General
<b>Enable Education Features</b>	Select <b>Enable</b> to turn education functionality on.
<b>Class Source</b>	Select your Apple or Workspace ONE UEM as your Education functionality provider. Note that changing sources and saving the configuration will delete all existing classes.
<b>Set Maximum Resident Users</b>	Specify the maximum number of users each device's memory can support. This value divides the local storage on the iPad evenly for that number of users. If the number of users exceeds this setting, additional users' information is stored on iCloud instead of on the device.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Blackberry / Blackberry 10 / General

Specify your company's PowerShell information so that the Workspace ONE UEM console can use PowerShell commands to push profiles using the Exchange ActiveSync protocol.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>PowerShell URL</b>	Specify the URL where the UEM console can access your PowerShell service.
<b>Username</b>	Specify the username that UEM console needs to communicate with the PowerShell service.
<b>Password</b>	Specify the password for the user account.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Blackberry / Blackberry 10 / Agent Settings

The Blackberry 10 Agent Settings page lets you configure various options related to the Blackberry 10 Agent.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Heartbeat Interval (min)</b>	Enter the time interval by which the Agent will check in with the Workspace ONE UEM server.
<b>Data Sample Interval (min)</b>	Enter the time interval by which the Agent will collect data from the device.
<b>Profile Refresh Interval (min)</b>	Enter the time interval by which the device profile list is refreshed on the Workspace ONE UEM server.
<b>Administrative Passcode</b>	Enter the passcode that is required to access the Agent settings on the device.
<b>Enable GPS</b>	Select whether to enable the AirWatch Agent to collect GPS coordinates of the device.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means

they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Blackberry / Blackberry 10 / BES 10 Settings

The Blackberry 10 BES Settings page lets you configure options related to your BES 10 component. For more information about integrating with your BES, refer to the BES 10 Server Integration section in the **VMware AirWatch BlackBerry Platform Guide**, available on docs.vmware.com.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>BES URL</b>	Enter the URL for the BlackBerry Web Services that contains all the web service APIs used to synchronize the Workspace ONE UEM solution and the BES 10 server. The URL format is <i>https://&lt;BES_URL&gt;:38443</i> .
<b>BES Admin Username / Password</b>	Enter the username and password needed to authenticate with the BES 10 server in the <b>BES Admin Username</b> field and the <b>BES Admin Password</b> field.
<b>Authentication Method</b>	Ensure that the <b>Authentication Method</b> field is set to <b>Active Directory</b> or <b>BlackBerry Administration Service</b> .
<b>Domain</b>	Enter a domain for the BES 10 server in the <b>Domain</b> field.
<b>Ignore SSL Errors</b>	If you want to ignore Secure Socket Layer (SSL) certificate errors between Workspace ONE UEM component and the BES 10 server then select the <b>Ignore SSL Errors</b> checkbox.
<b>BES Sync Batch Size</b>	Enter a value in the <b>BES Sync Batch Size</b> field for the maximum size of the message to be sent from the BES 10 server through the Workspace ONE UEM console to the device.
<b>Activation Code Expiration</b>	Enter the number of hours in the <b>Activation Code Expiration</b> field for the amount of time the end user has to activate their BES 10 server.
<b>Message Type</b>	Select either the <b>Email</b> or <b>SMS</b> radio button to determine the method used to deliver the <b>BES Registration Message</b> .
<b>BES Registration Message</b>	Select from the <b>BES Registration Message</b> drop-down a message the end user receives upon registration.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Blackberry / Legacy Blackberry / Agent Application

The Legacy Blackberry Agent Application settings page lets you specify the fully qualified file path of the location on the Workspace ONE UEM console server where the AirWatch Agent is located so it can be installed on devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.
- **Fully qualified path on local server to the Agent files for Blackberry devices** – Enter the file path location of the AirWatch Agent in the **Download Path** field. The Workspace ONE UEM Server finds the AirWatch Agent at this location to install it on the device.
- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Blackberry / Legacy Blackberry / Agent Settings

The Legacy Blackberry Agent settings page lets you configure options related to the legacy Blackberry Agent.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Heartbeat Interval</b>	Set the time (in minutes) the agent waits before checking in with the Workspace ONE UEM console.
<b>Data Sample Interval</b>	Set the time (in minutes) the agent waits to collect data from the device.
<b>Profile Refresh Interval</b>	Set the frequency (in minutes) the profile list of each device will be refreshed on the server.
<b>Collect Location Data</b>	Set the AirWatch Agent to send GPS data to the UEM console.
<b>GPS Sample Interval</b>	Set the interval at which the AirWatch Agent collects sample GPS data for the device.
<b>Administrative Passcode</b>	Set the passcode needed to access the <b>Settings</b> area of the AirWatch Agent.
<b>Enable Branding</b>	Brand the AirWatch Agent with attributes specific to your company. Set the following applicable options: <ul style="list-style-type: none"> <li>• <b>Login Title Text</b> – Specify the text users view to log in to the AirWatch Agent.</li> <li>• <b>Toolbar</b> – Specify the color of the toolbar in the AirWatch Agent.</li> <li>• <b>Background</b> – Specify the background color of the AirWatch Agent.</li> <li>• <b>Background Image</b> – Set a specific image for the background of the AirWatch Agent.</li> <li>• <b>Company Logo</b> – Import your company logo in to the AirWatch Agent.</li> </ul>

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / BlackBerry / Legacy BlackBerry / BES Settings

The Legacy BlackBerry BES Settings page lets you configure options related to your BES component. For more information about integrating with your BES, refer to the BES 10 Server Integration section in the **BlackBerry Platform Guide**, available on docs.vmware.com.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>BWS URL</b>	Enter the URL for the BlackBerry Web Services that contains all the web service APIs used to synchronize the Workspace ONE UEM solution and the BES. The URL format is <code>https://&lt;BES_URL&gt;/enterprise/admin/ws</code> .
<b>BWS Util URL</b>	Enter the URL for the BlackBerry Web Services Utility that contains helper APIs used to form credentials for connecting to the BWS. The URL format is <code>https://&lt;BES_URL&gt;/enterprise/admin/util/ws</code> .
<b>BES Locale</b>	Enter the country location of the BES. For example, en_US.
<b>Authentication Method</b>	Ensure that the <b>Authentication Method</b> field is set to <b>Active Directory</b> .
<b>BES Username and Password</b>	Enter the username and password needed to authenticate with the BES in the <b>BES Username</b> field and the <b>BES Password</b> field.
<b>Domain</b>	Enter a domain for the BES in the <b>Domain</b> field.
<b>Organization ID</b>	Enter the applicable ID associated with the BES in the <b>Organization ID</b> field. This entry is typically <b>0</b> .
<b>Sync Applications</b>	Enable <b>Sync Applications</b> if you want to pull a list of applications from BlackBerry devices registered with the BES and <b>Save</b> the settings.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / QNX / Agent Settings

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

## General

Setting	Description
<b>Device ID Algorithm</b>	Set the unique device identification algorithm used on the device.
<b>Heartbeat Interval (min)</b>	Set the time (in minutes) the agent waits before checking-in with the Workspace ONE UEM console.
<b>Data Sample Interval (min)</b>	Set the time (in minutes) the agent waits to collect data from the device.
<b>Data Transmit Time Interval (min)</b>	Set the time (in minutes) the agent waits to send data to the UEM console.

## Application List

Setting	Description
<b>Applications Poll Interval (min)</b>	Set the time (in minutes) the agent waits to check for new applications.

## Certificate List

Setting	Description
<b>Certificates Poll Interval (min)</b>	Set the time (in minutes) the agent waits to check for new certificates.

## Remote Management

Setting	Description
<b>Mode</b>	<p>Select the Mode to define how the remote management applet and the device communicate over the network.</p> <ul style="list-style-type: none"> <li>• <b>Off</b> – Communication happens directly between the applet and the device. This mode is used when the computer that has the applet and the device you want to remotely manage are on the same network or virtual network.</li> <li>• <b>Inbound</b> – This is a legacy setting for the Remote Management Tunnel Server.</li> <li>• <b>Outbound</b> – This is a legacy setting for the Remote Management Tunnel Server.</li> <li>• <b>WebSocket</b> – Communication flows from the device to the applet. There is no direct connection available between the applet and the device. The applet and the device both proactively establish connections with the tunnel server. Use this when the device and the tunnel server are on different networks and the device can connect to the tunnel server on a public IP, for instance a device out in the field and the applet and tunnel located in a central location.</li> </ul>
<b>Enable Encryption</b>	Enable to encrypt the data sent during remote management with AES 128 bit encryption.
<b>Passphrase</b>	Enter a passphrase used for authentication between the applet and the AirWatch Agent.

Setting	Description
<b>Remote Management Port</b>	Enter the port used to communicate between the Remote Management Agent and the Tunnel Agent on the end user device.  This port is responsible for catching the different frames on the device for use with screen sharing. The default port is 7775 and should not be changed unless port 7775 is in use for other uses in your organization.
<b>Device Log Level</b>	Set the level of verbosity for the device logs when using the remote control application.
<b>Log Folder Path</b>	Enter the folder path for storing the device log.
<b>Max Sessions</b>	Enter the maximum number of sessions allowed through remote management.
<b>Number of Retries</b>	The number of retries allowed before communication attempts stop. This setting is available when <b>WebSocket</b> is selected as the <b>Mode</b> .
<b>Retry Frequency (Seconds)</b>	The amount of time between attempts to communicate. This setting is available when <b>WebSocket</b> is selected as the <b>Mode</b> .
<b>Heart Beat Interval (Seconds)</b>	The amount of time (in seconds) that passes between status updates are sent from the device. This setting is available when <b>WebSocket</b> is selected as the <b>Mode</b> .
<b>Connection Loss Retry Frequency (Seconds)</b>	The amount of time (in seconds) that passes between attempts to reestablish connection. This setting is available when <b>WebSocket</b> is selected as the <b>Mode</b> .

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Tizen / Agent Settings

The Tizen Agent Settings page lets you configure various options that affect the Tizen Agent mobile app. Adjusting these intervals can impact battery life, with smaller values equating to more frequent pings and greater power consumption.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Beacon Interval (min)</b>	Enter the heartbeat time interval, which is how frequently the Agent checks in with the Workspace ONE UEM server. Reports beacon data to the Workspace ONE UEM console.

Setting	Description
<b>Data Sample Interval (min)</b>	Enter the data sample time interval, which is how frequently the Agent collects data from the device.
<b>Data Transmit Interval (min)</b>	Enter the data transmit time interval, which is how frequently the Agent sends data to the AirWatch server.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Chrome OS / Agent Settings

The Chrome OS Agent Setting page lets you to configure the settings for the AirWatch Agent for Chrome OS devices.

To access the agent settings page, navigate to **Groups & Settings > All Settings > Devices & Users > Chrome OS > Agent Settings**.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Beacon Interval (min)</b>	Enter the time interval (in minutes) at which the agent will check in with the Workspace ONE UEM console.
<b>Data Sample Interval (min)</b>	Enter the time interval (in minutes) at which the agent will collect a data sample from the device.
<b>Data Transmit Interval (min)</b>	Enter the time interval (in minutes) at which the agent will transmit the collected data sample to the console.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Auto-Discovery

The Windows Auto-Discovery (WADS) settings page lets you set the type of WADS deployment you want to use and configure the related options. Windows Auto-Discovery is a service that allows users to enroll using only their email address and removes the need for end users to enter in a server address and a group identifier.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

**Auto-Discovery Mode** – Select whether to use an on-premises WADS solution or to use Workspace ONE UEM Cloud-Hosted WADS.

- **On-Premises**
  - **Download Windows Auto-Discovery Installer** – Select to download the installer for creating an on-premises WADS solution.
- **Cloud-Hosted**
  - **Register Domain for Windows Auto-Discovery** – Select to launch the domain registry wizard for configuring a cloud-hosted WADS solution.

## Devices & Users / Windows / Windows Rugged / Agent Application

The Windows Rugged Agent Application settings page lets you configure the options for downloading the specific AirWatch Agent for Windows Rugged devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Use Default Cab</b>	<p>Enable to use the default AirWatch Agent for Windows Rugged cab file available from the Workspace ONE UEM console. Disable this option to use custom cabs you upload.</p> <ul style="list-style-type: none"> <li>• <b>Fully qualified path on local server to the Agent files for Windows Rugged devices</b> – Enter the file path on the local server for the default cab if you enable the default cab.</li> </ul>
<b>Add Application</b>	<p>Select to upload a custom cab file to push to Windows Rugged devices.</p> <ul style="list-style-type: none"> <li>• <b>Platform</b> – Choose the cab file's specific OS. This option allows you to upload different cabs for different operating systems that your Windows Rugged devices use.</li> </ul>
<b>WM enrollment cab</b>	Select the custom cab you want to push to devices running Windows Mobile.
<b>CE enrollment cab</b>	Select the custom cab you want to push to ARM-based devices running Windows CE.
<b>x86 CE enrollment cab</b>	Select the custom cab you want to push to x86-based devices running Windows CE.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Rugged / Agent Settings

The Windows Rugged Agent Settings page lets you configure the options for the AirWatch Agent for Windows Rugged devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

### General

Setting	Description
<b>Device ID Algorithm</b>	Set the unique device identification algorithm used on the device. <ul style="list-style-type: none"> <li>• Device ID Algorithm 3 – Agent uses the OS-provided API to generate the UDID.</li> <li>• Device ID Algorithm 5 – Along with the OS-provided API, the agent uses the MAC ID of the device to generate the UDID.</li> <li>• Device ID Algorithm 6 – Together with the OS-provided API and the MAC ID of the device, the agent also uses the serial number of the device to generate the UDID.</li> </ul>
<b>Heartbeat Interval (min)</b>	Set the time (in minutes) the agent waits before checking in with the Workspace ONE UEM console.
<b>Data Sample Interval (min)</b>	Set the time (in minutes) the agent waits to collect data from the device.
<b>Data Transmit Time Interval (min)</b>	Set the time (in minutes) the agent waits to send data collected from the device to the UEM console.
<b>Check-In on Condition (Event)</b>	Enable to limit the agent to check-in or beacon to the UEM console only when certain conditions (Wi-Fi connection, AC Power, or NW Adapter) are met. This helps reduce bandwidth issues as devices typically meet the condition when they are stored for after hours.

### Shared Devices (Check-in / Check-out)

Setting	Description
<b>Enable Shared Device Mode</b>	Select this check box to enable shared device functionality. For more information, see the Windows Rugged Launcher Profile Overview.

## Notifications

Setting	Description
<b>Enable Agent Installation Complete Notification</b>	Select this check box to enable or disable notifications for Agent installation completion.
<b>Enable Product Install Status Notification</b>	Select this check box to enable or disable notifications through the Agent for product installation completion.

## Location

Setting	Description
<b>Collect Location Data</b>	Enable to allow the agent to determine the device location based on a device's Wi-Fi network. When available, the agent will report the location to the Workspace ONE UEM console using the Data Transmit Interval.

## Application List

Setting	Description
<b>Applications Poll Interval (min)</b>	Set the time interval (in minutes) at which the applications list for each device will refresh on the Workspace ONE UEM console.

## Certificate List

Setting	Description
<b>Certificate Poll Interval (min)</b>	Set the time interval at which the certificate list for each device will refresh on the Workspace ONE UEM console.

## Proxy

Setting	Description
<b>Proxy Configuration</b>	Enable to allow the configuration of a proxy settings.

## Application Manager Package Scheduler (Only for AirWatch 3.3 Agent)

These settings are for the legacy AirWatch Agent v3.3.

Use the **APPLICATION MANAGER SCHEDULER** to define a schedule for devices with the AirWatch Agent v3.3+ to retrieve products provisioned on schedule.

Setting	Description
<b>Add Application Manager Scheduler</b>	Select to create schedules for provisioning products using Products (Legacy).
<b>Application Manager Scheduler</b>	Select the hour the product begins to push to devices.

Setting	Description
<b>Randomization Window (min)</b>	Select the amount of time the product is pushed over. The order of devices is randomized.

## Remote Management

Setting	Description
<b>Download Remote Control Cab</b>	Select this link to download the cabinet (CAB) installer file for Workspace ONE UEM Remote Management.
<b>Seek Permission</b>	<p>Enable Seek Permission if you want to prompt the end user to accept or decline the remote management request from the admin.</p> <ul style="list-style-type: none"> <li>Enter a <b>Seek Permission Message</b> that the end user sees when a remote request is sent.</li> <li>Enter the <b>Yes Caption</b> message for the accept button the end user sees on the Seek Permission request.</li> <li>Enter the <b>No Caption</b> message for the decline button the end user sees on the Seek Permission request.</li> </ul>
<b>Advanced</b>	
<b>Remote Management Port</b>	<p>Enter the port used to communicate between the Remote Management Agent and the Tunnel Agent on the end-user device.</p> <p>This port is responsible for caching the different frames on the device for use with the screen sharing function. The default port is 7775. Consider leaving the default setting unless port 7775 is in use for other uses in your organization.</p>
<b>Device Log Level</b>	Set the Device Log Level to control the verbosity of the remote management application on the device.
<b>Log Folder Path</b>	Define the Log Folder Path where the application saves the remote management log file on the device.
<b>Display Tray Icon</b>	Enable Display Tray Icon to show the remote management applet on the device.
<b>Max Sessions</b>	Enter the maximum number of concurrent sessions allowed on a device.
<b>Number of Retries</b>	Enter the number of retries allowed before communication attempts stop.
<b>Retry Frequency (Seconds)</b>	Enter the amount of time between attempts to communicate.
<b>Heartbeat Interval (Seconds)</b>	Enter the amount of time (in seconds) that passes between status updates that are sent from the device.
<b>Connection Loss Retry Frequency (Seconds)</b>	Enter the amount of time (in seconds) that passes between attempts to reestablish the connection.

## Product Provisioning

Settings	Descriptions
<b>Job Log Level</b>	<p>Select the level of detail your job logs contain. You can choose between the following options.</p> <p><b>Error</b> – The log contains errors only. This setting produces the smallest amount of detail.</p> <p><b>Warning</b> – The log contains errors and all warnings.</p> <p><b>Information</b> – The log contains all errors, all warnings, and all supplemental information.</p> <p><b>Verbose</b> – The log contains all of the above plus the entire ledger of exchanges between the device and the server, no matter how trivial. Select this option for troubleshooting purposes. This option produces the largest log.</p>

## Wipe

Settings	Descriptions
<b>Retain Agent Executables After Enterprise Wipe</b>	Enable to keep the agent executable files after an enterprise wipe command is issued to the device.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Rugged / Power on Password

With the Windows Rugged Power On Password settings, you can configure the options for requiring a password on a device startup.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Force Password Expiration</b>	Enable this setting to force the password to expire so that the user must change the password.
<b>View Power On Password</b>	Enable this setting to allow the user to see the password that they enter.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Rugged / Metrics

The Windows Rugged Metrics settings page lets you configure the options for downloading the MotoDC metrics application as well as configure the metrics collected.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Download MotoDC</b>	Select to download the MotoDC cab to collect device metrics. You can set which metrics to collect below the download link.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Rugged / Advanced

The Windows Desktop Advanced settings page lets you configure the various advanced options for the AirWatch Agent for Windows Rugged.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Path to App Update</b>	Enter the default directory for app updates on devices.
<b>Intermec Reboot Exe</b>	Enter the default path to the reboot executable (Intermec Devices).

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Phone / Agent Application

The Windows Phone Agent Application settings page lets you configure the options for hosting the AirWatch Agent for Windows Phone devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Agent Download URL</b>	Enter the AirWatch Agent for Windows Phone download URL.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Phone / Agent Settings

The Windows Phone Agent Settings page lets you configure the options for the AirWatch Agent for Windows Phone devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

### DM Sessions Settings

Setting	Description
<b>Enterprise Name</b>	Set the Enterprise Name that the Workplace feature of the Windows Phone device shows when a device is enrolled in Workspace ONE UEM.
<b>Device Sync Interval (min)</b>	Set the time (in minutes or hours) the native DM client waits before checking in with the Workspace ONE UEM console.

### AirWatch Agent Settings

Setting	Description
<b>Heartbeat Interval (min)</b>	Set the time (in minutes) the agent waits before checking in with the UEM console.
<b>Data Sample Interval (min)</b>	Set the time (in minutes) the agent waits to collect data from the device.
<b>Profile Refresh Interval (min)</b>	Set the frequency (in minutes) the profile list of each device refreshes on the server.
<b>Enable Passcode</b>	Enable the use of a passcode to access the agent settings on the device.
<b>Administrative Passcode</b>	Enter the administrative passcode to enter for access to agent settings on the device.
<b>Collect Location Data</b>	Enable to collect the location data from the device. The location is determined based on the Wi-Fi network of the device. When located data is available, the agent sends the location data to the console at the Transmit Interval.
<b>GPS Sample Interval (min)</b>	Set the time (in minutes) the agent waits before collecting GPS data from the device.

Setting	Description
<b>Enable Push Notification Services</b>	Enable to allow the console to send Push Notifications to devices.

## Enterprise App Management

Setting	Description
<b>Enable Enterprise App Management</b>	Enable to use the Enterprise Application Management feature for pushing internal applications to Windows Phone devices.
<b>Upload Enterprise Token</b>	Select Change to upload an Enterprise Token for use with Enterprise Application Management.

**Important:** This token expires annually. If the token is expired and still enabled, you cannot enroll into this organization group.

## About Page Configuration

Setting	Description
<b>Customize About Page Content</b>	Enable to display a text field for customizing the agent about page.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Phone / Company Hub Settings

The Windows Phone Company Hub settings page lets you configure the options for using the company hub applications with Windows Phone.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Enable Company Hub</b>	Enable to use the Company Hub functionality to silently push an enhanced AirWatch Agent to devices after enrollment. Company Hub requires the use of Enterprise Application Tokens.
<b>Company Hub Name</b>	Enter the display name of the Company Hub application.

Setting	Description
<b>Company Hub Application</b>	Select the Company Hub application from the drop-down list of all Windows Phone internal application.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Phone / MDM Sample Schedule

The Windows Phone MDM Sample Schedule settings page lets you configure the time intervals at which certain data samples are sent to the Workspace ONE UEM console server.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Application List Sample</b>	Enter the frequency by which application list information is refreshed on the Workspace ONE UEM server.
<b>Certificate List Sample</b>	Enter the frequency by which certificate list information is refreshed on the Workspace ONE UEM server.
<b>Device Details Sample</b>	Enter the frequency by which device information is refreshed on the Workspace ONE UEM server.
<b>Email EAS Active Sync Sample</b>	Enter the frequency by which EAS information is refreshed on the Workspace ONE UEM server.
<b>Enterprise Application Token</b>	Enter the frequency by which enterprise application token information is refreshed on the Workspace ONE UEM server.
<b>Internet Email Accounts Sample</b>	Enter the frequency by which internet email account information is refreshed on the Workspace ONE UEM server.
<b>Security Information Sample</b>	Enter the frequency by which security information is refreshed on the Workspace ONE UEM server.
<b>Health Attestation Sample</b>	Enter the frequency by which health attestation information is refreshed on the Workspace ONE UEM server.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Phone / Windows Health Attestation

The Health Attestation settings page allows you to configure the compromised status definitions for Windows Phone devices.

Settings	Descriptions
<b>Compromised Status Definition</b>	
<b>Use Custom Server</b>	Select to configure a custom server for Health Attestation. This option requires a server running Windows Server 2016 or newer. Enabling this option displays the <b>Server URL</b> field.
<b>Server URL</b>	Enter the URL for your custom Health Attestation server.
<b>Secure Boot Disabled</b>	Enable to flag compromised device status when Secure Boot is disabled on the device. Secure Boot forces the system to boot to a factory trusted state. When Secure Boot is enabled, the core components used to boot the machine must have the correct cryptographic signatures that the OEM trusts. The UEFI firmware verifies the trust before it allows the machine to start. Secure boot prevents the startup if any it detects any tampered files.
<b>Attestation Identity Key (AIK) Not Present</b>	Enable to flag compromised device status when the AIK is not present on the device. Attestation Identity Key (AIK) is present on a device, it indicates that the device has an endorsement key (EK) certificate. It can be trusted more than a device that does not have an EK certificate.
<b>Data Execution Prevention (DEP) Policy Disabled</b>	Enable to flag compromised device status when the DEP is disabled on the device. The Data Execution Prevention (DEP) Policy is a memory protection feature built into the system level of the OS. The policy prevents running code from data pages such as the default heap, stacks, and memory pools. DEP is enforced by both hardware and software.
<b>BitLocker Disabled</b>	Enable to flag compromised device status when BitLocker encryption is disabled on the device.
<b>Code Integrity Check Disabled</b>	Enable to flag compromised device status when the code integrity check is disabled on the device. Code integrity is a feature that validates the integrity of a driver or system file each time it is loaded into memory. Code integrity checks for unsigned drivers or system files before they load into the kernel. The check also scans for users with administrative privileges running system files modified by malicious software .
<b>Early Launch Anti-Malware Disabled</b>	Enable to flag compromised device status when the early launch anti-malware is disabled on the device. Early launch anti-malware (ELAM) provides protection for the computers in your network when they start up and before third-party drivers initialize.
<b>Code Integrity Version Check</b>	Enable to flag compromised device status when the code integrity version check fails.

Settings	Descriptions
<b>Boot Manager Version Check</b>	Enable to flag compromised device status when the boot manager version check fails.
<b>Boot App Security Version Number Check</b>	Enable to flag compromised device status when the boot app security version number does not meet the entered number.
<b>Boot Manager Security Version Number Check</b>	Enable to flag compromised device status when the boot manager security version number does not meet the entered number.
<b>Advanced Settings</b>	Enable to configure advance settings in the Software Version Identifiers section.
Software Version Identifiers	
<b>Code Integrity Policy Hash Check</b>	Enable to define a whitelist of known, valid hash values for the <b>Code Integrity</b> software. If the hash is not a whitelisted value, health attestation compliance fails.
<b>Secure Boot Config Policy Hash Check</b>	Enable to define a whitelist of known, valid hash values for the <b>Secure Boot Config</b> software. If the hash is not a whitelisted value, health attestation compliance fails.
<b>PCRO Check</b>	Enable to define a whitelist of known, valid measurements for the <b>PCRO Check</b> software. This measurement checks the BIOS trusted code to ensure that it has not been compromised. If the measurement is not a whitelisted value, health attestation compliance fails.

## Devices & Users / Windows / Windows 7 / Agent Application

The Windows 7 Agent Application settings page lets you configure the options for hosting the AirWatch Unified Agent for Windows 7 devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Fully qualified path on local server to the Agent files for Windows PC</b>	Enter the file path on the local server to the agent files for the AirWatch Unified Agent for Windows 7 devices.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows 7 / Agent Settings

The Windows 7 Agent Settings page lets you configure the options for the AirWatch Unified Agent for Windows 7 devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Beacon Interval (min)</b>	Enter the time interval (in minutes) at which the agent will check in with the Workspace ONE UEM console.
<b>Data Sample Interval (min)</b>	Enter the time interval (in minutes) at which the agent will collect a data sample from the device.
<b>Data Transmit Interval (min)</b>	Enter the time interval (in minutes) at which the agent will transmit the collected data sample to the console.  This settings also controls how often the AirWatch Agent checks for a new automatic upgrade if enabled.
<b>Block Enrollment if Windows Genuine validation fails</b>	Enable to block devices with non-genuine copies of Windows Operating Systems from enrolling into Workspace ONE UEM. <ul style="list-style-type: none"> <li>• If a device is enrolled and the agent detects the Windows copy is not genuine, the agent will send an Enterprise Wipe command to the device.</li> <li>• If a device attempts to enroll and the copy of Windows is not genuine, a Non-Compliance message will display and immediately unenroll a device.</li> </ul>
<b>Enforce Passcode Profile</b>	Enable to force the agent to prompt end users for password changes when a passcode profile is installed or updated. This option does not apply to domain-joined devices.
<b>Windows Agent Automatic Updates</b>	Enable to automatically update the AirWatch Agent when an update becomes available.

## Remote Management

Setting	Description
<b>Download Remote Control Cab</b>	Select this link to download the cabinet (CAB) installer file for Workspace ONE UEM Remote Management.

Setting	Description
<b>Seek Permission</b>	<p>Enable Seek Permission if you want to prompt the end user to accept or decline the remote management request from the admin.</p> <ul style="list-style-type: none"> <li>• Enter a <b>Seek Permission Message</b> that the end user sees when a remote request is sent.</li> <li>• Enter the <b>Yes Caption</b> message for the accept button the end user sees on the Seek Permission request.</li> <li>• Enter the <b>No Caption</b> message for the decline button the end user sees on the Seek Permission request.</li> </ul>
<b>Advanced</b>	
<b>Remote Management Port</b>	<p>Enter the port used to communicate between the Remote Management Agent and the Tunnel Agent on the end-user device.</p> <p>This port is responsible for caching the different frames on the device for use with the screen sharing function. The default port is 7775. Consider leaving the default setting unless port 7775 is in use for other uses in your organization.</p>
<b>Device Log Level</b>	Set the Device Log Level to control the verbosity of the remote management application on the device.
<b>Log Folder Path</b>	Define the Log Folder Path where the application saves the remote management log file on the device.
<b>Display Tray Icon</b>	Enable Display Tray Icon to show the remote management applet on the device.
<b>Max Sessions</b>	Enter the maximum number of concurrent sessions allowed on a device.
<b>Number of Retries</b>	Enter the number of retries allowed before communication attempts stop.
<b>Retry Frequency (Seconds)</b>	Enter the amount of time between attempts to communicate.
<b>Heartbeat Interval (Seconds)</b>	Enter the amount of time (in seconds) that passes between status updates that are sent from the device.
<b>Connection Loss Retry Frequency (Seconds)</b>	Enter the amount of time (in seconds) that passes between attempts to reestablish the connection.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Desktop / General

The Windows Desktop General settings page lets you configure the options for using Powershell with Windows 8.0/RT devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Settings	Descriptions
<b>PowerShell URL</b>	Enter the URL where the Workspace ONE UEM console can access your PowerShell service.
<b>Username</b>	Enter the username the UEM console needs to communicate with the PowerShell service.
<b>Password</b>	Enter the password the UEM console needs to communicate with the PowerShell service.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Desktop / Agent Application

The Windows Desktop Agent Application page lets you configure the various options for the AirWatch Unified Agent.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Publish AirWatch Protection Agent</b>	Enable to use the AirWatch Protection Agent for Windows 8.1 devices to configure device security and protection settings.
<b>Device Ownership Type</b>	Select the ownership types you want to require enrolling with the AirWatch Protection Agent enrollment method.
<b>Protection Agent Automatic Updates</b>	Enable to automatically update the AirWatch Protection Agent when a new version is available.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Desktop / Agent Settings

The Windows Desktop Agent Settings page lets you configure the various options for the AirWatch Agent for Windows Desktop devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

## Modern Agent

Settings	Descriptions
<b>Heartbeat Interval (min)</b>	Defines the intervals at which the AirWatch Agent and the Workspace ONE UEM console confirm a continued connection and synchronize.
<b>Data Sample Interval (min)</b>	Defines the intervals at which the AirWatch Agent takes samples of data.
<b>Administrative Passcode</b>	Sets the passcode to access administrative settings on the device.
<b>MDM Channel Security</b>	Defines the app layer security between Workspace ONE UEM and the AirWatch Unified Agent. This secure channel uses the enrollment certificate to sign, encrypt, or sign and encrypt communications between the UEM console and the agent.

## AirWatch Protection Agent

Setting	Description
<b>Data Sample Interval (min)</b>	Defines the intervals at which the AirWatch Protection Agent takes a sample of data from the device.

## Remote Management

Setting	Description
<b>Download Remote Control Cab</b>	Select this link to download the cabinet (CAB) installer file for Workspace ONE UEM Remote Management.
<b>Seek Permission</b>	<p>Enable Seek Permission if you want to prompt the end user to accept or decline the remote management request from the admin.</p> <ul style="list-style-type: none"> <li>Enter a <b>Seek Permission Message</b> that the end user sees when a remote request is sent.</li> <li>Enter the <b>Yes Caption</b> message for the accept button the end user sees on the Seek Permission request.</li> <li>Enter the <b>No Caption</b> message for the decline button the end user sees on the Seek Permission request.</li> </ul>
<b>Advanced</b>	
<b>Remote Management Port</b>	<p>Enter the port used to communicate between the Remote Management Agent and the Tunnel Agent on the end-user device.</p> <p>This port is responsible for caching the different frames on the device for use with the screen sharing function. The default port is 7775. Consider leaving the default setting unless port 7775 is in use for other uses in your organization.</p>

Setting	Description
<b>Device Log Level</b>	Set the Device Log Level to control the verbosity of the remote management application on the device.
<b>Log Folder Path</b>	Define the Log Folder Path where the application saves the remote management log file on the device.
<b>Display Tray Icon</b>	Enable Display Tray Icon to show the remote management applet on the device.
<b>Max Sessions</b>	Enter the maximum number of concurrent sessions allowed on a device.
<b>Number of Retries</b>	Enter the number of retries allowed before communication attempts stop.
<b>Retry Frequency (Seconds)</b>	Enter the amount of time between attempts to communicate.
<b>Heartbeat Interval (Seconds)</b>	Enter the amount of time (in seconds) that passes between status updates that are sent from the device.
<b>Connection Loss Retry Frequency (Seconds)</b>	Enter the amount of time (in seconds) that passes between attempts to reestablish the connection.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Desktop / App Deployments

The Windows Desktop App Deployments page lets you configure software package deployment for Win32 applications.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Software Package Deployment</b>	Select Enabled to enable the ability to deploy Win32 applications from the Apps & Books section so that you can use the application life cycle flow that exists for all internal applications.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Desktop / Enterprise Apps

The Windows Desktop Enterprise Apps settings page lets you configure the various options for Enterprise Application Management.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Enable Enterprise Application Management</b>	Enable to use the Enterprise Application Management feature for pushing internal applications to Windows Desktop devices.
<b>Side Loading Key</b>	Enter the Side Loading Key required for pushing internal applications to Windows Desktop devices.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Desktop / Windows Sample Schedule

The Windows Desktop Sample Schedule settings page lets you configure the time intervals at which certain data samples are sent to the Workspace ONE UEM console server.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Device Details Sample</b>	Enter the frequency by which device information is refreshed on the Workspace ONE UEM server.
<b>Security Information Sample</b>	Enter the frequency by which security information is refreshed on the Workspace ONE UEM server.
<b>Browser Information Sample</b>	Enter the frequency by which browser information is refreshed on the Workspace ONE UEM server.
<b>Application List Sample</b>	Enter the frequency by which application information is refreshed on the Workspace ONE UEM server.
<b>Certificate List Sample</b>	Enter the frequency by which certificate information is refreshed on the Workspace ONE UEM server.
<b>Restriction Information Sample</b>	Enter the frequency by which restriction information is refreshed on the Workspace ONE UEM server.

Setting	Description
<b>Health Attestation Sample</b>	Enter the frequency by which health attestation information is refreshed on the Workspace ONE UEM sever.
<b>Update Sample</b>	Enter the frequency by which Windows update information is refreshed on the Workspace ONE UEM server.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Windows / Windows Desktop / Windows Health Attestation

The Health Attestation settings page allows you to configure the compromised status definitions for Windows Desktop devices.

Settings	Descriptions
<b>Compromised Status Definition</b>	
<b>Use Custom Server</b>	Select to configure a custom server for Health Attestation. This option requires a server running Windows Server 2016 or newer. Enabling this option displays the <b>Server URL</b> field.
<b>Server URL</b>	Enter the URL for your custom Health Attestation server.
<b>Secure Boot Disabled</b>	Enable to flag compromised device status when Secure Boot is disabled on the device. Secure Boot forces the system to boot to a factory trusted state. When Secure Boot is enabled, the core components used to boot the machine must have the correct cryptographic signatures that the OEM trusts. The UEFI firmware verifies the trust before it allows the machine to start. Secure boot prevents the startup if any it detects any tampered files.
<b>Attestation Identity Key (AIK) Not Present</b>	Enable to flag compromised device status when the AIK is not present on the device. Attestation Identity Key (AIK) is present on a device, it indicates that the device has an endorsement key (EK) certificate. It can be trusted more than a device that does not have an EK certificate.
<b>Data Execution Prevention (DEP) Policy Disabled</b>	Enable to flag compromised device status when the DEP is disabled on the device. The Data Execution Prevention (DEP) Policy is a memory protection feature built into the system level of the OS. The policy prevents running code from data pages such as the default heap, stacks, and memory pools. DEP is enforced by both hardware and software.
<b>BitLocker Disabled</b>	Enable to flag compromised device status when BitLocker encryption is disabled on the device.

Settings	Descriptions
<b>Code Integrity Check Disabled</b>	Enable to flag compromised device status when the code integrity check is disabled on the device. Code integrity is a feature that validates the integrity of a driver or system file each time it is loaded into memory. Code integrity checks for unsigned drivers or system files before they load into the kernel. The check also scans for users with administrative privileges running system files modified by malicious software .
<b>Early Launch Anti-Malware Disabled</b>	Enable to flag compromised device status when the early launch anti-malware is disabled on the device. Early launch anti-malware (ELAM) provides protection for the computers in your network when they start up and before third-party drivers initialize.
<b>Code Integrity Version Check</b>	Enable to flag compromised device status when the code integrity version check fails.
<b>Boot Manager Version Check</b>	Enable to flag compromised device status when the boot manager version check fails.
<b>Boot App Security Version Number Check</b>	Enable to flag compromised device status when the boot app security version number does not meet the entered number.
<b>Boot Manager Security Version Number Check</b>	Enable to flag compromised device status when the boot manager security version number does not meet the entered number.
<b>Advanced Settings</b>	Enable to configure advance settings in the Software Version Identifiers section.
<b>Software Version Identifiers</b>	
<b>Code Integrity Policy Hash Check</b>	Enable to define a whitelist of known, valid hash values for the <b>Code Integrity</b> software. If the hash is not a whitelisted value, health attestation compliance fails.
<b>Secure Boot Config Policy Hash Check</b>	Enable to define a whitelist of known, valid hash values for the <b>Secure Boot Config</b> software. If the hash is not a whitelisted value, health attestation compliance fails.
<b>PCRO Check</b>	Enable to define a whitelist of known, valid measurements for the <b>PCRO Check</b> software. This measurement checks the BIOS trusted code to ensure that it has not been compromised. If the measurement is not a whitelisted value, health attestation compliance fails.

## Devices & Users / Windows / Windows Desktop / Staging & Provisioning

The Staging & Provisioning page displays the information you need to create a provisioning pack for bulk staging of Windows 10 devices. The information displayed is used in the creation. When you visit the page for the first time, a staging user is created that the information applies to.

## Devices & Users / Peripherals / Server

The Peripherals Server settings page lets you configure several options related to the management of printers connected to your Workspace ONE UEM environment.

The following settings display after you select **Add Printer Server**.

Setting	Description
<b>HMAC Token</b>	The HMAC key is auto-generated and will be used to associate the print server to the appropriate organization group in Workspace ONE UEM. This key will need to be entered into the relevant Print Server configuration file.
<b>User Id</b>	Select the appropriate enrollment user that will be associated to the Print Server. This user is typically an AirWatch Administrator and may be associated to multiple Print Servers.
<b>Service Uid</b>	Enter the ID of the print server which identifies it uniquely.

## Devices & Users / Peripherals / Sample Schedule

The Peripherals Sample Schedule settings page lets you configure the time intervals at which device details samples from peripheral devices are sent to the Workspace ONE UEM server.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Device Details Sample</b>	Enter the time range (days or hours) to collect peripheral device detail samples. Days range from 1 to 48 and hours range from 1 to 30.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Advanced / Bulk Management

The Bulk Management settings page lets you determine the maximum number of devices that can be affected by a bulk management action performed by an administrator in the Workspace ONE UEM console.

Next to each action, enter the maximum number of allowable device changes that you want to occur at once using bulk management.

Setting	Description
<b>Query</b>	Enter the maximum number of device queries you can run in a bulk command.
<b>Send Message</b>	Enter the maximum number of devices that can receive a bulk message.
<b>Enterprise Wipe</b>	Enter the maximum number of devices you may wipe in a bulk command.
<b>Delete Device</b>	Enter the maximum number of devices you may remove from Workspace ONE UEM as part of a bulk command.
<b>Enterprise Reset</b>	Enter the maximum number of devices you may invoke an enterprise reset in a bulk command.
<b>Device Wipe</b>	Enter the maximum number of devices you may wipe in a bulk command.
<b>Lock Device</b>	Enter the maximum number of devices you may lock in a bulk command.
<b>GPS</b>	Enter the maximum number of devices from which you may request GPS data in a bulk command.
<b>Change Organization Group</b>	Enter the maximum number of devices for which you may change the organization group in a bulk command.
<b>Change Ownership</b>	Enter the maximum number of ownership changes you may invoke upon devices as part of a bulk command.
<b>Warm Boot</b>	Enter the maximum number of devices you may invoke a warm boot operation in a bulk command.
<b>Provision Now</b>	Enter the maximum number of devices you may concurrently provision as part of a bulk command.
<b>Shutdown and Reboot</b>	Enter the maximum number of devices upon which you may invoke a shutdown and reboot bulk command.
<b>Do Not Disturb</b>	Enter the maximum number of devices you may set to Do Not Disturb as part of a bulk command.
<b>Add Tag</b>	Enter the maximum number of devices to which you are able to add a bulk tag.
<b>Enable Lost Mode</b>	Enter the maximum number of devices for which you may enable lost mode in a bulk command.
<b>Disable Lost Mode</b>	Enter the maximum number of devices for which you may disable lost mode in a bulk command.
<b>Custom Command</b>	Enter the maximum number of devices upon which you may invoke a custom bulk command.
<b>iOS Update</b>	Enter the maximum number of iOS devices whose operating systems can be updated concurrently as part of a bulk command.

## Devices & Users / Advanced / Custom Fields

The Custom Field Definitions settings page correlates with a legacy AirWatch Agent for Windows Rugged devices. If you are using up-to-date versions of the Agent this setting page does not apply to you. You should not modify the settings on

this page unless you know what they do and have talked to Workspace ONE UEM about modifying them.

## Devices & Users / Advanced / Device Groups

**Device Groups** is a legacy setting that defines a group of devices without reference to their location. In the current version of Workspace ONE UEM, this functionality is much better served by making use of device tags or smart groups.

Setting	Description
<b>Add New Device Group</b>	<p>Select this button to display the Add New Device Group screen and complete the following options.</p> <ul style="list-style-type: none"> <li>• <b>Device Group</b> – Required field used to label the device group.</li> <li>• <b>Organization Group</b> – Required field used to identify the OG in which this device group resides.</li> <li>• <b>Location</b> – This optional field allows you to define a single location for the device group, independent from the organization group.</li> <li>• <b>Description</b> – Enter a description of the device group's purpose.</li> </ul>

## Devices & Users / Advanced / Area

The Area settings page lets you add geofences or iBeacons for use in the Workspace ONE UEM console.

Workspace ONE UEM enables you to define your profile with a Geofencing Area. A geofence area limits the use of the device to specific areas including corporate offices, school buildings, and retail department stores. You can think of a geofence area as a virtual perimeter for a real-world geographic area.

For example, a geofence area with a 1-mile radius can apply to your office, while a much larger geofence area can apply approximately to an entire state. Once you have defined a geofence area you can apply it to profiles, SDK applications, and Workspace ONE UEM apps such as the VMware Content Locker, and more.

## Devices & Users / Advanced / Tags

The tags settings page lets you add tags for use in the Workspace ONE UEM console. Tags allow you to easily identify a specific device without requiring a device profile, smart group or compliance policy and without requiring the creation of a note.

## Devices & Users / Advanced / User Categories

**User Categories** is a legacy setting that defines a user or a group of users without reference to their location or role. In the current version of Workspace ONE UEM, this functionality is much better served by making use of child organization groups and user groups.

For Windows Rugged devices only, User Categories are the way to establish multi-user device staging. In such a case, you would create a User Category for each user that needs to share a single Windows Rugged device. You would then associate the Windows Rugged Launcher with the established User Categories, thereby effectively implementing multi-user device staging.

Select the **Add** button to create a user category and complete the following options.

Setting	Description
<b>Name</b>	Required field used to label the user category.
<b>Description</b>	Enter a description of the user category's purpose.

## Devices & Users / Advanced / User Migration

The User Migration settings page lets customers with Basic Users intending to switch over to LDAP users employ the User Migration feature. The User Migration tool provides an easy way to check existing Basic Users against current directory users and consolidate information throughout. Additionally, customers using Auth Proxy or legacy SAML who want to start utilizing user groups may employ the User Migration feature to update their users.

 For more information about the User Migration feature, refer to the following Workspace ONE UEM Knowledge Base article: <https://support.workspaceone.com/articles/115001701188>.

## Devices & Users / Advanced / Managed Device Wipe Protection

The Wipe Protection settings page lets you configure options that let you exert more control over how and when **managed devices** can be wiped to avoid mass wiping devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

### Managed Device Wipe Protection

Setting	Description
<b>Wiped Devices</b>	Enter the number of <b>Wiped Devices</b> that acts as your threshold for triggering wipe protection.
<b>Within (minutes)</b>	Enter the value for <b>Within (minutes)</b> which is the amount of time the wipes must occur to trigger wipe protection.
<b>Email</b>	<p>Select a message template to email to administrators.</p> <p>Create a message template for wipe protection by navigating to <b>Groups &amp; Settings &gt; All Settings &gt; Devices &amp; Users &gt; General &gt; Message Templates</b> and select <b>Add</b>, Next, select <b>Device Lifecycle</b> as the <b>Category</b> and <b>Wipe Protection Notification</b> as the <b>Type</b>. You can use the following lookup values as part of your message template.</p> <ul style="list-style-type: none"> <li>• {EnterpriseWipeInterval} – The value of <b>Within (minutes)</b> on the settings page.</li> <li>• {WipeLogConsolePage} – A link to the Wipe Log page.</li> </ul>
<b>To</b>	Enter the email addresses of administrators who must be notified. These administrators must have access to the Wipe Log page.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Devices & Users / Advanced / Profile Options

The Profile Options settings page lets you enable a setting that lets administrators select the **Interactive Assignment Type** for device profiles. The Interactive settings means the only way a profile can be installed on a device is if the user logs in to the Self-Service Portal and initiates the installation.

# Chapter 4:

## Apps

### **App Scan**

[Apps / App Scan / Third-Party Integration on page 101](#)

### **Application Integration**

[Apps / Application Integration / TouchDown on page 102](#)

### **Browser**

[Apps / Browser on page 103](#)

### **Workspace ONE**

[Apps / Workspace ONE / Application Categories on page 109](#)

[Apps / Workspace ONE / Paid Public Applications on page 111](#)

[Apps / Workspace ONE / App Restrictions on page 108](#)

[Apps / Workspace ONE / External App Repository on page 109](#)

[Apps / Workspace ONE / Application Removal Protection on page 109](#)

### **Airwatch Catalog**

[Apps / Workspace ONE / Catalog / General on page 106](#)

[Apps / Workspace ONE / Catalog / Standalone Catalog on page 107](#)

[Apps / Workspace ONE / Catalog / Featured Applications on page 110](#)

### **Container**

[Apps / Container on page 112](#)

### **Inbox**

[Apps / Inbox on page 112](#)

### **Video**

[Apps / Video on page 113](#)

### **Settings and Policies**

[Apps / Settings and Policies / Security Policies on page 114](#)

[Apps / Settings and Policies / Settings on page 115](#)

[Apps / Settings and Policies / Profiles on page 115](#)

## Microsoft Intune® App Protection Policies Settings

[Apps / Microsoft Intune® App Protection Policies on page 115](#)

### Apps / App Scan / Third-Party Integration

The Third-Party Integration setting allows you to add your App Scan service information to the UEM console so that the systems can share applications and scan results.

**Note:** Ensure that you are in the desired organization group that is a **Customer** type.

#### Common Settings

Setting	Description
<b>Enable Third Party App Scan Analysis</b>	Select to enable communication between Workspace ONE UEM and the App Scan Vendor and to display available options on the page.
<b>Choose App Scan Vendor</b>	Select the applicable third-party vendor.

Setting	Description
<b>Save</b>	Saves configurations and syncs with the App Scan Vendor when the Workspace ONE UEM scheduler task runs.
<b>Sync Now</b>	Saves configurations and begins a manual sync with the App Scan Vendor without waiting for the scheduler task to run.

#### Veracode Mobile Application Reputation Service (MARS) Settings

Setting	Description
<b>Veracode Username</b>	Enter the username for your Veracode MARS.
<b>Veracode Password</b>	Enter the password for the username to authenticate to your Veracode MARS.
<b>Veracode REST API URL</b>	Enter the URL for your Veracode MARS to direct Workspace ONE UEM to the service.

Setting	Description
<b>Enable Email Notification</b>	Displays the <b>Application Group Creation</b> area to configure the system to send notifications to admins when analysis creates new app groups in Workspace ONE UEM.
<b>Send Email To</b>	Enter email addresses to receive notifications about new app groups created by analysis. Use a comma to separate addresses.
<b>Message Template</b>	Use <b>Message Preview</b> to see the email that the system sends upon the creation of new app groups using the <b>Vendor Application Group Creation Notification</b> template.

## Palo Alto Networks WildFire Settings

Setting	Description
<b>WildFire API Key</b>	Enter the key for your WildFire system so Workspace ONE UEM can send application hashes directly to WildFire.

## Pradeo Security System

Setting	Description
<b>Pradeo Username</b>	Enter the username for your Pradeo.
<b>Pradeo Password</b>	Enter the password for the username to authenticate to your Pradeo.
<b>Pradeo REST API URL</b>	Enter the URL for your Pradeo to direct Workspace ONE UEM to the service.

Setting	Description
<b>Enable Email Notification</b>	Displays the <b>Application Group Creation</b> area to configure the system to send notifications to admins when analysis creates new app groups in Workspace ONE UEM.
<b>Send Email To</b>	Enter email addresses to receive notifications about new app groups created by analysis. Use a comma to separate addresses.
<b>Message Template</b>	Use <b>Message Preview</b> to see the email that the system sends upon the creation of new app groups using the <b>Vendor Application Group Creation Notification</b> template.

## Appthority

Setting	Description
<b>Appthority Username</b>	Enter the username for your Appthority.
<b>Appthority Password</b>	Enter the password for the username to authenticate to your Appthority.
<b>Appthority REST API URL</b>	Enter the URL for your Appthority to direct Workspace ONE UEM to the service.

Setting	Description
<b>Enable Email Notification</b>	Displays the <b>Application Group Creation</b> area to configure the system to send notifications to admins when analysis creates new app groups in Workspace ONE UEM.
<b>Send Email To</b>	Enter email addresses to receive notifications about new app groups created by analysis. Use a comma to separate addresses.
<b>Message Template</b>	Use <b>Message Preview</b> to see the email that the system sends upon the creation of new app groups using the <b>Vendor Application Group Creation Notification</b> template.

## Apps / Application Integration / TouchDown

The NitroDesk TouchDown settings page lets you configure some options related to the NitroDesk TouchDown email client.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>TouchDown for iOS Type</b>	Select the type of iOS Touchdown app. Options are Standard, Government, and Custom.
<b>Bundle</b>	The ID used by iOS to uniquely identify an application. It follows the reverse DNS format.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Apps / Browser

The Browser settings page lets you configure settings related to the VMware Browser app.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

### Browser Settings

Setting	Description
<b>Settings and Policies</b>	
<b>Application Profile</b>	Select an application profile to apply SDK functionality to your app. <ul style="list-style-type: none"> <li>• <b>Default</b> – Allow applications to use the default security policies and settings defined under <b>Apps and Books &gt; Settings &gt; Settings and Policies</b>.</li> <li>• <b>Custom</b> – Override default settings and apply custom profiles. Custom profiles use the security policies and settings defined under <b>Apps and Books &gt; Settings &gt; Settings and Policies &gt; Profiles</b>.</li> </ul>
<b>iOS SDK Profile</b>	Select the appropriate profile from the drop-down menu that appears when you enable a <b>Custom Application Profile</b> to override default SDK settings.
<b>Android SDK Profile</b>	Select the appropriate profile from the drop-down menu that appears when you enable a <b>Custom Application Profile</b> to override default SDK settings.
<b>Use Legacy Settings and Policies</b>	Enable to configure settings and policies for legacy browsers only.
<b>Disable Copy</b>	(Legacy Browsers only) Enable this option to prevent copying from device. Configure this option under <b>Data Loss Prevention</b> in <b>Settings &gt; Apps &gt; Settings and Policies</b> .
<b>Disable Printing</b>	(Legacy Browsers only) Enable this option to prevent printing from device. Configure this option under <b>Data Loss Prevention</b> in <b>Settings &gt; Apps &gt; Settings and Policies</b> .

<b>Force Downloads To Open in Content Locker</b>	(Legacy Browsers only) Enable this option to open the force downloaded documents in Content Locker. Configure this option under <b>Data Loss Prevention</b> in <b>Settings &gt; Apps &gt; Settings and Policies</b> .
<b>Enable AW Tunnel Proxy</b>	(Legacy Browsers only) Enable AW App Tunnel Proxy to access internal network. Configure this option under <b>Data Loss Prevention</b> in <b>Settings &gt; Apps &gt; Settings and Policies</b> .
<b>iOS SDK Profile (Legacy)</b>	Select the appropriate iOS SDK profile from the drop-down menu for the legacy browser.
<b>General</b>	
<b>Accept Cookies</b>	<b>Enable</b> to accept cookies from websites viewed in the VMware Browser.
<b>Clear Cookies Upon Exit</b>	<b>Enable</b> to clear cookies when the app fully closes.
<b>Clear Cookies and History if Idle</b>	<b>Enable</b> to clear cookies and history if the Browser is idle for x minutes.
<b>Clear Cookies and History if Idle for (mins)</b>	Set the idle time in minutes to a value between 0.5 and 60 to ensure cookies and history are clear.
<b>Remember History</b>	<b>Enable</b> to keep track of the sites visited by the user.
<b>Remember History From</b>	Select the length of time you want the app to remember history to from the drop-down menu.
<b>Caching</b>	<b>Enable</b> to enhance web performance and reduce perceived lag time. <b>Disable</b> to protect browsing data on compromised devices.
<b>Allow Connection to Untrusted Sites</b>	<b>Disable</b> if navigating to untrusted sites is a security concern for your organization. <b>Enable</b> to give end users maximum navigation flexibility and ease of use.
<b>Sync User Bookmarks</b>	<b>Enable</b> this to sync bookmarks across various devices of the same user.
<b>Default View Mode</b>	Set the default view mode for VMware Browser. Select Desktop to set desktop as the default view mode. When selected, the VMware Browser renders the web pages in desktop mode if the websites supports the mode.
<b>Mode</b>	
<b>Kiosk Mode</b>	<b>Enable</b> for VMware Browser to function in <b>Kiosk Mode</b> . Kiosk Mode removes the navigation bar and limits browsing to the homepage and its available links.
<b>Return Home After Inactivity</b>	Direct the browser back to the home page after a period of <b>Inactivity (min)</b> . The values can be greater than or equal to 0.5 minutes.

<b>Clear Cookies and History with Home</b>	Prevent users from accessing the previous user's secure information after they finish using the Browser.
<b>Enable Multiple Tabs Support</b>	You can have multiple tabs opened within kiosk mode. This feature is supported only on iOS and Android devices.
<b>Home Page URL</b>	Define the URL displayed when the browser starts. Leave this field blank to display a 'Recently Visited' page by default.
<b>Selection Mode</b>	<b>Allow</b> to limit browsing to domains white listed in the <b>Allowed Site URLs</b> field. <b>Deny</b> to allow browsing to all sites except those blacklisted in the <b>Denied Site URLs</b> field.
<b>Allowed/Denied Site URLs</b>	Utilize the following recommendations to whitelist allowed domains and blacklist denied domains. <ul style="list-style-type: none"> <li>Define domain names without including full URLs. The browser filters by domain only, not by folder or page level.</li> <li>Separate domains with a space, comma, or a new line.</li> <li>Define wildcards as part of the domains; listing items from most general to specific. Example: *.google.com is more general than http://yahoo.com. Entering *.google.com whitelists &lt;text&gt;.google.com, but it <i>does not</i> allow access to http://google.com.</li> <li>Leave out the scheme (http:// or https://) to test the domain for both schemes. Include the scheme to limit testing to the specified scheme.</li> <li>You can enter Port value separately. Restricted URL can contain the complete path, for example, http:// google.com:9191.</li> </ul>
<b>Allow IP Browsing</b>	Select to whitelist IP addresses for browsing. A user can navigate to a whitelisted IP address even if the actual domain for the IP address was included in the Denied Site URL listing.
<b>Allowed IP Addresses</b>	Whitelist IP addresses using the following recommendations: <ul style="list-style-type: none"> <li>Enter values in IPv4 formatting with four octets each separated by a period.</li> <li>Enter wildcards to whitelist octets. Adding an entry that includes a * in each octet allows browsing to any IP address.</li> </ul>
<b>Terms of Use</b>	
<b>Required Terms of Use</b>	Select the appropriate agreement from the drop-down menu. For all internal Workspace ONE UEM apps, including the VMware Browser, you can implement a single Terms of Use Agreement for end users to accept. This agreement applies to all Workspace ONE UEM internal applications, and eliminates the need for end users to accept the same agreement multiple times, across apps. You can configure and manage your Terms of Use Agreements by navigating to <b>Groups and Settings &gt; All Settings &gt; System &gt; Terms of Use</b> . For more information, please see the <b>VMware AirWatch Mobile Device Management Guide</b> .

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Bookmarks

Setting	Description
<b>URLs for Predefined Bookmarks in Browser</b>	Configure bookmarks to display as a URL address or with a friendly name.
<b>Name</b>	Provide text in this field to display as the friendly name. Leave this field blank to display the URL as the bookmark name.
<b>URL</b>	Provide the bookmark URL.
<b>Add Bookmark</b>	Select to add additional bookmarks.

## Notification

Do not configure any settings on this tab unless you have been provided with specific instructions on how to complete the fields from Workspace ONE UEM.

## Apps / Workspace ONE / Catalog / General

The Catalog / General settings page lets you configure several options related to the AirWatch App Catalog.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

## Authentication

Setting	Description
<b>Require Authentication</b>	Require users to log in with their username and password before they can access the app catalog. This option is disabled by default which sets Workspace ONE UEM to require no authentication to access the app catalog.
<b>Reauthenticate</b>	Select a reauthentication option. <ul style="list-style-type: none"> <li>• <b>Never - Keep User Signed In</b> – Keeps users signed in and does not require them to log in each time.</li> <li>• <b>After XX day(s)</b> – Require users to authenticate (log in) after a set number of days.</li> </ul> <p>Users still have to reauthenticate if they clear cookies on their devices, even with this option enabled.</p>

## Publishing

Setting	Description
<b>Catalog Title</b>	Enter a name for your app catalog. This title appears on the home screen of the device.
<b>Platforms</b>	Select the supported platforms for your app catalog. If this is enabled for the platform, the profile gets pushed to the device.  Apple iOS offers the option to open the app catalog web clip in full screen mode, if desired. Set this using the <b>Full Screen</b> option for iOS 6+ devices.
<b>Icon</b>	Upload an icon for your app catalog. This icon appears on the home screen of the device.  If you do not upload an icon, Workspace ONE UEM pushes a default icon to devices.

## Customization

Setting	Description
<b>Branding Logo</b>	Upload a logo to brand the app catalog for your organization. <ul style="list-style-type: none"> <li>This logo overrides any logo you set in <b>Groups &amp; Settings &gt; All Settings &gt; System &gt; Branding</b>.</li> <li>If you do not upload a logo for the app catalog, Workspace ONE UEM uses the logo from your <b>System &gt; Branding</b> settings.</li> <li>If you do not configure any branding scheme or logo the <b>System &gt; Branding</b> settings, Workspace ONE UEM uses a default scheme.</li> </ul>
<b>Default Filter</b>	Sets the app catalog to open with this filter enabled on the catalog's main page. However, if users need to install featured applications, the app catalog defaults to open with the <b>Featured</b> filter.  Users can change the default filter at any time and their selection stays active if they use the app catalog within a 24 hour period. After more than 24 hours of inactivity, the app catalog returns to the set default filter.
<b>Default Sort</b>	Sets the app catalog to open with a configured sorting option enabled.  Users can change the default sort at any time and their selection stays active and does not depend on activity.
<b>Pinned Categories</b>	Pins specific categories to the default menu.  Users can elect to see more categories.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Apps / Workspace ONE / Catalog / Standalone Catalog

The Standalone Catalog settings page lets you configure various options related to the standalone app catalog.

Many organizations do not need to manage devices for their mobile fleets for various reasons, including possible privacy or legal issues. However, they may need to distribute mobile applications, so Workspace ONE UEM offers the flexibility of deploying the Standalone Catalog.

Users do not have to enroll with Workspace ONE UEM using an Agent, but rather enroll with the Workspace ONE UEM Standalone Catalog. This catalog distributes all application types, public, purchased, internal, and web.

Although end user devices are not enrolled in MDM, you can access a device record in the UEM Console. The device record is for auditing purposes and the status of these devices in the UEM Console displays as **App Catalog Only**.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Standalone Catalog</b>	Enable the <b>Standalone Catalog</b> to prevent users that enroll into the selected App-Catalog-Only-Organization-Group from enrolling into MDM. Configure this setting in the App-Catalog-Only-Organization-Group or in a parent above it.
<b>Allow New User Registration</b>	Enable the <b>Allow New User Registration</b> check box to allow new users to register for access to the Standalone Catalog.
<b>Enable Email Domain Validation</b>	Select the <b>Enable Email Domain Validation</b> option to use specified email domains to validate users when they register to access to the Standalone Catalog. Enter email domains in the <b>Allowed Email Domains</b> field for the standalone MAM users. End users enter their email addresses and a Group ID to enroll with this Standalone Catalog. Workspace ONE UEM matches the domains entered in this field to the domains of MAM-only users.
<b>Catalog Title</b>	Enter a title in the <b>Catalog Title</b> field.
<b>Icon</b>	Upload an image in the <b>Icon</b> field for the Standalone Catalog.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Apps / Workspace ONE / App Restrictions

The App Restrictions settings page lets you configure a setting that lets you control which public apps can be installed on devices.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Restricted Mode for Public iOS Applications</b>	Enable this setting to restrict devices to only install assigned public apps from the iTunes App Store. This setting will send a restriction profile that blocks iTunes App Store access on iOS devices in the organization group so you do not have to configure any additional restriction profiles to block app store access.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Apps / Workspace ONE / Application Categories

You can define your own application categories to filter applications and books by type or function. Although they are labeled application categories, they apply to Workspace ONE UEM books, as well. You can create, view, edit, delete, and assign one or more categories for both public and internal applications and books in a selected organization group. The App and Book Catalogs display these categories, allowing end users to browse and filter.

## Apps / Workspace ONE / External App Repository

The External App Repository settings page is where you can set up a connection to your own external app repository server.

Host internal applications on your network with an external application repository and manage the applications with the Workspace ONE UEM. The Workspace ONE UEM uses Windows File Share protocols to make externally hosted applications available to user devices. Communication is secure because on-premises deployments must use the Content Gateway for Windows to transfer data from the on-premises network to the Workspace ONE UEM.

Setting	Description
<b>Username</b>	Enter the username for the external app repository.
<b>Password</b>	Enter the password for the external app repository.

## Apps / Workspace ONE / Application Removal Protection

The app removal protection feature helps ensure that the system does not remove business-critical applications unless approved by the admin. Internal applications are often developed to perform enterprise-specific tasks. Their abrupt removal can cause user frustration and halt work. To prevent the removal of important internal applications, the feature holds removal commands according to entered threshold values. Until an admin acts on the held commands, the system does not remove internal applications.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
Devices Affected	Enter the maximum amount of devices that can lose a critical application before the loss hinders the work of the enterprise.
Within (minutes)	Enter the maximum amount of minutes that the system sends removal commands before the loss of a critical application hinders devices from performing business tasks.
Email Template	Select an email notification template and make customizations. The system includes the <b>App Remove Limit Reached Notification</b> template, which is specific to app removal protection.
Send Email to	Enter email addresses to receive notifications about held removal commands so that the recipients can take actions in the app removal log.

## Apps / Workspace ONE / Catalog / Featured Applications

Use the featured application option to set a few select applications apart from other applications and to highlight specific applications within the AirWatch Catalog for your end users.

### Supported Platforms and App Types

You can configure Featured Applications for the following platforms:

- Android
  - Internal applications
  - Public applications
- Apple iOS
  - Internal applications
  - Public applications

### Configuring Featured Applications

The AirWatch Catalog lists featured apps in the main list of applications. You can feature public and internal applications.

## Devices & Users / Apple / VPP Managed Distribution

Use Apple's Managed Distribution system integrated with Workspace ONE UEM to distribute your free and purchased Volume Purchase Program (VPP) applications and books to Apple iOS 7+ devices. The managed distribution model uses service tokens (also called sTokens) to retrieve your VPP contents and distribute them to devices using the UEM console.

Navigate to **Groups & Settings > All Settings > Devices & Users > Apple > VPP Managed Distribution**.

Setting	Description
<b>Description</b>	<p>Enter your VPP Account ID.</p> <p>Using your VPP Account ID as the description has several advantages:</p> <ul style="list-style-type: none"> <li>• Identifies the correct account if you use multiple sTokens.</li> <li>• Reminds you the correct account when you renew the sToken.</li> <li>• Identifies the correct account to others in your organization who take over managing the VPP account.</li> </ul>
<b>sToken Upload</b>	Select <b>Upload</b> to navigate to the sToken on your network.
<b>Country</b>	<p>Select where Workspace ONE UEM should validate the sToken.</p> <p>This value reflects the region from where you bought content and ensures Workspace ONE UEM uploads the correct versions of your purchases.</p> <p>When you sync your licenses, Workspace ONE UEM pulls the correct regional version of the content.</p> <p>If Workspace ONE UEM cannot find the content in the app store from the region entered, Workspace ONE UEM automatically searches the iTunes App Store in the United States.</p>
<b>Automatically Send Invites</b>	<p>Send invitations to all the users immediately after you save the token. This is an invitation to join and register with Apple's VPP, so that users access the terms of use for participating in the program.</p> <p>Use the <b>Message Preview</b> option to review the invitation.</p> <p>Workspace ONE UEM automatically sends users of Apple iOS 7.0.3+ an invite command when you enable this option. It does not send them an email message.</p> <p>You do not have to enable this immediately. You can leave it disabled and still upload your token. Return and enable this feature to send invitations to all the enrolled devices whose users have not yet accepted to join the VPP.</p>
<b>Message Template</b>	Select an email template for an email message invitation for Apple iOS devices on Apple iOS 7.0.0 through 7.0.2.

## Apps / Workspace ONE / Paid Public Applications

The Paid Public Applications settings page lets you enable the management of paid public iOS apps when using Apple's Volume Purchase Program is not an option.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Management Of Paid Public Application</b>	Enable this setting to upload paid public iOS apps and distribute them in those distribution scenarios where using the VPP is not feasible. Workspace ONE UEM can apply deployment options to offer control over the use of the app.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Apps / Container

This Workspace settings page allows you to configure an AirWatch Container application with a different Bundle ID.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Notification</b>	
<b>Apple</b>	Select to set iOS device system preferences.
<b>Android</b>	Select to set Android device system preferences.
<b>Application Type</b>	<p>Leave the application type as <b>System</b> or select <b>Internal</b> to set system preferences.</p> <ul style="list-style-type: none"> <li>• <b>System</b> – Download this app type from an app store.</li> <li>• <b>Internal</b>– Upload this app type to the UEM console.</li> </ul>
<b>Application Name</b>	<p>Provide an app name for <b>Internal</b> applications.</p> <p>Navigate to <b>Apps &amp; Books &gt; Internal List View</b> and scan the list for an app name that matches the app name you entered. This list view only displays internal applications were uploaded with a matching APNs certificate.</p>
<b>Bundle ID</b>	Review the auto-populated field. This Bundle ID matches the application bundle ID that was uploaded internally or selected from the drop-down menu.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Apps / Inbox

The Inbox settings page lets you configure options related to the VMware Inbox application.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Application Type</b>	<p>Leave the application type as <b>System</b> or select <b>Internal</b> to set system preferences.</p> <ul style="list-style-type: none"> <li>• <b>System</b> – Download this app type from an app store.</li> <li>• <b>Internal</b>– Upload this app type to the UEM console.</li> </ul>
<b>Application Name</b>	<p>Provide an app name for <b>Internal</b> applications.</p> <p>Navigate to <b>Apps &amp; Books &gt; Internal List View</b> and scan the list for an app name that matches the app name you entered. This list view only displays internal applications were uploaded with a matching APNs certificate.</p>
<b>Bundle ID</b>	Enter the bundle ID of the application.
Settings and Policies	
<b>Application Profile</b>	<p>Select an application profile to apply SDK functionality to your app.</p> <ul style="list-style-type: none"> <li>• <b>Default</b> – Allow applications to use the default security policies and settings defined under <b>Apps and Books &gt; Settings &gt; Settings and Policies</b>.</li> <li>• <b>Custom</b> – Override default settings and apply custom profiles. Custom profiles use the security policies and settings defined under <b>Apps and Books &gt; Settings &gt; Settings and Policies &gt; Profiles</b>.</li> </ul>
<b>iOS SDK Profile</b>	<p>Select the corresponding profile from the drop-down menu. This profile applies the default security policies and settings defined under <b>Settings &amp; Policies</b> OR the custom security policies and settings defined under <b>Profiles</b>.</p> <p>This is an optional, advanced management feature. Instructions for configuring default SDK settings are available in the <b>VMware Workspace ONE UEM Mobile Application Management Guide</b>.</p>

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Apps / Video

The Video settings page lets you configure various settings related to the Workspace ONE UEM Video mobile app.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Settings and Policies</b>	
<b>Application Profile</b>	Select an application profile to apply SDK functionality to your app. <ul style="list-style-type: none"> <li>• <b>Default</b> – Allow applications to use the default security policies and settings defined under <b>Apps and Books &gt; Settings &gt; Settings and Policies</b>.</li> <li>• <b>Custom</b> – Override default settings and apply custom profiles. Custom profiles use the security policies and settings defined under <b>Apps and Books &gt; Settings &gt; Settings and Policies &gt; Profiles</b>.</li> </ul>
<b>iOS SDK Profile</b>	Select the appropriate profile from the drop-down menu that appears when you enable a <b>Custom Application Profile</b> to override default SDK settings.
<b>Android SDK Profile</b>	Select the appropriate profile from the drop-down menu that appears when you enable a <b>Custom Application Profile</b> to override default SDK settings.
<b>General</b>	
<b>Require MDM Enrollment</b>	Select to require Workspace ONE UEM MDM enrollment for Workspace ONE UEM Video access.
<b>Notification</b>	
<b>Apple</b>	Select to set iOS device system preferences.
<b>Android</b>	Select to set Android device system preferences.
<b>Application Type</b>	Leave the application type as <b>System</b> or select <b>Internal</b> to set system preferences. <ul style="list-style-type: none"> <li>• <b>System</b> – Download this app type from an app store.</li> <li>• <b>Internal</b>– Upload this app type to the UEM console.</li> </ul>
<b>Application Name</b>	Provide an app name for <b>Internal</b> applications. Navigate to <b>Apps &amp; Books &gt; Internal List View</b> and scan the list for an app name that matches the app name you entered. This list view only displays internal applications were uploaded with a matching APNs certificate.
<b>Bundle ID</b>	Review the auto-populated field. This Bundle ID matches the application bundle ID that was uploaded internally or selected from the drop-down menu.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Apps / Settings and Policies / Security Policies

The Settings and Policies > Security Policies page lets you configure options that affect Workspace ONE UEM apps and wrapped apps.

Not all of the settings here apply to all apps.

## Apps / Settings and Policies / Settings

The Settings and Policies > Settings page lets you configure options that affect Workspace ONE UEM apps and wrapped apps.

Not all of the settings here apply to all apps.

## Apps / Settings and Policies / Profiles

The Settings and Policies > Profiles page lets you create custom app wrapping and SDK profiles that you can assign to your internal apps. Custom settings for profiles offer granular control for specific applications and the ability to override default (security policies) settings. However, they also require separate input and maintenance.

Not all of the settings here apply to both app wrapping profiles and SDK profiles. For a comparison matrix of the two, see Settings and Policies Compatibility Matrices on page 1.

## Apps / Microsoft Intune® App Protection Policies

You can configure the data loss prevention (DLP) application policies for your Microsoft Intune® App Protection applications in Workspace ONE UEM. Microsoft Intune® App Protection Policies allow administrators to configure policies to protect Office 365 apps and data using Microsoft's Graph APIs. After you integrate the two systems, you can manage the DLP application policies in the UEM console so that the integration stays current.

# Chapter 5:

## Content

### **Applications**

[Content / Applications / Content Locker Sync on page 117](#)

[Content / Applications / Content Locker on page 117](#)

[Content / Applications / Outlook Add-In on page 120](#)

### **Content Gateway**

[Content / Content Gateway on page 120](#)

### **Personal Content**

[Content / Personal Content on page 120](#)

### **Remote Storage**

[Content / Remote Storage on page 123](#)

### **User Storage**

[Content / User Storage on page 123](#)

### **Content Viewer**

[Content / Content Viewer on page 123](#)

### **Advanced**

[Content / Advanced / File Extensions on page 124](#)

[Content / Advanced / Onboarding on page 125](#)

## Content / Applications / Content Locker Sync

The VMware Content Locker Sync settings page lets you configure the various options for using the VMware Content Locker Sync client.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Content Locker Sync</b>	Enable to allow end users to use the VMware Content Locker Sync client.
<b>Client Download</b>	Enable to allow end users to download the VMware Content Locker Sync client to their macOS or Windows 7 devices from the Self-Service Portal.
<b>Require MDM Enrollment</b>	Enable to require MDM enrollment before devices sign in to VMware Content Locker Sync to enforce compliance.

## Terms of Use

Setting	Description
<b>Required Terms of Use</b>	Select the Terms of Use end users must agree to follow before using VMware Content Locker Sync.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Content / Applications / Content Locker

The VMware Content Locker settings page lets you configure the various options for the VMware Content Locker application.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

## Settings and Policies

Setting	Description
<b>Application Profile</b>	<p>Set to define the security policies and settings used by this application.</p> <p>Leave as <b>Default</b> and configure the Recommended Default SDK settings to define app behavior using Workspace ONE UEM recommendations.</p> <p>Alternatively, select <b>Custom</b> application settings to override the default SDK settings and configure a unique set off behaviors for the app.</p>
<b>iOS Profile</b>	Select a custom-created SDK profile from the drop-down list.
<b>Android Profile</b>	Select a custom-created SDK profile from the drop-down list.
<b>Use Legacy Settings and Policies</b>	<p>Only enable legacy settings if directed to do so by a Workspace ONE UEM representative. Legacy settings do not leverage Shared SDK profile settings and should only be implemented in certain edge cases.</p>
<b>Default Authentication Method</b>	Select the authentication method for the applications.
<b>Enable "Keep me signed in"</b>	Enable to allow end users to remain signed in between uses.
<b>Maximum Number of Failed Attempt</b>	Set the number of passcode entry attempts allowed before all data in the VMware Content Locker will be wiped from a device.
<b>Authentication Grace Period (min)</b>	Enter the time (in minutes) after closing the VMware Content Locker before reopening the VMware Content Locker will require users to enter credentials again.
<b>Prevent Compromised Devices</b>	Enable to prevent compromised devices from accessing VMware Content Locker.
<b>Enable Offline Login Compliance</b>	Enable to allow offline login compliance.
<b>Maximum Number of Offline Logins</b>	Enter the number of offline logins allowed before you have to go online.

## General

Setting	Description
<b>Numbers of Days to Keep Content New</b>	Select the number of days recently added documents will be labeled as new in the VMware Content Locker.
<b>Block Enrollment via Content Locker, Boxer, and Browser</b>	<p>Enable to prevent enrollment through VMware Content Locker, VMware Boxer, and VMware Browser.</p> <p>If Content Locker uses the VMware AirWatch SDK for iOS in Objective-C, then MDM enrollment is required for the single-sign on SDK setting to function correctly.</p>

Setting	Description
<b>Change Repository Name</b>	Enable to change the repository name in the <b>Root Repository Name</b> field that appears.
<b>Root Repository Name</b>	Enter the new repository name you want to use.
<b>Allow Hyperlinks</b>	Enable to allow end users to open hyperlinks located in documents in the <b>Open Internet Links with</b> field that appears.
<b>Open Internet Links with</b>	Select the application in which to open hyperlinks.
<b>Local Storage</b>	<p>Enable to provide a storage alternative for user content. Local storage saves on the device and doesn't sync with other Personal Content in the cloud.</p> <p>Disable local storage to force all user content to save in a location that syncs with other Personal Content in the cloud.</p>
<b>Upload on Wi-Fi Only</b>	Enable to restrict uploads from VMware Content Locker to Wi-Fi connections only.

## Terms of Use

Setting	Description
<b>Required Terms of Use</b>	Select the Terms of Use end users must accept.

## Notification

Setting	Description
<b>Platform</b>	Select the platform for which to configure notification settings.
<b>Application Type</b>	Select to use a <b>System</b> or <b>Internal</b> application.
<b>Application Name</b>	Select the application's name.
<b>Bundle ID</b>	Select the Bundle ID number used to identify the app in the app store.
<b>Badge Count</b>	Select the type of notifications that create app badges.

## VMware Content Locker for Windows PC

Setting	Description
<b>Client Download</b>	Enable to allow end users to download VMware Content Locker for Desktop using the download link in the Self-Service Portal.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Content / Applications / Outlook Add-In

The Outlook Add-In settings page lets you configure options related to the Outlook Add-In for Windows 7.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Client Download</b>	<p><b>Enable</b> to allow end users to download the Outlook Add-In client from the Self-Service Portal.</p> <p><b>Disable</b> if your organization does an enterprise deployment of Outlook Add-In.</p>
<b>Automatically convert attachments to links</b>	<p><b>Enable</b> to automatically convert large attachments into a link.</p> <p>Enter the amount that triggers the conversion of attachments to links into the field that appears.</p>
<b>Recommend converting attachments to links</b>	<p><b>Enable</b> to recommend end users convert attachments into a link.</p> <p>Enter the amount that triggers the conversion of attachments to links into the field that appears.</p>

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Content / Content Gateway

The Content Gateway settings page is used to configure the Content Gateway component.

## Content / Personal Content

The Personal Content settings pages lets you configure the various options for personal content.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

### Storage Allocation

Setting	Description
<b>Storage Quota</b>	<p>Divide the allocated storage between the Workspace ONE UEM Managed and Personal Content repositories, dedicating an amount of the available storage to Personal Content.</p> <p>By default, all available storage gets dedicated to Personal Content, indicated by the far-right position of the slider.</p>

Setting	Description
<b>User Quota</b>	Set the maximum amount of storage any one user can consume, in MB. This quota applies to users in the same Organizational Group hierarchy as Storage Quota.
<b>User Group Quota(s)</b>	Select <b>Add New</b> and configure storage exceptions on a user group basis.

## Shared Links

Setting	Description
<b>Link Sharing</b>	Enable link sharing of documents.
<b>Auto Expire Days</b>	Enable and fill in a numerical value to specify the number of <b>Days</b> links remain available for sharing. Disable to leave the option open for end users to configure when they share their links.
<b>Auto Expire Downloads</b>	Enable and input a numerical value to set the maximum number of <b>Downloads</b> before the link expires. Disable to leave the option open for end users to configure when they share their links.
<b>Require Password Protection</b>	Enable and set the <b>Minimum Length</b> in characters and the <b>Complexity</b> of the password. Disable to leave the option open for end users to configure when they share their links.

## Shared Folders

Setting	Description
<b>Folder Sharing</b>	Enable to provide end users with the option to share folders with other users.
<b>Share with User Groups</b>	Enable to provide end users with the option to share folders with entire user groups in lieu of manually listing each user they want to share their folder with.
<b>Available Sharing Roles</b>	Set the access privilege role for those that end users share a folder with. See the Sharing Roles matrix below, for an overview of sharing roles and their permissions.
<b>Share with External Users</b>	Enable to allow end users to share folders with external users.
<b>Available Sharing Roles</b>	Set the role for those that end users share their folder with. See the Sharing Roles matrix below, for an overview of sharing roles and their permissions.
<b>User Quota</b>	Leave the quota at 0 to have all external user uploads count against the folder sharer's quota. Set a quota to give external users dedicated space for uploads.

## Sharing Roles

The matrix below displays the available roles and their permissions available for selection when you enable user group and external user sharing. These permissions apply to the user group or external user that an end-user shares a folder with.

	Co-Owner	Editor	Reader
View File and Folders	✓	✓	✓
Download Files to Computer	✓	✓	✓
Add Comments to Files	✓	✓	✓
Upload Files to Folder	✓	✓	
Delete Files or Sub-folders	✓	✓	
Edit Files	✓	✓	
View Other Folder Collaborators	✓	✓	
View Other Collaborators Activity in Feed	✓	✓	✓
Modify Sharing of Folder	✓		
Generate Shared Links to Files			
Transfer Folder Ownership			

## Email Notification

Setting	Description
<b>Email Notifications</b>	Enable to alert users through email when a folder is shared with them.

## Data Loss Prevention

Setting	Description
<b>Allow Open in Email</b>	Enable to allow content to open in emails. Disable for maximum security.
<b>Allow Open in Third Party Apps</b>	Enable to open personal content in other applications. You can set a list of approved apps in the SDK Profile. Disable for maximum security.
<b>Allow Printing</b>	Enable iOS devices to print personal content PDFs using AirPrint. Disable for maximum security.
<b>Watermark</b>	Enable to apply a dynamic watermark to the files rendered in the HTML5 Viewer. By default, the user's email is applied as the file's watermark. You can reconfigure the watermark text in the SDK.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Content / User Storage

The User Storage settings page lets you edit and remove the user content storage quotas. View the available content using the Summary overview available on the main screen. Select **Edit** to override User Storage on an individual level. This takes precedence over organization group or user group storage quota configurations. Select **Delete** to enter a pin and delete a user's content. A pin configuration is in place to protect user content from being deleted by administrators without precaution.

## Content / Remote Storage

The Remote Storage settings page lets you configure the various options for remote file storage of personal content.

Standalone RFS	
SaaS	On-Premise
<p>Use RFS instead of the cloud-based Workspace ONE Database to store your organization's personal content. Benefits include:</p> <ul style="list-style-type: none"> <li>Addressing security concerns about storing private information in the cloud.</li> <li>Meeting requirements to utilize the Content Rendering Engine.</li> </ul>	<p>Use RFS instead of the Workspace ONE Server to store your organization's personal content. Benefits include:</p> <ul style="list-style-type: none"> <li>Meeting requirements to utilize the Content Rendering Engine.</li> <li>Leveraging existing storage infrastructure.</li> <li>Complying with physical data storage regulatory requirements.</li> <li>Minimizing Internet bound bandwidth consumption.</li> </ul>
RFS with CRE	
<ul style="list-style-type: none"> <li>Rendering of personal content files store in RFS in an HTML5 enabled browser.</li> <li>Sharing content without losing control of data.</li> <li>Protecting sensitive documents with a dynamic watermark.</li> <li>Enforcing "View Only" restrictions for content shared with external parties.</li> <li>Improving usability.</li> </ul>	

## Content / Content Viewer

The Content Viewer settings pages lets you configure the various options for the Content Viewer.

If you do not have an RFS instance set up, select **Configure**.

If you previously installed an RFS instance, select **Add**.

Enter the following information about your RFS node:

1. Navigate to **Content > Settings > Content Viewer**, at a Customer level Organization Group.
2. Select **Configure** if configuring the first CRE instance. After the first instance, the option switches to **Add**.
3. On the **Assignment** screen, select an **RFS Node** from the same data-center or network as CRE to have content rendered in the SSP. Limit one CRE instance per RFS node. Select **Next**.
4. Configure the fields on the **Details** screen. Select **Next**.

Setting	Description
<b>Name</b>	Provide a name for the content viewer. This name displays in the UEM Console.
<b>CRE URL</b>	Provide the externally accessible URL for the CRE you set up on your server.

5. Assign a **Public SSL Certificate** on the **Authentication** screen to establish trust between RFS and the Content Viewer. Select **Next**.
6. Select the **Edit** icon  from the actions menu for the CRE node.
7. Select the **Advanced** tab.
  - Copy and record the **Client ID**.
  - Select **Generate PEM**. Copy and paste the text into a text editor, saving it as a .pem file.  
**Example:** Save the text as **CreClientCertificate.pem**.
8. Review the **Summary** screen. Select **Save** after reviewing the newly configured settings.
9. Select **Download** under the **Installer** column and follow the prompts.
10. Use the manual utility to upload the SSL certificate to the RFS Tokens server selected during configuration.

## Content / Advanced / File Extensions

The File Type settings page lets you configure the various options for supported file types for personal content.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Allowed File Extensions</b>	Specify the file type allowed for upload and repository sync.
<b>Apply Restrictions to Personal Content</b>	Set to <b>Yes</b> to apply restrictions to personal content.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Content / Advanced / Onboarding

The Onboarding settings page lets you configure the various options for required content in the VMware Content Locker.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Onboarding</b>	Enable to lock the end user's iOS device in the VMware Content Locker application until the end user has completed all required content.
<b>Administrative Unlock Code</b>	Enter the code that allows administrators to unlock iOS devices that are locked in Onboarding.
<b>Entrance Message</b>	Enable to display a message to users when signing in to VMware Content Locker for the first time when onboarding is enabled. <ul style="list-style-type: none"> <li>• <b>Message Text</b> – Enter the message to display as an entrance message.</li> </ul>
<b>Exit Message</b>	Enable to display a message when exiting onboarding mode. <ul style="list-style-type: none"> <li>• <b>Message Text</b> – Enter the message to display as an exit message.</li> </ul>

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

# Chapter 6:

## Email

### **Configuration**

[Email / Configuration on page 127](#)

### **Email Notification**

[Email / Email Notification on page 127](#)

## Email / Configuration

The Email Configuration page lets you configure the various options for using Workspace ONE UEM Mobile Email Management. Mobile Email Management configuration uses a wizard to help you set up email for devices.

## Email / Email Notification

The Email Notification page provides access to the Email Notification Service installer. The ENS provides email notification for AirWatch Inbox and VMware Boxer applications.

Select the **Enable Email Notification** check box to enable the email notification for AirWatch Inbox or VMware Boxer mail clients.

### General

- **Cloud Notification Service URL** - Enter the AirWatch cloud notification service URL. This is the URL to which the Email Notification Service (ENS) server sends notifications.

On selecting **Save**, the **Download Email Notification Installer** link appears on the screen.

Select the **Download Email Notification Installer** link, create a password for Email Notification Certificate, and download the installer to the local folder.

### Advanced

View the generated certificates and API key on the advanced page.

- **Regenerate Certificates** - Select this to generate a new certificate.
- **Regenerate API Key** - Select this to generate a new API key.

# Chapter 7:

## Telecom

### General

[Telecom / General on page 129](#)

### Jasper Integration

[Telecom / Jasper Integration on page 129](#)

## Telecom / General

The Telecom General page displays the current Telecom configuration and lets you change the various options available through Telecom Management.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.
- **Enable Telecom Management** – Enable to use the Workspace ONE UEM Telecom Management system and configure the various options.

Changing the Pooled Plan Usage ranges in the System Settings menu only configures how users' plan consumption is displayed on the Telecom Dashboard, and is for reference purposes only. Data presented and configured in the UEM console may not reflect actual carrier billing.

Workspace ONE UEM default values for Usage Ranges are:

Range	Calls	Data	Messages
Very Low	0 to 499 minutes	0 up to 1 GB	0 to 499 messages
Low	500 to 999 minutes	1 up to 2 GB	500 to 999 messages
Medium	1000 to 1499 minutes	2 up to 3 GB	1000 to 1499 messages
High	1500 to 1999 minutes	3 up to 4 GB	1500 to 1999 messages
Very High	2000+ minutes	4+ GB	2000+ messages

### Apple iOS

- **Change These Settings** – Selecting this option opens [Devices & Users / Apple / Apple iOS / Agent Settings on page 58](#).

### Android

- **Change These Settings** – Selecting this opens [Devices & Users / Android / Agent Settings on page 50](#).

### Privacy

- **Change These Settings** – Selecting this opens [Devices & Users / General / Privacy on page 46](#).
- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Telecom / Jasper Integration

The Telecom Jasper Integration page lets you connect your Jasper account to manage SIM cards through Workspace ONE UEM.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Setting	Description
<b>Jasper Integration</b>	Enable to use the Jasper Integration system to configure the user settings.
<b>Username</b>	Enter the username associated with your Jasper account.
<b>Password</b>	Enter the password associated with your Jasper account.
<b>API Key</b>	Enter your API key generated from your Jasper console.
<b>API URL</b>	Enter the API URL associated with your Jasper account.

- **Test Connection** – Select to check if there is connectivity between the Workspace ONE UEM console and the Jasper account.
- **Clear Account** – Select to clear all the Jasper Integration settings.
- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

# Chapter 8:

## Admin

### **Custom Attribute Settings**

[Admin / Custom Attribute Settings on page 132](#)

### **Product Provisioning**

[Admin / Product Provisioning on page 132](#)

### **UEIP**

[Admin / Product Improvement Programs on page 133](#)

## Admin / Custom Attribute Settings

When custom attribute auditing is enabled through this system settings page, the Workspace ONE UEM console creates a log record any time the value of a custom attribute for a device is changed. The record contains the device ID, attribute ID, original values and new values, and the date/time it was modified. Access these records through **Device > Custom Attributes – Search > Change Report API**.

## Admin / Product Improvement Programs

VMware's Product Improvement Programs give you the opportunity to impact the quality and effectiveness of our products. Our programs enable our Research & Development team to test on a scrubbed version of our customers' production data, which is essential to ensuring our customers' real-world needs are being met.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Settings	Description
<b>Participate in VMware's Product Quality Improvement Program</b>	<p>Select <b>Yes</b> to influence the experience users encounter while interacting with our products. By opting in to this program, you help us to run critical tests utilizing an anonymous and sanitized version of your production data.</p> <p>Your participation is essential to helping our team ensure your experience using our products is always the best it can be.</p> <p>To learn more about this program, see <a href="https://resources.workspaceone.com/view/9yfk6r2pzldhjlhrz9">https://resources.workspaceone.com/view/9yfk6r2pzldhjlhrz9</a>.</p>
<b>Participate in VMware's User Experience Improvement Program</b>	<p>Select <b>Yes</b> to contribute technical information related to the performance, configuration, and use of Workspace ONE UEM. Your participation improves and benchmarks our products and services, fixes problems, and help us to advise customers on the usage of our software.</p> <p>The data is used by VMware and its service providers strictly on an aggregated basis.</p>

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Admin / Product Provisioning

The Product Provisioning page is where you can enable Job Statistics logging to record each job action performed as part of product provisioning.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Settings	Description
<b>Enable Job Statistics</b>	Enable to record each action performed in a job for product provisioning. Such statistics include actions such as "Job Received" and "Job Complete."
<b>Display Offline Provisioning Help</b>	Enable to turn on a button that displays on the Device Details Page under Products. When this button is selected, the Workspace ONE UEM console creates an offline .zip (or a tar.gz file depending on the platform) containing all of the products or product set jobs and components. Download this .zip file for use offline.

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.

## Admin / Product Improvement Programs

VMware's Product Improvement Programs give you the opportunity to impact the quality and effectiveness of our products. Our programs enable our Research & Development team to test on a scrubbed version of our customers' production data, which is essential to ensuring our customers' real-world needs are being met.

- **Current Setting** – Select whether to **Inherit** or **Override** the displayed settings. Inherit means use the settings of the current organization group's parent OG, while Override enables the settings for editing so you can modify the current OG's settings directly.

Settings	Description
<b>Participate in VMware's Product Quality Improvement Program</b>	<p>Select <b>Yes</b> to influence the experience users encounter while interacting with our products. By opting in to this program, you help us to run critical tests utilizing an anonymous and sanitized version of your production data.</p> <p>Your participation is essential to helping our team ensure your experience using our products is always the best it can be.</p> <p>To learn more about this program, see <a href="https://resources.workspaceone.com/view/9yfk6r2pzldhjlhrz9">https://resources.workspaceone.com/view/9yfk6r2pzldhjlhrz9</a>.</p>
<b>Participate in VMware's User Experience Improvement Program</b>	<p>Select <b>Yes</b> to contribute technical information related to the performance, configuration, and use of Workspace ONE UEM. Your participation improves and benchmarks our products and services, fixes problems, and help us to advise customers on the usage of our software.</p> <p>The data is used by VMware and its service providers strictly on an aggregated basis.</p>

- **Child Permission** – Select the available behavior of child organization groups that exist below the currently selected organization group. *Inherit only* means child OGs are only allowed to inherit these settings. *Override only* means they override the settings, and *Inherit or Override* means you can choose to inherit or override settings in child OGs that exist below the currently selected OG.