

Setting Up Horizon 7 for Linux Desktops

Modified on 06 SEP 2018

VMware Horizon 7 7.6



vmware®

You can find the most up-to-date technical documentation on the VMware website at:

<https://docs.vmware.com/>

If you have comments about this documentation, submit your feedback to

docfeedback@vmware.com

VMware, Inc.
3401 Hillview Ave.
Palo Alto, CA 94304
www.vmware.com

Copyright © 2016, 2018 VMware, Inc. All rights reserved. [Copyright and trademark information.](#)

Contents

Setting Up VMware Horizon 7 for Linux Desktops 6

1 Features and System Requirements 7

Features of Horizon Linux Desktops 7

Overview of Configuration Steps for Horizon 7 for Linux Desktops 12

System Requirements For Horizon 7 for Linux 14

Virtual Machine Settings for 2D and vSGA Graphics 23

2 Preparing a Linux Virtual Machine for Desktop Deployment 27

Create a Virtual Machine and Install Linux 27

Prepare a Linux Machine for Remote Desktop Deployment 28

Install Dependency Packages for Horizon Agent 30

3 Setting Up Active Directory Integration for Linux Desktops 33

Integrating Linux with Active Directory 33

Setting Up Single Sign-On and Smart Card Redirection 36

4 Setting Up True SSO for Linux Desktops 39

Configure True SSO on RHEL/CentOS 7.x Desktops 39

5 Setting Up Graphics for Linux Desktops 42

Configure Supported RHEL Distributions for vGPU 42

Install the VIB for the NVIDIA GRID vGPU Graphics Card on the ESXi Host 43

Configure a Shared PCI Device for vGPU on the Linux Virtual Machine 44

Install the NVIDIA GRID vGPU Display Driver 45

Verify That the NVIDIA Display Driver Is Installed 47

Configure RHEL 6 for vDGA 48

Enable DirectPath I/O for NVIDIA GRID on a Host 48

Add a vDGA Pass-Through Device to a RHEL 6 Virtual Machine 49

Install the NVIDIA Display Driver for vDGA 50

Verify That the NVIDIA Display Driver Is Installed 51

Configure RHEL 7.x for vSGA 52

Install the VIB for the NVIDIA Graphics Card for vSGA on the ESXi Host 52

Configure 3D Capabilities for vSGA on the Linux Virtual Machine 53

Verify that vSGA is Running on a Linux Virtual Machine 54

6 Installing Horizon Agent 56

- Install Horizon Agent on a Linux Virtual Machine 56
- install_viewagent.sh Command-Line Options 57
- Configure the Certificate for Linux Agent 59
- Upgrading the Horizon Agent on a Linux Virtual Machine 60
- Upgrade Horizon Agent on a Linux Virtual Machine 61
- Uninstall Horizon 7 for Linux Machines 62

7 Configuration Options for Linux Desktops 63

- Setting Options in Configuration Files on a Linux Desktop 63
- Using Smart Policies 72
 - Requirements for Smart Policies 72
 - Installing User Environment Manager 72
 - Configuring User Environment Manager 73
 - Horizon Smart Policy Settings 73
 - Adding Conditions to Horizon Smart Policy Definitions 74
 - Create a Horizon Smart Policy in User Environment Manager 74
- Example Blast Settings for Linux Desktops 76
- Examples of Client Drive Redirection Options for Linux Desktops 77
- Suppress the vSphere Console Display of a Linux Desktop 77

8 Create and Manage Linux Desktop Pools 78

- Create a Manual Desktop Pool for Linux 78
- Manage Desktop Pool for Linux 79
- Create an Automated Full-Clone Desktop Pool for Linux 81
- Create an Instant-Clone Floating Desktop Pool for Linux 83
- Broker PowerCLI Commands 86

9 Bulk Deployment of Horizon 7 for Manual Desktop Pools 89

- Overview of Bulk Deployment of Linux Desktops 89
- Overview of Bulk Upgrade of Linux Desktops 91
- Create a Virtual Machine Template for Cloning Linux Desktop Machines 92
- Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops 94
- Sample Script to Clone Linux Virtual Machines 94
- Sample Script to Join Cloned Virtual Machines to AD Domain 98
- Sample Script to Join Cloned Virtual Machines to AD Domain Using SSH 101
- Sample Script to Upload Configuration Files to Linux Virtual Machines 105
- Sample Script to Upload Configuration Files to Linux Virtual Machines Using SSH 108
- Sample Script to Upgrade Horizon Agent on Linux Desktop Machines 113
- Sample Script to Upgrade Horizon Agent on Linux Virtual Machines Using SSH 117
- Sample Script to Perform Operations on Linux Virtual Machines 123

10 Troubleshooting Linux Desktops 127

- Using Horizon Help Desk Tool in Horizon Console 127
 - Start Horizon Help Desk Tool in Horizon Console 128
 - Troubleshooting Users in Horizon Help Desk Tool 128
 - Session Details for Horizon Help Desk Tool 130
 - Session Processes for Horizon Help Desk Tool 134
 - Troubleshoot Linux Desktop Sessions in Horizon Help Desk Tool 135
- Collect Diagnostic Information for Horizon 7 for Linux Machine 136
- Troubleshooting Copy and Paste between Remote Desktop and Client Host 136
- View Agent Fails to Disconnect on an iPad Pro Horizon Client 137
- SLES 12 SP1 Desktop Does Not Auto-Refresh 137
- SSO Fails to Connect to a PowerOff Agent 137
- Unreachable VM After Creating a Manual Desktop Pool for Linux 138

Setting Up VMware Horizon 7 for Linux Desktops

The *Setting Up Horizon 7 for Linux Desktops* document provides information about setting up a Linux virtual machine for use as a VMware Horizon[®] 7 for Linux desktop. The information includes preparing the Linux guest operating system, installing Horizon Agent on the virtual machine, and configuring the machine in Horizon 7 Administrator for use in a Horizon 7 deployment.

Intended Audience

This information is intended for anyone who wants to configure and use remote desktops that run on Linux guest operating systems. The information is written for experienced Linux system administrators who are familiar with virtual machine technology and data center operations.

Features and System Requirements

1

With Horizon 6 or later, users can connect to remote desktops that run the Linux operating system.

This chapter includes the following topics:

- [Features of Horizon Linux Desktops](#)
- [Overview of Configuration Steps for Horizon 7 for Linux Desktops](#)
- [System Requirements For Horizon 7 for Linux](#)

Features of Horizon Linux Desktops

Horizon 7 version 7.6 introduces several new features for Linux desktops.

The following new features are supported beginning with Horizon 7 version 7.6 release for Linux desktops.

- True SSO (single sign-on) support on the RHEL/CentOS 7 desktops.
- Additional platform support for Ubuntu 18.04, RHEL/CentOS 6.10, and RHEL/CentOS 7.5.
- Instant clone support for RHEL 7.1 and later versions.

The following list presents the key features for Horizon Linux desktops.

True SSO Support Beginning with Horizon 7 version 7.6 release, True SSO is supported on RHEL/CentOS 7 desktops. See [Chapter 4 Setting Up True SSO for Linux Desktops](#).

Horizon Smart Policies Beginning with Horizon 7 version 7.5 release, you can use VMware User Environment Manager™ 9.4 or later to create Horizon Smart Policies that control the behavior of the USB redirection, clipboard redirection, and client drive redirection features on specific remote Linux desktops. See [Using Smart Policies](#).

Help Desk Tool Horizon Help Desk Tool is a Web application that is available for troubleshooting Linux desktop sessions, beginning with Horizon 7 version 7.5 release. You can use Horizon Help Desk Tool to get the status of Horizon 7 user sessions and to perform troubleshooting and maintenance operations. See [Using Horizon Help Desk Tool in Horizon Console](#).

Network Intelligence Support for VMware Blast

Beginning with the release of Horizon 7 version 7.5 for Linux desktop, the Network Intelligence transport is supported for VMware Blast. It is enabled by default.

When User Datagram Protocol (UDP) is enabled, Blast establishes both Transmission Control Protocol (TCP) and UDP connections. Based on the current network conditions, Blast dynamically chooses one of the transports for transmitting data to provide the best user experience. For example, in a local area network, TCP performs better than UDP, and so Blast chooses TCP to transport data. Similarly, in a wide area network (WAN), UDP performance is better than TCP and Blast chooses the UDP transport in that environment.

If one of the inline components used does not support UDP, Blast establishes a TCP connection only. For example, if your connection is using the Blast Security Gateway component of the Horizon Connection Server or Security Server, only a TCP connection is established. Even if both client and agent enabled UDP, the connection uses TCP because Blast Security Gateway does not support UDP. If users are connecting from outside the corporate network, the UDP component requires the VMware Unified Access Gateway (formerly called Access Point), which supports UDP.

Use the following information to establish a UDP-based Blast connection.

- If the client connects to a Linux desktop directly, enable the UDP in both the client and agent. UDP is enabled by default in both the client and agent.
- If the client connects to a Linux desktop using Unified Access Gateway, enable UDP in the client, agent, and Unified Access Gateway.

Active Directory Integration with PBIS Open

Beginning with Horizon 7 version 7.4 release, Linux-based desktops can authenticate with Active Directory using PowerBroker Identity Services Open (PBISO). This feature is supported only on Ubuntu 14.04, 16.04, and 18.04 systems. See the PowerBroker Identity Services Open (PBISO) Authentication section in [Integrating Linux with Active Directory](#) for more information.

Instant-Clone Floating Desktop Pool

Beginning with Horizon 7 version 7.4 release, you can create instant-clone floating desktop pools for Linux desktops. This feature is supported only on systems with Ubuntu 14.04/16.04/18.04, or RHEL 7.1 or later installed. For more information, see [Create an Instant-Clone Floating Desktop Pool for Linux](#).

Automated Full-Clone Desktop Pool

Beginning with Horizon 7 version 7.0.2 release, you can create automated full-clone desktop pools for Linux desktops.

Manual Desktop Pool

Machine source.

- Managed Virtual Machine - Machine source of the vCenter virtual machine. A managed virtual machine is supported for new and upgrade deployment.
- Unmanaged Virtual Machine - Machine source of other sources. An unmanaged virtual machine is only supported when the upgrade is from an unmanaged virtual machine deployment.

Note To ensure the best possible performance, do not use an unmanaged virtual machine.

Multiple Monitors

- vDGA/vGPU desktop supports a maximum resolution of 2560x1600 on four monitors.
- 2D/vSGA desktop on VMware vSphere® 6.0 or later supports a maximum resolution of 2048x1536 on four monitors or a maximum resolution of 2560x1600 on three monitors.

For Ubuntu 14.04, 16.04, and 18.04, you must use Gnome, KDE, or the MATE desktop environment to use the multiple monitors feature. See <http://kb.vmware.com/kb/2151294> for more information.

For SLES 12 SP1, you must use the default package with kernel level kernel-default-3.12.49-11.1. If you upgraded the package, the multi-monitor feature fails and the desktop is shown in one monitor.

VMware Horizon HTML Access™ does not support the multi-monitor feature in Horizon 7 for Linux desktops.

Lossless PNG

Images and videos that are generated on a desktop are rendered on the client device in a pixel-exact manner.

H.264 Encoder

H.264 can improve the Blast Extreme performance for a Horizon desktop, especially under a low-bandwidth network. If the client side disabled H.264, Blast Extreme automatically falls back to JPEG/PNG encoding.

From Horizon 7 version 7.3 for Linux release, hardware H.264 encoder support is added with the software H.264 encoder support. The hardware H.264 support has the following requirements.

- The vGPU is configured with the NVIDIA graphics card.
- The NVIDIA driver 384 series or later is installed in the NVIDIA graphics card.

When the system meets the preceding requirements, Horizon 7 for Linux uses the hardware H.264 encoder. Otherwise, the software H.264 encoder is used.

3D Graphics

The 3D graphic feature supports the following combinations of Linux versions and graphics cards:

- vSGA is supported on RHEL 7 Workstation x64 with NVIDIA GRID K1 or K2 graphics cards.
- vDGA is supported on RHEL 6 Workstation x64 with NVIDIA GRID K1 or K2 graphics cards.
- vGPU is supported on RHEL 6 Workstation x64 with NVIDIA Maxwell M60 graphics cards.
- vGPU is supported on RHEL 7 Workstation x64 with NVIDIA Maxwell M60 graphics cards.
- vGPU is supported on RHEL 6 Workstation x64 with NVIDIA M6 graphics cards.
- vGPU is supported on RHEL 7 Workstation x64 with NVIDIA M6 graphics cards.

3Dconnexion Mouse

The 3Dconnexion mouse is supported beginning with Horizon 7 version 7.4 for Linux release. To begin using your 3Dconnexion mouse, you must install the appropriate device driver and pair the mouse using the Connect USB Device menu on your Linux desktop.

Clipboard Redirection

With the clipboard redirection feature, you can copy and paste a rich text or a plain text between a client host and a remote Linux desktop. You can set the copy/paste direction and the maximum text size using Horizon Agent options. This feature is enabled by default. You can disable it during installation.

Single Sign-on

Single sign-on (SSO) is supported on the following Linux distributions.

- RHEL 6/7 Workstation x64
- CentOS 6/7 x64
- SLED 11 SP3/SP4 x64
- Ubuntu 14.04/16.04/18.04 x64

Smart Card Redirection with SSO

Smart card redirection is supported on RHEL 6 Workstation x64. Personal Identity Verification (PIV) cards and Common Access Cards (CAC) are supported. Mac client is not supported.

Audio-in

Audio input redirection from a client host to a remote Linux desktop is supported. This feature is not based on the USB redirection function. If you want this feature enabled, you must select it during installation. You must select the system default audio in device "PulseAudio server (local)" in your application for the audio input. This feature is supported on the following Linux distributions.

- Ubuntu 14.04 x64 with MATE, KDE, or Gnome Fallback (Metacity) desktop environment
- Ubuntu 16.04 x64 with MATE or Gnome Flashback (Metacity) desktop environment
- Ubuntu 18.04 x64 with MATE or Gnome Ubuntu desktop environment
- RHEL 7 Workstation x64 with KDE or Gnome desktop environment

Audio-out

Audio output redirection is supported. This feature is enabled by default. To disable this feature, you must set the `RemoteDisplay.allowAudio` option to **false**. Beginning with Horizon 7 version 7.2 release, VMware Horizon HTML Access accessed using Chrome and Firefox browsers provides audio-out support for Linux desktops.

Client Drive Redirection

The Client Drive Redirection (CDR) feature is available beginning with the Horizon 7 version 7.2 release. When you enable the CDR feature, your local system's shared folders and drives become available for you to access. You use the `tsc\client` folder that is located in your home directory in the remote Linux desktop. To use this feature, you must install the CDR components.

USB Redirection

The USB Redirection feature is available beginning with the Horizon 7 version 7.2 release. The feature gives you access to locally attached USB devices from remote Linux desktops. You must install the USB Redirection components and USB VHCI driver kernel module to use the USB feature. Ensure that you have been granted sufficient privileges to use the USB device that you want to redirect.

Note USB 3.0 protocol is supported in Horizon 7 version 7.2 release.

Keyboard Layout and Locale Synchronization

This feature specifies whether to synchronize a client's system locale and current keyboard layout with the Horizon Linux Agent desktops. When this setting is enabled or not configured, synchronization is allowed. When this setting is disabled, synchronization is not allowed.

This feature is supported only for VMware Horizon for Windows, and only for the English, French, German, Japanese, Korean, Spanish, Simplified Chinese and Traditional Chinese locales.

K Desktop Environment Beginning with Horizon 7 version 7.2 release, the K Desktop Environment (KDE) is supported. The following are the currently supported Linux distributions.

- CentOS 6 and 7
- RHEL 6 and 7
- Ubuntu 14.04, 16.04, and 18.04
- SLED 11 SP4

MATE Desktop Environment As of Horizon 7 version 7.3 release, the MATE Desktop Environment is supported on the following Linux distributions.

- Ubuntu 14.04
- Ubuntu 16.04
- Ubuntu 18.04

FIPS 140-2 Mode The Federal Information Processing Standard (FIPS) 140-2 mode support, although not yet validated with the NIST Cryptographic Module Validation Program (CMVP), is available beginning with Horizon 7 version 7.2.

The Horizon 7 Agent for Linux implements cryptographic modules that are designed for FIPS 140-2 compliance. These modules were validated in operational environments listed in CMVP certificate #2839 and #2866, and were ported to this platform. However, the CAVP and CMVP testing requirement to include the new operational environments in VMware's NIST CAVP and CMVP certificates remains to be completed on the product roadmap.

Note The Transport Layer Security (TLS) protocol version 1.2 is required to support FIPS 140-2 mode.

Linux desktops and desktop pools have the following limitations:

- Virtual Printing, location-based printing, and Real-Time Video are not supported.
- The VMware HTML Access file transfer feature is not supported.

Note When a security server is used, port 22443 must be open in the internal firewall to allow traffic between the security server and the Linux desktop.

Overview of Configuration Steps for Horizon 7 for Linux Desktops

When you install and configure Horizon 7 for Linux desktops, you must follow a different sequence of steps depending on whether you install 2D graphics or 3D graphics on the virtual machines.

2D Graphics - Overview of Configuration Steps

For 2D graphics, take the following steps:

- 1 Review the system requirements for setting up a Horizon 7 for Linux deployment. See [System Requirements For Horizon 7 for Linux](#).
- 2 Create a virtual machine in vSphere and install the Linux operating system. See [Create a Virtual Machine and Install Linux](#).
- 3 Prepare the guest operating system for deployment as a desktop in a Horizon 7 environment. See [Prepare a Linux Machine for Remote Desktop Deployment](#).
- 4 Configure the Linux guest operating system to authenticate with Active Directory. This step is implemented with 3rd-party software, based on the requirements in your environment. See [Integrating Linux with Active Directory](#) for more information.
- 5 Install Horizon Agent on the Linux virtual machine. See [Install Horizon Agent on a Linux Virtual Machine](#).
- 6 Create a desktop pool that contains the configured Linux virtual machines. See [Create a Manual Desktop Pool for Linux](#).

3D Graphics - Overview of Configuration Steps

You must complete the NVIDIA GRID vGPU, vDGA, or vSGA configuration on the Linux virtual machines before you install Horizon Agent on the machines and deploy a desktop pool in View Administrator.

- 1 Review the system requirements for setting up a Horizon 7 for Linux deployment. See [System Requirements For Horizon 7 for Linux](#).
- 2 Create a virtual machine in vSphere and install the Linux operating system. See [Create a Virtual Machine and Install Linux](#).
- 3 Prepare the guest operating system for deployment as a desktop in a Horizon 7 environment. See [Prepare a Linux Machine for Remote Desktop Deployment](#).
- 4 Configure the Linux guest operating system to authenticate with Active Directory. This step is implemented with 3rd-party software, based on the requirements in your environment. See [Integrating Linux with Active Directory](#) for more information.
- 5 Configure 3D capabilities on your ESXi hosts and the Linux virtual machine. Follow the procedures for the 3D feature you intend to install.
 - See [Configure Supported RHEL Distributions for vGPU](#).
 - See [Configure RHEL 6 for vDGA](#).
 - See [Configure RHEL 7.x for vSGA](#).
- 6 Install Horizon Agent on the Linux virtual machine. See [Install Horizon Agent on a Linux Virtual Machine](#).

- 7 Create a desktop pool that contains the configured Linux virtual machines. See [Create a Manual Desktop Pool for Linux](#).

Bulk Deployment

With View Administrator, you can only deploy Linux virtual machines in a manual desktop pool. With vSphere PowerCLI, you can develop scripts that automate the deployment of a pool of Linux desktop machines. See [Chapter 9 Bulk Deployment of Horizon 7 for Manual Desktop Pools](#).

System Requirements For Horizon 7 for Linux

To install Horizon 7 for Linux, your Linux system must meet certain requirements for the operating system, Horizon 7, and vSphere platform.

Supported Linux Versions for Horizon Agent

[Table 1-1](#) lists the Linux operating systems that are supported on virtual machines in a desktop pool.

Table 1-1. Supported Linux Operating Systems for Horizon Agent

Linux Distribution	Architecture
Ubuntu 14.04, 16.04, and 18.04	x64
Note You must apply one of the solutions described in VMWare KB article http://kb.vmware.com/kb/2151294 .	
Ubuntu 12.04	x64
RHEL 6.6, 6.7, 6.8, 6.9, 6.10, 7.2, 7.3, 7.4, and 7.5	x64
CentOS 6.6, 6.7, 6.8, 6.9, 6.10, 7.2, 7.3, 7.4, and 7.5	x64
NeoKylin 6 Update 1	x64
SLED 11 SP3/SP4	x64
SLED 12 SP1/SP2/SP3	x64
SLES 12 SP1/SP2/SP3	x64

Note Linux agent has dependency packages on some Linux distributions. See [Install Dependency Packages for Horizon Agent](#) for more information.

Required Platform and Horizon 7 Software Versions

To install and use Horizon 7 for Linux, your deployment must meet certain requirements for the vSphere platform, Horizon 7, and the Horizon Client software.

Table 1-2. Required Platform and Horizon 7 Software Versions

Platform and Software	Supported Versions
vSphere platform version	<ul style="list-style-type: none"> ■ vSphere 6.0 U2 or a later release ■ vSphere 6.5 U1 or a later release ■ vSphere 6.7 or later release
Horizon environment	<ul style="list-style-type: none"> ■ Horizon Connection Server 7.6
Horizon Client software	<ul style="list-style-type: none"> ■ Horizon Client 4.9.0 for Android ■ Horizon Client 4.9.0 for Windows ■ Horizon Client 4.9.0 for Linux ■ Horizon Client 4.9.0 for Mac OS X ■ Horizon Client 4.9.0 for iOS (iPad Pro) ■ HTML Access 4.9.0 on Chrome, Firefox, and Internet Explorer ■ Zero clients are not supported

TCP/UDP Ports Used by Linux Virtual Machines

Horizon Agent and Horizon Clients use TCP or UDP ports for network access between each other and various Horizon server components.

Table 1-3. TCP/UDP Ports Used by Linux Virtual Machines

Source	Port	Target	Port	Protocol	Description
Horizon Client	*	Linux Agent	22443	TCP/UDP	Blast if Blast Security Gateway is not used
Security Server, Horizon Connection Server, or Access Point appliance	*	Linux Agent	22443	TCP/UDP	Blast if Blast Security Gateway is used
Horizon Agent	*	Horizon Connection Server	4001, 4002	TCP	JMS SSL traffic.

Note For more information on TCP and UDP ports used by clients, see TCP and UDP Ports Used by Clients and Horizon Agent in the *Horizon Client and Agent Security* in document.

To allow users to connect to their Linux desktops, the desktops must be able to accept incoming TCP connections from Horizon Client devices, security server, and View Connection Server.

On Ubuntu and Kylin distributions, the `iptables` firewall is configured by default with an input policy of `ACCEPT`.

On RHEL and CentOS distributions, where possible, the Horizon Agent installer script configures the `iptables` firewall with an input policy of `ACCEPT`.

Make sure that `iptables` on an RHEL or CentOS guest operating system has an input policy of `ACCEPT` for new connections from the Blast port, 22443.

When the BSG is enabled, client connections are directed from a Horizon Client device through the BSG on a security server or View Connection Server to the Linux desktop. When the BSG is not enabled, connections are made directly from the Horizon Client device to the Linux desktop.

Verify the Linux Account Used by Linux Virtual Machines

[Table 1-4](#) lists the account name and account type used by Linux virtual machines.

Table 1-4. Account Name and Account Type

Account Name	Account Type	Used By
root	Linux OS built-in	Java Standalone Agent, mksvchanserver, shell scripts
vmwblast	Created by Linux Agent installer	VMwareBlastServer
<current login user>	Linux OS built-in or AD user or LDAP user	Python script

Desktop Environment

Horizon 7 for Linux supports multiple desktop environments on different Linux distributions. [Table 1-5](#) lists the default desktop environments for each Linux distribution and the additional desktop environments supported by Horizon 7 for Linux.

Table 1-5. Supported Desktop Environments

Linux Distribution	Default Desktop Environment	Desktop Environments Supported by Horizon 7 for Linux Desktops
Ubuntu 18.04	Gnome	Gnome Ubuntu, K Desktop Environment (KDE), MATE
Ubuntu 16.04	Unity	Gnome Flashback (Metacity), KDE, MATE
Ubuntu 14.04	Unity	Gnome Fallback (Metacity), KDE, MATE
Ubuntu 12.04	Unity	Unity
RHEL/CentOS 6.x	Gnome	Gnome, KDE
RHEL/CentOS 7.x	Gnome	Gnome, KDE
SLED 11 SP4	Gnome	Gnome, KDE
SLED 12 SP1/SP2/SP3	Gnome	Gnome
SLES 12 SP1/SP2/SP3	Gnome	Gnome
NeoKylin 6 Update 1	Mate	Mate

To change the default desktop environment used on one of the supported Linux distributions, you must use the following steps and commands appropriate for your Linux desktop.

Note Single sign-on (SSO) for KDE and the MATE Desktop Environment only works when your Linux desktop is using the default greeter (login screen). You must install KDE and MATE using the commands listed in [Table 1-6](#).

When using SLED 11 SP3/SP4, RHEL/CentOS 7, and Ubuntu 14.04/16.04/18.04 distributions, SSO fails to unlock a locked KDE session. You must manually enter your password to unlock the locked session.

- 1 Install the supported Linux distribution's operating system with the default desktop environment setting.
- 2 Run the appropriate commands in [Table 1-6](#) for your specific Linux distribution.

Table 1-6. Commands to Install Desktop Environments

Linux Distribution	New Default Desktop Environment	Commands to Change the Default Desktop Environment
RHEL/CentOS 6	KDE	<code># yum groupinstall "X Window System" "KDE Desktop"</code>
RHEL/CentOS 7	KDE	<code># yum groupinstall "KDE Plasma Workspaces"</code>
SLED 11 SP4	KDE	<code># zypper install -t pattern desktop-kde</code>
Ubuntu 14.04/16.04/18.04	KDE	<code># apt install plasma-desktop</code>
Ubuntu 18.04	MATE 1.225	<code># apt install ubuntu-mate-desktop</code>
Ubuntu 16.04	MATE 1.16	<code># apt-add-repository ppa:ubuntu-mate-dev/xenial-mate</code> <code># apt update</code> <code># apt upgrade</code> <code># apt install mate</code> <code># apt install ubuntu-mate-themes</code>
Ubuntu 14.04	MATE 1.8	<code># apt-add-repository ppa:ubuntu-mate-dev/ppa</code> <code># apt-add-repository ppa:ubuntu-mate-dev/trusty-mate</code> <code># apt-get update</code> <code># apt-get upgrade</code> <code># apt-get install mate</code>
Ubuntu 16.04	Gnome Flashback (Metacity)	<code># apt install gnome-session-flashback</code>
Ubuntu 14.04	Gnome Fallback (Metacity)	<code># apt-get install gnome-session-fallback</code>

- 3 To begin using the new default desktop environment, restart the desktop.

If you enabled SSO on a Linux desktop that has multiple desktop environments installed, use the following information to select the desktop environment to use in an SSO session.

- For Ubuntu 14.04/16.04/18.04 and RHEL/CentOS 7.x, use the information in [Table 1-7](#) to set the `SSODesktopType` option in the `/etc/vmware/viewagent-custom.conf` file to specify the desktop environment to use with SSO.

Table 1-7. SSODesktopType Option

Desktop Type	SSODesktopType Option Setting
MATE	<code>SSODesktopType=UseMATE</code>
GnomeUbuntu	<code>SSODesktopType=UseGnomeUbuntu</code>
GnomeFlashback	<code>SSODesktopType=UseGnomeFlashback</code>
KDE	<code>SSODesktopType=UseKdePlasma</code>
GnomeClassic	<code>SSODesktopType=UseGnomeClassic</code>

- For RHEL/CentOS 6.x and SLED 11 SP3/SP4, for the SSO login session to use KDE, remove all the desktop startup files, except for the KDE startup file, from the `/usr/share/xsession` directory. Use the following set of commands as an example.

```
# cd /usr/share/xsessions
# mkdir backup
# mv *.desktop backup
# mv backup/kde*.desktop ./
```

After the initial setup, the end user must log out or reboot their Linux desktop to make KDE as the default desktop in their next SSO session.

If you disabled SSO on a Linux desktop that has multiple desktop environments installed, you do not need to perform any of the previously described steps. The end users have to select their desired desktop environment when they log in to that Linux desktop.

Network Requirements

VMware Blast Extreme supports both User Datagram Protocol (UDP) and Transmission Control Protocol (TCP). Network conditions affect the performances of UDP and TCP. To receive the best user experience, select UDP or TCP based on the network condition.

- Select TCP if the network condition is good, such as in a local area network (LAN) environment.
- Select UDP if the network condition is poor, such as in a wide area network (WAN) environment with packet loss and time delay.

Use a network analyzer tool, such as Wireshark, to determine whether VMware Blast Extreme is using TCP or UDP. Use the following set of steps, which use Wireshark, as a reference example.

- 1 Download and install Wireshark on your Linux VM.

For RHEL/CentOS 6:

```
sudo yum install wireshark
```

For Ubuntu 14.04/16.04/18.04:

```
sudo apt install tshark
```

For SLE 11/12:

```
sudo zypper install wireshark
```

- 2 Connect to the Linux desktop using VMware Horizon Client.
- 3 Open a terminal window and run the following command, which displays the TCP package or UDP package used by VMware Blast Extreme.

```
sudo tshark -i any | grep 22443
```

USB Redirection and Client Drive Redirection (CDR) features are sensitive to network conditions. If the network condition is bad, such as a limited bandwidth with time delay and packet loss, the user experience becomes poor. In such condition, the end user might experience one of the following.

- Copying remote files can be slow. In this situation, transmit smaller sized files instead.
- USB device does not appear in the remote Linux desktop.
- USB data does not transfer completely. For example, if you copy a large file, you might get a file smaller in size than the original file.

VHCI Driver for USB Redirection

The USB redirection feature is supported beginning with Horizon 7 version 7.1 for Linux desktops. The feature has a dependency on the USB Virtual Host Controller Interface (VHCI) kernel driver. You must patch the VHCI driver to support USB 3.0.

The Horizon for Linux installer includes the VHCI driver binary for the default kernel of the supported Linux distributions. The installer installs the VHCI driver when the USB redirection feature is selected. [Table 1-8](#) lists the default kernel versions that the Horizon for Linux installer installs.

Table 1-8. Default Kernel Versions

Linux Distribution	Default Kernel Version
RHEL/CentOS 6.9	2.6.32-696.el6.x86_64
RHEL/CentOS 6.10	2.6.32-754.el6.x86_64
RHEL/CentOS 7.5	3.10.0-862.el7.x86_64
SUSE 12 SP2	4.4.21-69-default
Ubuntu 14.04	3.13.0-24-generic

Table 1-8. Default Kernel Versions (Continued)

Linux Distribution	Default Kernel Version
Ubuntu 16.04	4.4.0-21-generic
Ubuntu 18.04	4.15.0-20-generic

If your Linux system uses a kernel version that is different from the default versions included with the Horizon for Linux installer, you must download the USB VHCI source code from <https://sourceforge.net/projects/usb-vhci/files/linux%20kernel%20module/>. You must then compile the VHCI driver source code and install the resulting binary on your Linux system.

Note The VHCI driver installation must be done before the installation of Horizon for Linux.

After you download the latest version of the USB VHCI driver source code, use the commands in [Table 1-9](#) to compile and install it on your Linux system. For example, if you unpack the installation file, VMware-horizonagent-linux-x86_64-*<version>-<build-number>*.tar.gz, under the /install_tmp/ directory, the *full-path-to-patch-file* is /install_tmp/VMware-horizonagent-linux-x86_64-*<version>-<buildnumber>*/resources/vhci/patch/vhci.patch and the patch command to use is

```
# patch -p1 < /install_tmp/VMware-horizonagent-linux-x86_64-<version>-<build-number>/resources/vhci/patch/vhci.patch
```

Table 1-9. Compile and Install USB VHCI Driver

Linux Distribution	Steps to Compile and Install USB VHCI Driver
Ubuntu 18.04	<ol style="list-style-type: none"> 1 Install the dependency packages. <pre># apt-get install make # apt-get install gcc # apt-get install libelf-dev</pre> 2 Compile and install the VHCI drivers. <pre># tar -xzf vhci-hcd-1.15.tar.gz # cd vhci-hcd-1.15 # patch -p1 < <i>full-path-to-patch-file</i> # make clean && make && make install</pre>
Ubuntu 14.04 Ubuntu 16.04	<p>Compile and install the VHCI drivers.</p> <pre># tar -xzf vhci-hcd-1.15.tar.gz # cd vhci-hcd-1.15 # patch -p1 < <i>full-path-to-patch-file</i> # make clean && make && make install</pre>

Table 1-9. Compile and Install USB VHCI Driver (Continued)

Linux Distribution	Steps to Compile and Install USB VHCI Driver
RHEL/CentOS 6.9/6.10	1 Install the dependency packages.
RHEL/CentOS 7	<pre># yum install gcc-c++ # yum install kernel-devel-\$(uname -r) # yum install kernel-headers-\$(uname -r) # yum install patch</pre>
	2 Compile and install the VHCI drivers.
	<pre># tar -xzvf vhci-hcd-1.15.tar.gz # cd vhci-hcd-1.15 # patch -p1 < full-path-to-patch-file # make clean && make && make install</pre>
SUSE 11 SP4	1 Find out the version of the current kernel package
SUSE 12 SP2	<pre># rpm -qa grep kernel-default-\$(echo \$(uname -r) cut -d '-' -f 1,2)</pre> <p>The output is the name of the kernel package currently installed. If, for example, the package name is <code>kernel-default-3.0.101-63.1</code>, then the current kernel package version is <code>3.0.101-63.1</code>.</p>
	2 Install the dependency packages.
	<p>a For SUSE 11, install the <code>kernel-source</code> and <code>kernel-default-devel</code> packages that match the current kernel; the <code>gcc</code> and the <code>patch</code> packages.</p> <pre># zypper install --oldpackage kernel-source-<kernel-package-version> \ kernel-default-devel-<kernel-package-version> gcc patch</pre> <p>For example:</p> <pre># zypper install --oldpackage kernel-source-3.0.101-63.1 kernel-default- devel-3.0.101-63.1 gcc patch</pre>

Table 1-9. Compile and Install USB VHCI Driver (Continued)

Linux Distribution	Steps to Compile and Install USB VHCI Driver
	<p>b For SUSE 12, install the <code>kernel-devel</code>, <code>kernel-default-devel</code>, <code>kernel-macros</code>, and the <code>patch</code> packages.</p> <pre># zypper install --oldpackage kernel-devel-<kernel-package-version> \ kernel-default-devel-<kernel-package-version> kernel-macros-<kernel-package-version> patch</pre> <p>For example:</p> <pre># zypper install --oldpackage kernel-devel-4.4.21-90.1 kernel-default-devel-4.4.21-90.1 kernel-macros-4.4.21-90.1 patch</pre> <p>3 Compile and install the VHCI drivers.</p> <pre># tar -xzvf vhci-hcd-1.15.tar.gz # cd vhci-hcd-1.15 # patch -p1 < full-path-to-patch-file # mkdir -p linux/\$(echo \$(uname -r) cut -d '-' -f 1)/drivers/usb/core # cp /lib/modules/\$(uname -r)/source/include/linux/usb/hcd.h linux/\$(echo \$(uname -r) cut -d '-' -f 1)/drivers/usb/core # make clean && make && make install</pre>

If your Linux kernel version is changed, you must recompile and reinstall the VHCI driver, but you do not need to reinstall Horizon for Linux.

You can also add Dynamic Kernel Module Support (DKMS) to the VHCI driver using the steps similar to the following example for an Ubuntu 16.04/18.04 system.

- 1 Install the kernel headers.

```
# apt install linux-headers-$(uname -r)
```

- 2 Install dkms using the following command.

```
# apt install dkms
```

- 3 Extract and patch the VHCI TAR file.

```
# tar xzvf vhci-hcd-1.15.tar.gz
# cd vhci-hcd-1.15
# patch -p1 <full-path-to-patch-file>
# cd ..
```

- 4 Copy the extracted VHCI source files to the `/usr/src` directory.

```
# cp -r vhci-hcd-1.15 /usr/src/usb-vhci-hcd-1.15
```

- 5 Create a file named `dkms.conf` and place it in the `/usr/src/usb-vhci-hcd-1.15` directory.

```
# touch /usr/src/usb-vhci-hcd-1.15/dkms.conf
```

- 6 Add the following contents to the `dkms.conf` file.

```
PACKAGE_NAME="usb-vhci-hcd"
PACKAGE_VERSION=1.15
MAKE_CMD_TMPL="make KVERSION=$kernelver"

CLEAN="$MAKE_CMD_TMPL clean"

BUILT_MODULE_NAME[0]="usb-vhci-iocifc"
DEST_MODULE_LOCATION[0]="/kernel/drivers/usb/host"
MAKE[0]="$MAKE_CMD_TMPL"

BUILT_MODULE_NAME[1]="usb-vhci-hcd"
DEST_MODULE_LOCATION[1]="/kernel/drivers/usb/host"
MAKE[1]="$MAKE_CMD_TMPL"

AUTOINSTALL="YES"
```

- 7 Add this VHCI driver in dkms.

```
# dkms add usb-vhci-hcd/1.15
```

- 8 Build the VHCI driver.

```
# dkms build usb-vhci-hcd/1.15
```

- 9 Install the VHCI driver.

```
# dkms install usb-vhci-hcd/1.15
```

Virtual Machine Settings for 2D and vSGA Graphics

When you create certain Horizon 7 for Linux virtual machines, you must change the memory settings and configuration parameters to the minimum values recommended.

Virtual machines that are configured to use NVIDIA vDGA use the NVIDIA physical graphic card. Virtual machines that are configured to use NVIDIA GRID vGPU use the NVIDIA virtual graphic card, which is based on the NVIDIA physical graphic accelerator. You do not need to change the Video Memory (vRAM) settings and configuration parameters for these virtual machines.

Virtual machines that are configured to use 2D or vSGA graphics use the VMware virtual graphic card and you must change the following settings for these types of virtual machines:

- Video Memory (vRAM) settings
- Configuration parameters

- 3D Memory settings
- vCPU and virtual memory settings for performance requirement

Video Memory (vRAM) Settings

When you create a Linux virtual machine in vSphere Client, configure the vRAM size as shown in [Table 1-10](#). Set the vRAM size that is recommended for the number and resolution of the monitors that you configure for the virtual machine.

Table 1-10. Recommended vRAM Settings for 2D or vSGA Graphics

vRAM Size	Number of Monitors	Maximum Resolution
10 MB	1	1600x1200 or 1680x1050
12 MB	1	1920x1440
32 MB	1	2560x1600
48 MB	2	2048x1536
80 MB	2	2560x1600
128 MB	3	2560x1600
128 MB	4	2048x1536

These vRAM sizes are the minimum recommendations. If more resources are available on the virtual machine, set the vRAM to larger values for improved video performance.

10 MB is the minimum vRAM size recommendation for a machine that is configured with a single monitor at the lowest resolution.

You must power off the virtual machine to set the number of displays and the amount of video memory to use, as described in [Create a Virtual Machine and Install Linux](#).

Horizon Connection Server 7 does not automatically configure the vRAM settings on Linux virtual machines like it does on Windows virtual machines. You must manually configure the vRAM settings in vSphere Client.

If a Linux virtual machine is configured with a smaller vRAM size than is recommended, the following issues might occur:

- Desktop sessions might be disconnected right after the initial connection is made.
- Autofit might fail to work. The desktop is then displayed in a small area of the screen.

If a Linux virtual machine's **Number of displays** value is less than the actual required count, one or more monitors display blank for the desktop.

If you encounter an autofit issue with the recommended settings, you can specify a larger vRAM size. vSphere Client permits a maximum vRAM size of 128 MB. If your specified size exceeds 128 MB, you must modify the vmx configuration file manually. The following example specifies a vRAM size of 256 MB:

```
svga.vramSize = "268435456"
```


Configuration Parameters

To display the Linux remote desktop on multiple monitors, you must set certain configuration parameters for the virtual machine. The general steps to set a configuration parameter for a virtual machine are as follows:

- 1 Power off the virtual machine.
- 2 In the vSphere Web Client, right-click the virtual machine and select **Edit Settings**.
- 3 Click the **VM Options** tab and click **Advanced**.
- 4 Click **Edit Configuration** and then **Add Row**.
- 5 Enter the configuration parameter name and value.
- 6 Click **OK** to save the changes.

You must set the following configuration parameters:

- Set `svga.autodetect` to false.

```
svga.autodetect="false"
```

- Calculate the `svga.maxWidth` and `svga.maxHeight` values according to the number and orientation (horizontal or vertical) of the display monitors. The general rule is that the `svga.maxWidth` and `svga.maxHeight` values must be large enough to support all the displays. For example, to support four displays at the maximum resolution of 2560x1600, you must set the following values:

```
svga.maxHeight="3200"
svga.maxWidth="10240"
```

If you have multiple monitors, you must set these configuration parameters. Otherwise, you might encounter one or more of the following problems:

- The desktop is displayed on some of the monitors and the other monitors are blank.
- A keystroke is displayed multiple times.
- The desktop becomes slow.
- The desktop is displayed in a small area of the screen.

Screen Size Limitation of 8192x8192 Monitors

For RHEL 6.8/6.9/6.10/7.3/7.4, CentOS 6.8/6.9/6.10/7.3/7.4, Ubuntu 16.04, SLED 12 SP2/SP3, and SLES 12 SP2/SP3, the maximum screen size for 2D and vSGA is 4096x4096. When you run the `xrandr` command, the first line of the output has `maximum 4096x4096`.

For Ubuntu 18.04, RHEL 7.5, and CentOS 7.5, the maximum screen size for 2D and vSGA is 8192x8192.

For Ubuntu 14.04, the limitation is also introduced if you install the latest patches from the official Ubuntu repositories.

Multiple-monitor connection might require a screen size larger than 4096x4096. To bypass this limitation, use one of the following solutions:

- If you have to use VMware Hardware version 11 (HWv11) or later for your virtual machine, add the following line into the virtual machine's VMX configuration file:

```
mks.enable3d = TRUE
```

With this solution, the Linux operating system can report 3D capabilities to software applications, such as Chrome. However, doing so might impact the Linux system's performance.

- If your virtual machine can use VMware Hardware version 10, use the following line in your virtual machine's VMX file:

```
virtualHW.version = "10"
```

This solution is not applicable for RHEL 6.8 and CentOS 6.8.

To make this solution work on Ubuntu 16.04 systems, you must install the latest patches from the official Ubuntu repositories.

vCPU and Memory Settings

To improve the performance of a 2D or vSGA desktop, set more vCPUs and virtual memory for the Linux virtual machine. For example, set 2 vCPUs and 2 GB of virtual memory.

For the large screen of multiple monitors, such as four monitors, set 4 vCPUs and 4 GB of virtual memory for the virtual machine.

For the video playback purpose in a 2D or vSGA desktop, set 4 vCPUs and 4 GB of virtual memory for the virtual machine.

3D Memory Settings

To improve performance in a vSGA multiple monitor environment, set the **3D Memory** setting for the virtual machine to 1 GB or larger.

Preparing a Linux Virtual Machine for Desktop Deployment

2

Setting up a Linux desktop involves creating a Linux virtual machine and preparing the operating system for remote desktop deployment.

This chapter includes the following topics:

- [Create a Virtual Machine and Install Linux](#)
- [Prepare a Linux Machine for Remote Desktop Deployment](#)
- [Install Dependency Packages for Horizon Agent](#)

Create a Virtual Machine and Install Linux

You create a new virtual machine in vCenter Server for each remote desktop that is deployed in Horizon 7. You must install your Linux distribution on the virtual machine.

Prerequisites

- Verify that your deployment meets the requirements for supporting Linux desktops. See [System Requirements For Horizon 7 for Linux](#).
- Familiarize yourself with the steps for creating virtual machines in vCenter Server and installing guest operating systems. See "Creating and Preparing Virtual Machines" in the *Setting Up Virtual Desktops in Horizon 7* document.
- Familiarize yourself with the video memory (vRAM) settings requirements for the monitors you plan to use with the virtual machine. See [System Requirements For Horizon 7 for Linux](#).

Procedure

- 1 In vSphere Web Client or vSphere Client, create a new virtual machine.

2 Configure custom configuration options.

- a Right-click the virtual machine and click **Edit Settings**.
- b Specify the number of vCPUs and the vMemory size.

For the required settings, follow the guidelines in the installation guide for your Linux distribution.

For example, Ubuntu 12.04 specifies configuring 2048 MB for vMemory and 2 vCPUs.

- c Select **Video card** and specify the number of displays and the total video memory (vRAM).

Set the vRAM size in vSphere Web Client for virtual machines that use 2D or vSGA, which use the VMware driver. The vRAM size has no effect on vDGA or NVIDIA GRID vGPU machines, which use NVIDIA drivers.

For the required settings, follow the guidelines in the [System Requirements For Horizon 7 for Linux](#). Do not use the Video Memory Calculator.

3 Power on the virtual machine and install the Linux distribution.

4 Configure the desktop environment to use for the specific Linux distribution.

See the Desktop Environment section in [System Requirements For Horizon 7 for Linux](#) for additional information.

5 Ensure that the system hostname is resolvable to 127.0.0.1.

Prepare a Linux Machine for Remote Desktop Deployment

You must perform certain tasks to prepare a Linux machine for use as a desktop in a Horizon 7 deployment.

Before a Linux machine can be managed by Horizon 7, the machine must be able to communicate with Connection Server. You must configure networking on the Linux machine so that the Linux machine can ping the Connection Server instance using its FQDN (fully qualified domain name).

Open VMware Tools (OVT) are pre-installed on RHEL 7, CentOS 7, SLED 12, and SLES 12 machines. If you are preparing either of these machines for use as a remote desktop, you can skip steps 1 through 5 in the following procedure, which describe how to install VMware Tools by manually running the installer.

If you are using an Ubuntu 16.04/18.04 machine, install OVT on it. If you are preparing this machine for use as a remote desktop, you can skip steps 1 through 5 in the following procedure and manually install OVT on your Ubuntu 16.04/18.04 machine using the following command:

```
apt-get install open-vm-tools-desktop
```

Prerequisites

- Verify that a new virtual machine (VM) was created in vCenter Server and your Linux distribution was installed on the machine

- Familiarize yourself with the steps for mounting and installing VMware Tools on a Linux VM. See "Manually Install or Upgrade VMware Tools in a Linux Virtual Machine" in the *vSphere Virtual Machine Administration* document.
- Familiarize yourself with the steps for configuring your Linux machine to be resolvable through DNS. These steps vary for the different Linux distributions and releases. For instructions, consult the documentation for your Linux distribution and release.

Procedure

- 1 In vSphere Web Client or vSphere Client, mount the VMware Tools virtual disk on the VM.
- 2 Right-click the VMware Tools installer file, `VMwareTools-x.x.x-xxxx.tar.gz`, click **Extract to**, and select the desktop for your Linux distribution.

The `vmware-tools-distrib` folder is extracted to the desktop.

- 3 On the VM, log in as root and open a terminal window.
- 4 Uncompress the VMware Tools tar installer file.

For example:

```
tar xzpf /mnt/cdrom/VMwareTools-x.x.x-yyyy.tar.gz
```

- 5 Run the installer and configure VMware Tools.

The command might vary slightly in different Linux distributions. For example:

```
cd vmware-tools-distrib
sudo ./vmware-install.pl -d
```

Usually, the `vmware-config-tools.pl` configuration file runs after the installer file finishes running.

- 6 Map the Linux machine's host name to 127.0.0.1 in the `/etc/hosts` file.

For RHEL, CentOS, SLES, and SLED, you must manually map the host name to 127.0.0.1 because it is not automatically mapped. For Ubuntu, this step is not necessary because the mapping is there by default. This step is also not necessary when you bulk deploy desktops because the cloning process adds this mapping.

Note If you change the Linux machine's host name after installing Horizon Agent, you must map the new host name to 127.0.0.1 in the `/etc/hosts` file. Otherwise, the old host name will continue to be used.

- 7 For RHEL 7 and CentOS 7, verify that `virbr0` is disabled.

```
virsh net-destroy default
virsh net-undefine default
service libvirtd restart
```

- 8 Ensure that the View Connection Server instances in the pod can be resolved through DNS.

- 9 Configure the Linux machine so that the default runlevel is 5.

The runlevel must be 5 for the Linux desktop to work.

- 10 On an Ubuntu machine that was configured to authenticate with an OpenLDAP server, set the fully qualified domain name on the machine.

This step ensures that the information can be displayed correctly in the User field on the Sessions page in View Administrator. Edit the `/etc/hosts` file as follows:

- a `# nano /etc/hosts`
- b Add the fully qualified domain name. For example: `127.0.0.1 hostname.domainname hostname.`
- c Exit and save the file.

- 11 For SUSE, disable Change Hostname via DHCP. Set the hostname or domain name.

- a In Yast, click **Network Settings**.
- b Click the **Hostname/DNS** tab.
- c Deselect **Change Hostname via DHCP**.
- d Enter the hostname and the domain name.
- e Click **OK**.

After installing VMware Tools, if you upgrade the Linux kernel, VMware Tools might stop running. To resolve the problem, see <http://kb.vmware.com/kb/2050592>.

Install Dependency Packages for Horizon Agent

Horizon Agent for Linux has some dependency packages unique to a Linux distribution. You must install these packages before installing Horizon Agent for Linux.

Prerequisites

Verify that a new virtual machine (VM) is created in vCenter Server and your Linux distribution is installed on the machine.

Procedure

- 1 Install the mandatory packages that are not installed or upgraded by default. If any package does not meet the requirement, the installer breaks the installation.

Table 2-1. Mandatory Dependency Packages

Linux Distribution	Packages
SLED 11 SP3/SP4 Upgrade xorg-x11-server to a version later than 7.4.27.111.1.	<code>zypper update xorg-x11-server</code>
SLES 12 SP1/SLED 12 SP1 Upgrade xf86-video-vmware to a version later than 13.0.2-3.2 from the SUSE repository.	<ol style="list-style-type: none"> 1 Register SUSE 12 to enable the SUSE repositories. <code>SUSEConnect -r <i>Registration Code</i> -e <i>Email</i></code> 2 Update the xf86-video-vmware version. <code>zypper update xf86-video-vmware</code>
SLES 12	<p>Install python-gobject2 is required for SLES 12 Linux desktop when you are installing Horizon Agent.</p> <ol style="list-style-type: none"> 1 Register SUSE 12 to enable the SUSE repositories. <code>SUSEConnect -r <i>Registration Code</i> -e <i>Email</i></code> 2 Install python-gobject2. <code>zypper install python-gobject2</code>
Ubuntu 14.04 Upgrade the indicator-session package to 12.10.5+15.04.20150327, available in https://launchpad.net/ubuntu/wily/amd64/indicator-session/12.10.5+15.04.20150327-0ubuntu1 .	<code>wget http://launchpadlibrarian.net/201393830/indicator-session_12.10.5+15.04.20150327-0ubuntu1_amd64.deb</code> <code>sudo dpkg -i ./indicator-session_12.10.5+15.04.20150327-0ubuntu1_amd64.deb</code>
Ubuntu 16.04	<code>apt-get install python-dbus python-gobject</code>
Ubuntu 18.04	<code>apt-get install python python-dbus python-gobject</code> <code>apt-get install lightdm (select lightdm as display manager during installation)</code>

2 Install the optional package for Horizon Agent.

- By default, RHEL or CentOS 6.7 has `glibc-2.12-1.166.el6.x86_64` installed which might cause a deadlock issue. As a result, the desktop connection is stuck. To overcome this issue, you must upgrade `glibc` to the latest version from an online repository.

```
sudo yum install glibc
```


Setting Up Active Directory Integration for Linux Desktops

3

View uses the existing Microsoft Active Directory (AD) infrastructure for user authentication and management. You can integrate the Linux desktops with Active Directory so that users can log in to a Linux desktop using their Active Directory user account.

This chapter includes the following topics:

- [Integrating Linux with Active Directory](#)
- [Setting Up Single Sign-On and Smart Card Redirection](#)

Integrating Linux with Active Directory

Multiple solutions exist to integrate Linux with Microsoft Active Directory (AD) and Horizon 7 for Linux Desktop has no dependency on which solution is used.

The following solutions are known to work in a Horizon 7 for Linux desktop environment.

- OpenLDAP Server Pass-through Authentication
- System Security Services Daemon (SSSD) LDAP Authentication against the Microsoft Active Directory
- Winbind Domain Join
- PowerBroker Identity Services Open (PBISO) Authentication

If you use the LDAP-based solutions, you must perform the configuration in a template virtual machine and no additional steps are required in the cloned virtual machines.

Note For ease of deployment, use the SSSD LDAP authentication against the Microsoft Active Directory solution.

OpenLDAP Server Pass-Through Authentication

At a high level, the OpenLDAP Pass-through authentication solution involves the following steps:

- 1 To enable LDAPS (Lightweight Directory Access Protocol over SSL), install Certificate Services on the Active Directory.
- 2 Set up an OpenLDAP server.

- 3 Synchronize user information (except password) from the Active Directory to the OpenLDAP server.
- 4 Configure the OpenLDAP server to delegate password verification to a separate process such as `saslauthd`, which can perform password verification against the Active Directory.
- 5 Configure the Linux desktops to use an LDAP client to authenticate users with the OpenLDAP server.

System Security Services Daemon (SSSD) LDAP Authentication Against the Microsoft Active Directory

The SSSD LDAP authentication against the Microsoft Active Directory solution involves the following steps:

- 1 To enable LDAPS, install the Certificate Services on the Active Directory.
- 2 To use LDAP authentication directly against the Microsoft Active Directory, configure the SSSD in the Linux desktop.

Winbind Domain Join

The Winbind Domain Join solution involves the following steps:

- 1 Install the Winbind, Samba, and Kerberos packages on the Linux desktop.
- 2 Join the Linux desktop to the Microsoft Active Directory.

If you use the Winbind Domain Join solution or other Kerberos authentication-based solution, join the template virtual machine to the Active Directory, and re-join the cloned virtual machine to the Active Directory. For example, use the following command:

```
sudo /usr/bin/net ads join -U <domain_user>%<domain_password>
```

Use the following options to run the domain re-join command on a cloned virtual machine for the Winbind solution:

- Remote connect such as SSH or vSphere PowerCLI to each virtual machine and run the command. For more information on scripts, see [Chapter 9 Bulk Deployment of Horizon 7 for Manual Desktop Pools](#).
- Include the command to a shell script and set the script path to the Horizon agent `RunOnceScript` option in the `/etc/vmware/viewagent-custom.conf` file. For more information, see [Setting Options in Configuration Files on a Linux Desktop](#).

PowerBroker Identity Services Open (PBISO) Authentication

Configuring the PowerBroker Identity Services Open (PBISO) authentication solution involves the following steps:

- 1 Download PBISO 8.5.6 or later from <https://www.beyondtrust.com/products/powerbroker-identity-services-open/>.

2 Install PBISO on your Linux VM.

```
sudo ./pbis-open-8.5.6.2029.linux.x86_64.deb.sh
```

3 Install Horizon 7 Agent for Linux.

4 Use PBISO to join the Linux desktop to the AD domain.

In the following example, **lxdc.vdi** is the domain name and **administrator** is the domain user name.

```
sudo domainjoin-cli join lxdc.vdi administrator
```

5 Set up the default configuration for domain users.

```
sudo /opt/pbis/bin/config UserDomainPrefix lxdc
sudo /opt/pbis/bin/config AssumeDefaultDomain true
sudo /opt/pbis/bin/config LoginShellTemplate /bin/bash
sudo /opt/pbis/bin/config HomeDirTemplate %H/%U
```

6 Edit the /etc/pam.d/common-session file.

- a Locate the line that says **session sufficient pam_lsass.so**.
- b Replace that line with **session [success=ok default=ignore] pam_lsass.so**.

Note This step must be repeated after you reinstall or update the Horizon Agent for Linux.

7 Edit the /usr/share/lightdm/lightdm.conf.d/50-unity-greeter.conf file and append the following lines.

Note If you are using Ubuntu 14.04, the lightdm configuration file is named 60-lightdm-gtk-greeter.conf.

```
allow-guest=false
greeter-show-manual-login=true
```

8 Reboot your system and log in.

Note

- If the `/opt/pbis/bin/config AssumeDefaultDomain` option is set to **false**, you must update the `SSOUserFormat=<username>@<domain>` setting in the `/etc/vmware/viewagent-custom.conf` file.
- When using the Horizon instant-clone floating desktop pool feature, to avoid losing the DNS Server setting when the new network adapter is added to the cloned VM, modify the `resolv.conf` file for your Linux system. Use the following example, for an Ubuntu 16.04 system, as a guide for adding the necessary lines in the `/etc/resolvconf/resolv.conf.d/head` file.

```
nameserver 10.10.10.10
search mydomain.org
```

Setting Up Single Sign-On and Smart Card Redirection

To set up single sign-on (SSO) and smart card redirection, you must perform some configuration steps.

Single Sign-On

The Horizon single sign-on module communicates with PAM (pluggable authentication modules) in Linux and does not depend on the method that you use to integrate Linux with Active Directory (AD). Horizon SSO is known to work with the OpenLDAP and Winbind solutions that integrate Linux with AD.

By default, SSO assumes that AD's `sAMAccountName` attribute is the login ID. To ensure that the correct login ID is used for SSO, you must perform the following configuration steps if you use the OpenLDAP or Winbind solution:

- For OpenLDAP, set `sAMAccountName` to `uid`.
- For Winbind, add the following statement to the configuration file `/etc/samba/smb.conf`.

```
winbind use default domain = true
```

If users must specify the domain name to log in, you must set the `SSOUserFormat` option on the Linux desktop. For more information, see [Setting Options in Configuration Files on a Linux Desktop](#). Be aware that SSO always uses the short domain name in upper case. For example, if the domain is `mydomain.com`, SSO uses `MYDOMAIN` as the domain name. Therefore, you must specify `MYDOMAIN` when setting the `SSOUserFormat` option. Regarding short and long domain names, the following rules apply:

- For OpenLDAP, you must use short domain names in upper case.
- Winbind supports both long and short domain names.

AD supports special characters in login names, but Linux does not. Therefore, do not use special characters in login names when setting up SSO.

In AD, if a user's `UserPrincipalName` (UPN) attribute and `sAMAccount` attribute do not match, and the user logs in with the UPN, SSO fails. For example, if you have a user, `juser` in AD `mycompany.com`, but the user's UPN is set to `juser123@mycompany.com` instead of `juser@mycompany.com`, SSO fails. The workaround is for the user to log in using the name that is stored in `sAMAccount`. For example, `juser`.

View does not require the user name to be case-sensitive. You must ensure that the Linux operating system can handle case-insensitive user names.

- For Winbind, the user name is case-insensitive by default.
- For OpenLDAP, Ubuntu uses NSCD to authenticate users and is case-insensitive by default. RHEL and CentOS use SSSD to authenticate users and the default is case-sensitive. To change the setting, edit the file `/etc/sss/sss.conf` and add the following line in the `[domain/default]` section:

```
case_sensitive = false
```

If your Linux desktop has multiple desktop environments installed on it, refer to [Desktop Environment](#) to select the desktop environment to use with SSO.

Smart Card Redirection

To set up smart card redirection, first follow the instructions from the Linux distributor and from the smart card vendor. Then update the `pcsc-lite` package to 1.7.4. For example, run the following commands:

```
#yum groupinstall "Development tools"
#yum install libudev-devel
#service pcscd stop
#wget https://alioth.debian.org/frs/download.php/file/3598/pcsc-lite-1.7.4.tar.bz2
#tar -xjvf pcsc-lite-1.7.4.tar.bz2
#cd ./pcsc-lite-1.7.4
#./configure --prefix=/usr/ --libdir=/usr/lib64/ --enable-usbdropdir=/usr/lib64/pcsc/drivers
--enable-confdir=/etc --enable-ipcdire=/var/run --disable-libusb --disable-serial --disable-usb
--disable-libudev
#make
#make install
#service pcscd start
```

For Winbind, add the following statement to the configuration file `/etc/samba/smb.conf`.

```
winbind use default domain = true
```

When you install the Horizon Agent, you must first disable SELinux or enable the permissive mode for SELinux. You must also specifically select the smart card redirection component because the component is not selected by default. For more information, see [install_viewagent.sh Command-Line Options](#).

Smartcard SSO is enabled in Horizon 7 version 7.0.1 or later. In addition, if the smart card redirection feature is installed on a virtual machine, vSphere Client's USB redirection does not work with the smart card.

Smart card redirection supports only one smart card reader. This feature does not work if two or more readers are connected to the client device.

Smart card redirection supports only one certificate on the card. If more than one certificate is on the card, the one in the first slot is used and the others are ignored. This behavior is a Linux limitation.

Note

- Smartcard supports the following winbind value. Else the smartcard SSO and manual login fails.

```
winbind use default domain=true
```

- When you use Horizon Client for Linux to authenticate the broker with PIV card, which is supported by Linux desktop smartcard redirection, you must configure the PIV smart card with TLSv1.2 support to avoid receiving an SSL error. Use the solution described in VMWare KB article <http://kb.vmware.com/kb/2150470>.
-

Setting Up True SSO for Linux Desktops

4

With the True SSO (single sign-on) feature, after users log in to VMware Identity Manager using a smart card or RSA SecurID or RADIUS authentication, users are not required to enter Active Directory credentials again to use a Linux virtual desktop or a published desktop or application.

If a user authenticates by using Active Directory (AD) credentials, the True SSO feature is not necessary. However, you can configure True SSO to be used even in this case, so that the desktop can support both AD credentials and True SSO.

When connecting to a Linux virtual desktop or a published desktop or application, users can select to use either the native Horizon Client or HTML Access.

This feature has the following limitations:

- This feature is supported on RHEL/CentOS 7 desktops only.
- Only the RHEL/CentOS 7 default join domain tools, Samba, System Security Services Daemon (SSSD), and the Kerberos network authentication protocol, are supported.

To set up True SSO on your Linux environment, perform the following tasks.

- 1 Set up and configure True SSO in your Horizon 7 environment. See "Setting up True SSO" in the *Horizon 7 Administration* document.
- 2 [Configure True SSO on RHEL/CentOS 7.x Desktops](#)

Configure True SSO on RHEL/CentOS 7.x Desktops

To enable the True SSO feature in an RHEL/CentOS 7.x desktop, install the libraries on which the True SSO feature depends, the root CA certificate, and the Horizon Agent version 7.6 or later.

Beginning with Horizon 7 version 7.6, the True SSO feature is available for Red Hat Enterprise Linux (RHEL) 7.x or CentOS 7.x desktops. The feature is disabled by default. Use the following steps to enable True SSO on these Linux desktops.

Prerequisites

- Configure True SSO for VMware Identity Manager and Horizon Connection Server.

- Integrate your RHEL/CentOS 7.x desktop to a Microsoft Active Directory (AD) domain using System Security Services Daemon (SSSD) LDAP authentication. See "Using realmd to Connect to an Active Directory Domain" section of the [Red Hat Enterprise Linux 7 Windows Integration Guide](#) for information.
- Obtain a root Certificate Authority certificate and save it to /tmp/certificate.cer on your RHEL/CentOS 7.x desktop. See [How to Export Root Certification Authority Certificate](#).

Procedure

- 1 Install the PKCS11 support package group.

```
# yum install -y nss-tools nss-pam-ldapd pam_krb5 krb5-libs krb5-workstation krb5-pkinit
```

- 2 Install a Root Certification Authority (CA) certificate.

- a Transfer the root CA certificate you saved to /tmp/certificate.cer and transfer it to a .pem file.

```
# openssl x509 -inform der -in /tmp/certificate.cer -out /tmp/certificate.pem
```

- 3 Use the certutil command to install the root CA certificate to the system database /etc/pki/nssdb.

```
# certutil -A -d /etc/pki/nssdb -n "root CA cert" -t "CT,C,C" -i /tmp/certificate.pem
```

- 4 Add the root CA certificate to the list of CA certificates trusted on your RHEL/CentOS 7.x system and update the system-wide trust store configuration using the update-ca-trust command.

```
# cp /tmp/certificate.pem /etc/pki/ca-trust/source/anchors/ca_cert.pem
# update-ca-trust
```

- 5 Modify the appropriate section in your system's SSSD configuration file for your domain. Use the following example, where you replace *your_org_AD.com* with the path to your organization's AD domain.

```
[domain/your_org_AD.com]
ad_domain = your_org_AD.com
krb5_realm = YOUR_ORG_AD.COM
realmd_tags = manages-system joined-with-samba
cache_credentials = True
id_provider = ad
krb5_store_password_if_offline = True
default_shell = /bin/bash
ldap_id_mapping = True
#set the next line to false, so you can use the short name instead of the full domain name.
use_fully_qualified_names = False
fallback_homedir = /home/%u@d
access_provider = ad
```


6 Modify the Kerberos configuration file `/etc/krb5.conf`.

Use the following example, where *your_org_AD.com* is the path to your organization's AD domain and *your_org_DNS_server* is the path to your organization's DNS server.

```
[libdefaults]
    dns_lookup_realm = false
    ticket_lifetime = 24h
    renew_lifetime = 7d
    forwardable = true
    rdns = false
    default_ccache_name = KEYRING:persistent:%{uid}
    # Add following line, if the system doesn't add it automatically
    default_realm = YOUR_ORG_AD.COM

[realms]
    EXAMPLE.COM = {
        kdc = kerberos.example.com
        admin_server = kerberos.example.com
    }
    YOUR_ORG_AD.COM = {
        kdc = your_org_DNS_server
        admin_server = your_org_DNS_server
        # Add the following three lines for pkinit_*
        pkinit_anchors = DIR:/etc/pki/ca-trust/source/anchors
        pkinit_kdc_hostname = your_org_DNS_server
        pkinit_eku_checking = kpServerAuth
    }
[domain_realm]
    your_org_AD.com = YOUR_ORG_AD.COM
    .your_org_AD.com = YOUR_ORG_AD.COM
```

7 Install the Horizon Agent package.

```
#sudo ./install_viewagent.sh -T yes
```

8 Add the following parameter to the Horizon Agent custom configuration file `/etc/vmware/viewagent-custom.conf`. Use the following example, where *NETBIOS_NAME_OF_DOMAIN* is the NetBIOS name of your organization's domain.

```
NetbiosDomain=NETBIOS_NAME_OF_DOMAIN
```

9 Reboot your RHEL/CentOS 7.x desktop.

Setting Up Graphics for Linux Desktops

5

You can configure the currently supported RHEL distributions to take advantage of NVIDIA capabilities on ESXi host or on a guest operating system.

VM Clone Requirements for Setting Up 3D Graphics

You must consider the following requirements for VM Clone before setting up 3D graphics.

- For vGPU and vSGA, complete the graphic setup in the base VM. Clone the VMs. The graphic settings work for cloned VMs and no further settings are required.
- For vDGA, complete the graphic setup in the base VM. Clone the VMs. However before you power on the cloned VMs, you must remove the existing NVIDIA pass-through PCI device from the cloned VM and add the new NVIDIA pass-through PCI device to the cloned VM. NVIDIA pass-through PCI device cannot be shared between VMs. Each VM uses a dedicated NVIDIA pass-through PCI device.

This chapter includes the following topics:

- [Configure Supported RHEL Distributions for vGPU](#)
- [Configure RHEL 6 for vDGA](#)
- [Configure RHEL 7.x for vSGA](#)

Configure Supported RHEL Distributions for vGPU

You can set up a supported RHEL distribution to take advantage of NVIDIA vGPU (shared GPU hardware acceleration) capabilities on the ESXi host.

You must use the NVIDIA Linux VM display driver that matches the ESXi host GPU driver(.vib). See the NVIDIA Web site for information about driver packages.

Important NVIDIA vGPU is supported on NVIDIA Maxwell M60 graphics cards and NVIDIA M6 graphics cards. This feature does not work on other NVIDIA graphics cards such as GRID K1 or K2.

Caution Before you begin, verify that Horizon Agent is not installed on the Linux virtual machine. If you install Horizon Agent before you configure the machine to use NVIDIA vGPU, required configuration parameters in the `xorg.conf` file are overwritten, and NVIDIA vGPU does not work. You must install Horizon Agent after the NVIDIA vGPU configuration is completed.

Install the VIB for the NVIDIA GRID vGPU Graphics Card on the ESXi Host

You must download and install the VIB for your NVIDIA GRID graphics card on the ESXi 6.0 U1 or later host.

NVIDIA provides a vGPU software package that includes a vGPU Manager, which you install on the ESXi host in this procedure, and a Linux Display Driver, which you will install on the Linux virtual machine in a later procedure.

Prerequisites

- Verify that vSphere 6.0 U1 or a later release is installed in your environment.
- Verify that the NVIDIA Maxwell M60 GPUs or M6 GPUs are installed on the ESXi host.

Procedure

- 1 Download the VIB for your NVIDIA GRID vGPU graphics card from the [NVIDIA Driver Downloads](#) site.

Select the appropriate VIB version from the drop-down menus.

Option	Description
Product Type	GRID
Product Series	Select NVIDIA GRID vGPU .
Product	Select the version (such as GRID K2) that is installed on the ESXi host.
Operating System	Select the VMware vSphere ESXi version.

- 2 Uncompress the vGPU software package .zip file.
- 3 Upload the vGPU Manager folder to the ESXi 6.0 U1 host.

Note You will install the Linux Display Driver on the Linux virtual machine in a later procedure.

- 4 Power off or suspend all virtual machines on the ESXi host.
- 5 Connect to the ESXi host using SSH.
- 6 Stop the xorg service.

```
# /etc/init.d/xorg stop
```

- 7 Install the NVIDIA VIB.

For example:

```
# esxcli system maintenanceMode set --enable true
# esxcli software vib install -v /path-to-vib/NVIDIA-VIB-name.vib
# esxcli system maintenanceMode set --enable false
```

8 Reboot or update the ESXi host.

- ◆ For an installed ESXi host, reboot the host.
- ◆ For a stateless ESXi host, take the following steps to update the host. (These steps also work on an installed host.)

```
Update vmkdevmgr:
# kill -HUP $(cat /var/run/vmware/vmkdevmgr.pid)

Wait for the update to complete:
# localcli --plugin-dir /usr/lib/vmware/esxcli/int deviceInternal bind

This is a new requirement with the NVIDIA 352.* host driver:
# /etc/init.d/nvidia-vgpu start

Restart xorg, which is used for GPU assignment:
# /etc/init.d/xorg start
```

9 Verify that the xorg service is running after the host is restarted.

Configure a Shared PCI Device for vGPU on the Linux Virtual Machine

To use NVIDIA vGPU, you must configure a shared PCI device for the Linux virtual machine.

Prerequisites

- Verify that the Linux virtual machine is prepared for use as a desktop. See [Create a Virtual Machine and Install Linux](#) and [Prepare a Linux Machine for Remote Desktop Deployment](#).
- Verify that Horizon Agent is not installed on the Linux virtual machine.
- Verify that the NVIDIA VIB is installed on the ESXi host. See [Install the VIB for the NVIDIA GRID vGPU Graphics Card on the ESXi Host](#).
- Familiarize yourself with the virtual GPU types that are available with NVIDIA vGPU, which you select with the **GPU Profile** setting. The virtual GPU types provide varying capabilities on the physical GPUs installed on the ESXi host. See [NVIDIA Virtual GPU Types](#).

Procedure

- 1 Power off the virtual machine.
- 2 In vSphere Web Client, select the virtual machine and, under the **VM Hardware** tab, click **Edit Settings**.
- 3 In the **New device** menu, select **Shared PCI Device**.
- 4 Click **Add** and select **NVIDIA GRID vGPU** from the drop-down menu.
- 5 For the **GPU Profile** setting, select a virtual GPU type from the drop-down menu.
- 6 Click **Reserve all memory** and click **OK**.

You must reserve all virtual machine memory to enable the GPU to support NVIDIA GRID vGPU.

7 Power on the virtual machine.

NVIDIA Virtual GPU Types

With the **GPU Profiles** setting on the Virtual Hardware page in vSphere Web Client, you can select a virtual GPU type that provides specific capabilities on the physical NVIDIA GPU on the ESXi host.

On Linux virtual machines, NVIDIA GRID vGPU is supported on NVIDIA Maxwell M60 GPUs or NVIDIA M6 GPUs.

Table 5-1. Virtual GPU Types Available for NVIDIA GRID M60 vGPU on Linux Virtual Machines

Virtual GPU Type	Physical Board	Physical GPUs	FB Per Virtual GPU	Display Heads	Maximum Resolution	Maximum Virtual GPUs Per Physical GPU	Maximum Virtual GPUs Per Physical Board
GRID M60-0q	GRID M60	two	512M	2	2560x1600	16	32
GRID M60-1q	GRID M60	two	1G	2	2560x1600	8	16
GRID M60-2q	GRID M60	two	2G	4	2560x1600	4	8
GRID M60-4q	GRID M60	two	4G	4	3840x2160	2	4
GRID M60-8q	GRID M60	two	8G	4	3840x2160	1	2

Table 5-2. Virtual GPU Types Available for NVIDIA GRID M6 vGPU on Linux Virtual Machines

Virtual GPU Type	Physical Board	Physical GPUs	FB Per Virtual GPU	Display Heads	Maximum Resolution	Maximum Virtual GPUs Per Physical GPU	Maximum Virtual GPUs Per Physical Board
GRID M6-0q	GRID M6	one	512M	2	2560x1600	16	16
GRID M6-1q	GRID M6	one	1G	2	2560x1600	8	8
GRID M6-2q	GRID M6	one	2G	4	2560x1600	4	4
GRID M6-4q	GRID M6	one	4G	4	3840x2160	2	2
GRID M6-8q	GRID M6	one	8G	4	3840x2160	1	1

Install the NVIDIA GRID vGPU Display Driver

To install the NVIDIA GRID vGPU display driver, you must disable the default NVIDIA driver, download the NVIDIA display drivers, and configure the PCI device on the virtual machine.

Prerequisites

- Verify that you downloaded the vGPU software package from the NVIDIA download site, uncompressed the package, and have the Linux Display Driver (a package component) ready. See [Install the VIB for the NVIDIA GRID vGPU Graphics Card on the ESXi Host](#).

Also verify that a shared PCI device was added to the virtual machine. See [Configure a Shared PCI Device for vGPU on the Linux Virtual Machine](#).

Procedure

- 1 Disable and blacklist the default NVIDIA Nouveau driver.

- a Edit the `grub.conf` or `grub` file.

For RHEL 6, the file is `/boot/grub/grub.conf`. For RHEL 7, the file is `/etc/default/grub`.

RHEL Version	Command
6	<code>sudo vi /boot/grub/grub.conf</code>
7	<code>sudo vi /etc/default/grub</code>

- b Add the `rdblacklist=nouveau` line at the end of the kernel options.
- c Edit the `blacklist.conf` file.

```
sudo vi /etc/modprobe.d/blacklist.conf
```

- d Add the following line anywhere in the `blacklist.conf` file.

```
blacklist nouveau
```

- 2 Restart the virtual machine.

The display has a changed look and feel.

- 3 (Optional) Verify that the Nouveau driver is disabled.

```
/sbin/lsmmod | grep nouveau
```

If the `grep` search does not return any results, the Nouveau driver is disabled.

- 4 Copy the NVIDIA Linux Display Driver to the virtual machine.
- 5 Open a remote terminal to the virtual machine, or switch to a text console by typing `Ctrl-Alt-F2`, log in as root, and run the `init 3` command to disable X Windows.

- 6 Install additional components that are required for the NVIDIA driver.

```
sudo yum install gcc-c++
sudo yum install kernel-devel-$(uname -r)
sudo yum install kernel-headers-$(uname -r)
```

- 7 Add an executable flag to the NVIDIA GRID vGPU driver package.

```
chmod +x NVIDIA-Linux-x86_64-version-grid.run
```

- 8 Start the NVIDIA GRID vGPU installer.

```
sudo ./NVIDIA-Linux-x86_64-version-grid.run
```

- 9 Accept the NVIDIA software license agreement and select **Yes** to update the X configuration settings automatically.

What to do next

Install Horizon Agent on the Linux virtual machine. See [Install Horizon Agent on a Linux Virtual Machine](#).

Create a desktop pool that contains the configured Linux virtual machines. See [Create a Manual Desktop Pool for Linux](#).

Verify That the NVIDIA Display Driver Is Installed

You can verify that the NVIDIA display driver is installed on an RHEL 6.x virtual machine by displaying the NVIDIA driver output in a View desktop session.

Prerequisites

- Verify that you installed the NVIDIA display driver.
- Verify that Horizon Agent is installed on the Linux virtual machine. See [Install Horizon Agent on a Linux Virtual Machine](#).
- Verify that the Linux virtual machine is deployed in a desktop pool. See [Create a Manual Desktop Pool for Linux](#).

Procedure

- 1 Restart the Linux virtual machine.

The Horizon Agent startup script initializes the X server and display topology.

You can no longer view the virtual machine display in the vSphere console.

- 2 From Horizon Client, connect to the Linux desktop.

- 3 In the Linux desktop session, verify that the NVIDIA display driver is installed.

Open a terminal window and run the `glxinfo | grep NVIDIA` command.

The NVIDIA driver output is displayed. For example:

```
[root]# glxinfo | grep NVIDIA
server glx vendor string: NVIDIA Corporation
client glx vendor string: NVIDIA Corporation
OpenGL vendor string: NVIDIA Corporation
OpenGL version string: 4.5.0 NVIDIA 346.47
OpenGL shading language version string: 4.50 NVIDIA
```

The user can access the NVIDIA graphics capabilities on the remote desktop.

After verifying the installation of NVIDIA display driver, perform the following tasks for installation to work correctly.

- If you upgrade the Linux kernel, Horizon Agent might not be able to communicate with View Connection Server. To resolve the problem, reinstall the NVIDIA driver.
- Set the NVIDIA GRID licensing in the Linux VM. See NVIDIA documentation for more information. If licensing is not set, the Linux desktop does not work correctly. For example, auto-fit does not work.

Configure RHEL 6 for vDGA

You can set up an RHEL 6 guest operating system so that Horizon 7 for Linux desktop can take advantage of vDGA capabilities on the ESXi host.

Caution Before you begin, verify that Horizon Agent is not installed on the Linux virtual machine. If you install Horizon Agent before you configure the machine to use vDGA, required configuration parameters in the `xorg.conf` file are overwritten, and vDGA does not work. You must install Horizon Agent after the vDGA configuration is completed.

Enable DirectPath I/O for NVIDIA GRID on a Host

Before you configure a Linux virtual machine to use vDGA, you must make the NVIDIA GRID GPU PCI devices available for DirectPath I/O passthrough on the ESXi host.

Prerequisites

- Verify that vSphere 6.0 or a later release is installed in your environment.
- Verify that the NVIDIA GRID K1 or K2 graphics cards are installed on the ESXi host.

Procedure

- 1 In the vSphere Web Client, browse to the ESXi host.
- 2 Click the **Manage** tab and click **Settings**.
- 3 In the Hardware section, click **PCI Devices**.

- 4 To enable DirectPath I/O passthrough for the NVIDIA GRID GPUs, click **Edit**.

Icon	Description
Green icon	The PCI device is active and can be enabled.
Orange icon	The state of the device has changed. You must reboot the host before you can use the device.

- 5 Select the NVIDIA GRID GPUs and click **OK**.

The PCI devices are added to the table, DirectPath I/O PCI Devices Available to VMs.

- 6 Reboot the host to make the PCI devices available for use by the Linux virtual machines.

Add a vDGA Pass-Through Device to a RHEL 6 Virtual Machine

To configure a RHEL 6 virtual machine to use vDGA, you must add the PCI device to the virtual machine. With this step, the physical device on the ESXi host can be passed through for use on the virtual machine.

Prerequisites

- Verify that the Linux virtual machine is prepared for use as a desktop. See [Create a Virtual Machine and Install Linux](#) and [Prepare a Linux Machine for Remote Desktop Deployment](#).
- Verify that Horizon Agent is not installed on the Linux virtual machine.
- Verify that the NVIDIA GRID GPU PCI device was made available for DirectPath I/O pass-through on the host. See [Enable DirectPath I/O for NVIDIA GRID on a Host](#).

Procedure

- 1 Log in to the RHEL 6 guest operating system as a local user configured with sudo rights.
- 2 In vSphere Web Client, select the virtual machine and, under the **VM Hardware** tab, click **Edit Settings**.
- 3 In the **New device** menu, select **PCI Device**.
- 4 Click **Add** and select the PCI device from the drop-down menu.
- 5 Click **Reserve all memory** and click **OK**.
You must reserve all virtual machine memory to enable the GPU to support vDGA.
- 6 Power on the virtual machine and open vSphere console to connect to the machine.

- 7 Verify that the NVIDIA GRID device is passed through to the virtual machine.

Open a terminal window and run the following command:

```
lspci | grep NVIDIA
```

The XX:00.0 VGA-compatible controller is displayed. For example:

```
NVIDIA Corporation GK104GL [GRID K2]
```

Install the NVIDIA Display Driver for vDGA

To install the NVIDIA display driver for vDGA, you must disable the default NVIDIA driver, download the NVIDIA display drivers, and configure the PCI device on the virtual machine.

Prerequisites

- Verify that the PCI device was added to the RHEL 6.x virtual machine. See [Add a vDGA Pass-Through Device to a RHEL 6 Virtual Machine](#).

Procedure

- 1 Disable and blacklist the default NVIDIA Nouveau driver.

- a Edit the `grub.conf` file.

For RHEL 6, the file is `/boot/grub/grub.conf`.

RHEL Version	Command
6	<code>sudo vi /boot/grub/grub.conf</code>

- b Add the `rdblacklist=nouveau` line at the end of the kernel options.
 - c Edit the `blacklist.conf` file.

```
sudo vi /etc/modprobe.d/blacklist.conf
```

- d Add the following line anywhere in the `blacklist.conf` file.

```
blacklist nouveau
```

- 2 Restart the virtual machine.

The display has a changed look and feel.

- 3 (Optional) Verify that the Nouveau driver is disabled.

```
/sbin/lsmmod | grep nouveau
```

If the `grep` search does not return any results, the Nouveau driver is disabled.

- Download the NVIDIA driver from the [NVIDIA Driver Downloads](#) site.

Select the appropriate driver version from the NVIDIA drop-down menus:

Option	Description
Product Type	GRID
Product Series	GRID Series
Product	Select the version (such as GRID K2) that is installed on the ESXi host.
Operating System	Linux 64-bit or Linux 32-bit

- To connect to the virtual machine, open a remote terminal, or use a text console by typing Ctrl-Alt-F2, log in as root, and run the `init 3` command to disable X Windows.
- Install additional components that are required for the NVIDIA driver.

```
sudo yum install gcc-c++
sudo yum install kernel-devel-$(uname -r)
sudo yum install kernel-headers-$(uname -r)
```

- Add an executable flag to the NVIDIA driver package for vDGA.

```
chmod +x NVIDIA-Linux-x86_64-version.run
```

- Run the NVIDIA installer.

```
sudo ./NVIDIA-Linux-x86_64-version.run
```

- Accept the NVIDIA software license agreement and select **Yes** to update the X configuration settings.

What to do next

Install Horizon Agent on the Linux virtual machine. See [Install Horizon Agent on a Linux Virtual Machine](#).

Create a desktop pool that contains the configured Linux virtual machines. See [Create a Manual Desktop Pool for Linux](#).

Verify That the NVIDIA Display Driver Is Installed

You can verify that the NVIDIA display driver is installed on an RHEL 6.x virtual machine by displaying the NVIDIA driver output in a View desktop session.

Prerequisites

- Verify that you installed the NVIDIA display driver.
- Verify that Horizon Agent is installed on the Linux virtual machine. See [Install Horizon Agent on a Linux Virtual Machine](#).
- Verify that the Linux virtual machine is deployed in a desktop pool. See [Create a Manual Desktop Pool for Linux](#).

Procedure

- 1 Restart the Linux virtual machine.

The Horizon Agent startup script initializes the X server and display topology.

You can no longer view the virtual machine display in the vSphere console.

- 2 From Horizon Client, connect to the Linux desktop.

- 3 In the Linux desktop session, verify that the NVIDIA display driver is installed.

Open a terminal window and run the `glxinfo | grep NVIDIA` command.

The NVIDIA driver output is displayed. For example:

```
[root]# glxinfo | grep NVIDIA
server glx vendor string: NVIDIA Corporation
client glx vendor string: NVIDIA Corporation
OpenGL vendor string: NVIDIA Corporation
OpenGL version string: 4.5.0 NVIDIA 346.47
OpenGL shading language version string: 4.50 NVIDIA
```

The user can access the NVIDIA graphics capabilities on the remote desktop.

After verifying the installation of NVIDIA display driver, perform the following tasks for installation to work correctly.

- If you upgrade the Linux kernel, Horizon Agent might not be able to communicate with View Connection Server. To resolve the problem, reinstall the NVIDIA driver.
- Set the NVIDIA GRID licensing in the Linux VM. See NVIDIA documentation for more information. If licensing is not set, the Linux desktop does not work correctly. For example, auto-fit does not work.

Configure RHEL 7.x for vSGA

You can set up an RHEL 7.x guest operating system so that a Horizon 7 for Linux desktop can take advantage of vSGA capabilities.

Install the VIB for the NVIDIA Graphics Card for vSGA on the ESXi Host

You must download and install the VIB for your NVIDIA GRID graphics card on the ESXi 6.0 U1 or later host.

NVIDIA provides a VMware vSphere ESXi Driver for vSGA. For vSGA, an NVIDIA display driver is not installed on the Linux virtual machine.

Prerequisites

- Verify that vSphere 6.0 U1 or a later release is installed in your environment.
- Verify that NVIDIA driver is installed in your environment.

- Verify that the NVIDIA GRID K1 or K2 GPUs are installed on the ESXi host.

Procedure

- 1 Download the VIB for your NVIDIA GRID vGPU graphics card from the [NVIDIA Driver Downloads](#) site.

Select the appropriate VIB version from the drop-down menus.

Option	Description
Product Type	GRID
Product Series	Select GRID Series .
Product	Select the version (such as GRID K2) that is installed on the ESXi host.
Operating System	Select the VMware vSphere ESXi version.

- 2 Upload the VMware vSphere ESXi Driver for vSGA to the ESXi 6.0 U1 host.
- 3 Power off or suspend all virtual machines on the ESXi host.
- 4 Connect to the ESXi host using SSH.
- 5 Stop the xorg service.

```
# /etc/init.d/xorg stop
```

- 6 Install the NVIDIA VIB.

For example:

```
# esxcli system maintenanceMode set --enable true
# esxcli software vib install -v /path-to-vib/NVIDIA-VIB-name.vib
# esxcli system maintenanceMode set --enable false
```

- 7 Restart xorg, which is used for GPU assignment:

```
# /etc/init.d/xorg start
```

- 8 Reboot the ESXi host.
- 9 Verify that the xorg service is running after the host is restarted.

Configure 3D Capabilities for vSGA on the Linux Virtual Machine

To configure a RHEL 7 virtual machine to use vSGA, you must configure 3D settings for the virtual machine's video card in vSphere Web Client.

Prerequisites

- Verify that the Linux virtual machine is prepared for use as a desktop, Horizon Agent is installed, and the machine is deployed in a desktop pool.

- Verify that the NVIDIA VIB is installed on the ESXi host. See [Install the VIB for the NVIDIA Graphics Card for vSGA on the ESXi Host](#).

Procedure

- 1 Power off the virtual machine.
- 2 In vSphere Web Client, select the virtual machine and, under the **VM Hardware** tab, click **Edit Settings**.
- 3 In the Virtual Hardware tab, click **Video card** to expand the menu settings.
- 4 Set the **Total video memory** to 128 MB.
- 5 For **3D Graphics**, select **Enable 3D Support**.
- 6 For **3D Renderer**, select **Hardware** from the drop-down menu.
- 7 For **3D Memory**, select a suitable value for your application requirements.
If your users connect to more than 3 monitors, set this value to at least 1024 MB.
- 8 Click **OK**.
- 9 Power on the virtual machine.

What to do next

Verify that vSGA is running on the Linux virtual machine.

Next, install Horizon Agent on the Linux virtual machine. See [Install Horizon Agent on a Linux Virtual Machine](#).

Verify that vSGA is Running on a Linux Virtual Machine

You can verify that vSGA is running on a RHEL 7 virtual machine by checking the virtual machine log file and checking the guest operating system.

Procedure

- 1 Open the `vmware.log` file for the virtual machine.

If a supported GPU and NVIDIA VIB are installed correctly, the log file displays lines such as those in the following example:

```
2015-06-24T22:19:25.259Z| mks| I120: OpenGL Version: "4.0.0 NVIDIA 346.69" (4.0.0)
2015-06-24T22:19:25.259Z| mks| I120: GLSL Version: "4.00 NVIDIA" (4.00.0)
2015-06-24T22:19:25.259Z| mks| I120: OpenGL Vendor: "NVIDIA Corporation"
2015-06-24T22:19:25.259Z| mks| I120: OpenGL Renderer: "Quadro 4000/PCIe/SSE2"
```

If a supported GPU and NVIDIA VIB are not installed correctly, the virtual machine uses the Software Renderer. The `vmware.log` file displays lines such as those in the following example:

```
2015-07-06T17:09:26.423Z| vmx| I120: [msg.mks.noGPUResourceFallback] Hardware GPU resources are
not available. The virtual machine uses software rendering.
2015-07-06T17:09:26.423Z| vmx| I120: -----
2015-07-06T17:09:26.425Z| svga| I120: MKS-SWP: plugin started - llvmpipe (LLVM 3.3, 256 bits)
2015-07-06T17:09:26.426Z| svga| I120: Started Shim3D
2015-07-06T17:09:26.426Z| svga| I120: MKS-RenderMain: Starting SWRenderer
```

- 2 In the guest operating system on the virtual machine, type the following command.

```
glxinfo|grep Gallium
```

If vSGA is working, the command returns the following text:

```
OpenGL renderer string: Gallium 0.4 on SVGA3D; build : RELEASE;
```

If vSGA is not working correctly, the command returns the following text:

```
OpenGL renderer string: Gallium 0.4 on llvmpipe (LLVM 3.3, 256 bits)
```

What to do next

Install Horizon Agent on the Linux virtual machine. See [Install Horizon Agent on a Linux Virtual Machine](#).

Installing Horizon Agent

You must install Horizon Agent on the Linux desktops so that View Connection Server can communicate with and manage the desktops.

This chapter includes the following topics:

- [Install Horizon Agent on a Linux Virtual Machine](#)
- [Configure the Certificate for Linux Agent](#)
- [Upgrading the Horizon Agent on a Linux Virtual Machine](#)
- [Uninstall Horizon 7 for Linux Machines](#)

Install Horizon Agent on a Linux Virtual Machine

You must install Horizon Agent on a Linux virtual machine before you can deploy the machine as a remote desktop.

Beginning with Horizon 7.0.1 release, Horizon Agent for Linux uses vCenter managed virtual machines. The managed virtual machines provide the following enhancements.

- vCenter is a mandatory requirement for Linux desktop deployment.
- Horizon Agent installation on Linux does not require registration.
- For a large number of Linux desktop deployment, you can install the Horizon Agent on the base virtual machine.

Caution If you intend to use NVIDIA GRID vGPU, vDGA, or vSGA, you must configure these 3D features on the Linux virtual machine before you install Horizon Agent. If you install Horizon Agent first, required parameters in the `xorg.conf` file are overwritten, and the 3D graphics features do not work.

See [Configure Supported RHEL Distributions for vGPU](#), [Configure RHEL 6 for vDGA](#), or [Configure RHEL 7.x for vSGA](#). Install Horizon Agent after the 3D graphics configuration is completed.

For 2D graphics configuration, you can install Horizon Agent after you complete the steps in [Prepare a Linux Machine for Remote Desktop Deployment](#).

Prerequisites

- Verify that the Linux guest operating system is prepared for desktop use. See [Prepare a Linux Machine for Remote Desktop Deployment](#).

- Familiarize yourself with the Horizon Agent installer script for Linux. See [install_viewagent.sh Command-Line Options](#).

Procedure

- 1 Download the Horizon Agent for Linux installer file from the VMware download site at <https://my.vmware.com/web/vmware/downloads>.

Under Desktop & End-User Computing, select the VMware Horizon 7 download, which includes the Horizon Agent for Linux installer.

The installer filename is VMware-horizonagent-linux-x86_64-y.y.y-xxxxxxx.tar.gz for 64-bit Linux where y.y.y is the version number and xxxxxxx is the build number.

- 2 Unpack the tarball for your Linux distribution on the guest operating system.

For example:

```
tar -xzvf <View Agent tar ball>
```

- 3 Navigate to the tar ball folder.
- 4 Run the `install_viewagent.sh` script as superuser.

See [install_viewagent.sh Command-Line Options](#) for a list of the command line options.

For example:

```
sudo ./install_viewagent.sh
```

- 5 Type **Yes** to accept the EULA if you run `install_viewagent.sh` without specifying the `-A` option.

The installer does not run unless you accept the EULA.

- 6 Reboot Linux for the changes to take effect.

After installation, the `viewagent` service is started. Verify that the service is started using `sudo service viewagent status`.

What to do next

Deploy the virtual machine in a desktop pool. See [Create a Manual Desktop Pool for Linux](#).

install_viewagent.sh Command-Line Options

The `install_viewagent.sh` script installs Horizon Agent on a Linux guest operating system.

Use the following form of the `install_viewagent.sh` script in a command window in the gnome desktop environment.

```
install_viewagent.sh command_option argument [command_option argument] . . .
```

The `install_viewagent.sh` script includes mandatory and optional parameters.

Table 6-1. install_viewagent.sh Optional but Required Parameter

Optional Parameter (Required Information)	Description
-A yes no	Accept or refuse the End User License Agreement (EULA) and Federal Information Processing Standards (FIPS) statement. You must specify yes for the install to proceed.

Table 6-2. install_viewagent.sh Optional Parameters

Optional Parameters	Description
-a yes no	Install or bypass audio input redirection support. Default is yes .
-f yes no	Install or bypass support of the cryptographic modules designed for Federal Information Processing Standards (FIPS) 140-2. Default is no . For more information, see the FIPS 140-2 Mode description in Features of Horizon Linux Desktops .
-j	JMS SSL keystore password. By default, installer generates a random string.
-m yes no	Install or bypass the smart card redirection support. Default is no .
-r yes no	Restart the system automatically after installation. Default is no .
-s	Self signed cert subject DN. By default, installer uses Blast.
-C yes no	Install or bypass Clipboard Redirection support. Default is yes .
-F yes no	Install or bypass CDR support. Default is yes .
-M yes no	Upgrade the Linux Agent to managed or unmanaged agent. Default is yes .
-S yes no	Install or bypass Single Sign-On (SSO) support. Default is yes .
-U yes no	Install or bypass USB support. Default is no .

Table 6-3. Examples of install_viewagent.sh Parameters

Condition	Examples
Fresh Installation	<pre>sudo ./install_viewagent.sh -A yes</pre> <p>Fresh installation always requires a new desktop pool creation.</p>
Upgrade from an unmanaged virtual machine and retain the unmanaged virtual machine style	<pre>sudo ./install_viewagent.sh -A yes -M no</pre> <p>This type of upgrade does not require a new desktop pool creation. You can reuse the existing desktop pool.</p> <p>Note To ensure the best possible performance, do not use an unmanaged virtual machine.</p>
Upgrade from an unmanaged virtual machine deployment and convert to a managed virtual machine style. The upgrade requires new desktop pool creation on broker	<pre>sudo ./install_viewagent.sh -A yes</pre> <p>This type of upgrade requires a new desktop pool creation. You must delete the existing desktop pool.</p>

Configure the Certificate for Linux Agent

When you install Linux Agent, the installer generates a self-signed certificate for VMwareBlastServer.

- When the Blast Security Gateway is disabled on the broker, VMwareBlastServer presents this certificate to the browser that uses HTML Access to connect to the Linux Desktop.
- When the Blast Security Gateway is enabled on the broker, Blast Security Gateway's certificate presents the certificate to the browser.

To comply with industry or security regulations, you can replace the self-signed certificate with a certificate that is signed by a Certificate Authority (CA).

Procedure

- 1 Install the private key and the certificate to VMwareBlastServer.
 - a Rename the private key to rui.key and the certificate to rui.crt .
 - b Run `sudo chmod 550 /etc/vmware/ssl`.
 - c Copy the rui.crt and rui.key to /etc/vmware/ssl.
 - d Run `chmod 440 /etc/vmware/ssl`.

- 2 Install the root and intermediate Certificate Authority into the Linux OS Certificate Authority store.

Note Check your Linux distribution documentation for the Linux system settings change.

Upgrading the Horizon Agent on a Linux Virtual Machine

You can upgrade Horizon Agent on a Linux virtual machine by installing the latest version of Horizon Agent.

Unmanaged virtual machine: The agent installer registers the virtual machine to the broker which requires broker admin information. The **Desktop Pool Creation** wizard uses **Other Sources** in the Machine Source page to select the registered virtual machine.

Managed virtual machine: The installer does not communicate with the broker. The **Desktop Pool Creation** wizard uses **vCenter virtual machines** in the Machine Source page to select the virtual machines through vCenter. The managed virtual machine deployment supports the following functions.

- Remote Machine Power Policy
- Allow users to reset their machines

Note Horizon Agent for Linux 7.0.0 and earlier versions functioned as unmanaged virtual machines. The Horizon Agent for Linux 7.0.1 functions as managed virtual machine support.

You can use the following methods to upgrade from unmanaged to a managed virtual machine deployment.

- Retain the unmanaged virtual machine deployment and upgrade to the required version. This type of upgrade does not require any configuration modifications in View Connection Server.
- Upgrade from an unmanaged virtual machine deployment to a managed virtual machine deployment to any version. This type of upgrade requires a new desktop pool creation on the View Connection Server.

Note For the upgrade from a managed virtual machine deployment, you can retain the managed virtual machine deployment and upgrade to the required version. However, to convert the managed virtual machine deployment to an unmanaged virtual machine deployment during an upgrade is not supported.

The following parameters are available for upgrade.

Table 6-4. Optional Parameters for Upgrading the Horizon Agent

Parameter	Description
-A yes	EULA and FIPS statement acceptance. You must specify yes for the install to proceed. If this parameter is not specified, the install script prompts for the value.
-a yes no	Install or bypass audio input redirection support.
-f yes no	Install or bypass support of the cryptographic modules designed for Federal Information Processing Standards (FIPS) 140-2. Default is no . For more information, see the FIPS 140-2 Mode description in Features of Horizon Linux Desktops .
-m yes no	Install or bypass the smart card redirection support. Default is no .

Table 6-4. Optional Parameters for Upgrading the Horizon Agent (Continued)

Parameter	Description
-r yes no	Reboot the operating system after installation. The default is no .
-C yes no	Install or bypass Clipboard Redirection support. Default is yes .
-F yes no	Install or bypass CDR support. Default is yes .
-M yes no	Upgrade the Linux Agent to managed unmanaged agent. The default value is yes .
-S yes no	Install or bypass SingleSignOn (SSO) support. Default is yes .
-U yes no	Install or Bypass USB support. Default is no .

Upgrade Horizon Agent on a Linux Virtual Machine

You can upgrade Horizon Agent on a Linux machine by installing the latest version of Horizon Agent.

Prerequisites

- Verify that the VMwareBlastServer process is not running.

To stop this process, ensure that the user logs off the machine and no desktop session is active, or reboot the machine.

Procedure

- 1 Download the latest installer file for Horizon Agent for Linux from the VMware download site at <https://my.vmware.com/web/vmware/downloads>.

Under Desktop & End-User Computing, select to download VMware Horizon 7, which includes the installer for Horizon Agent for Linux.

The installer filename is `VMware-viewagent-linux-x86_64-y.y.y-xxxxxxx.tar.gz` for 64-bit Linux where `y.y.y` is the version number and `xxxxxxx` is the build number.

- 2 Unpack the tarball for your Linux distribution on the guest operating system.

For example:

```
tar -xzvf <View Agent tar ball>
```

- 3 Navigate to the tar ball folder.

- 4 To upgrade unmanaged virtual machines, run the `install_viewagent.sh` script using one of the following deployment scenarios.

Option	Description
Upgrade an unmanaged virtual machine deployment and retain the unmanaged virtual machine deployment	<pre>sudo ./install_viewagent.sh -A yes -M no</pre> <p>Note To ensure the best possible performance, do not use an unmanaged virtual machine.</p>
Upgrade an unmanaged virtual machine deployment and change it to managed virtual machine deployment	<pre>sudo ./install_viewagent.sh -A yes -M yes</pre> <p>Note In View Administrator, delete the existing desktop pool for unmanaged virtual machine deployment and create a desktop pool for a managed virtual machine deployment. For more info, see Create a Manual Desktop Pool for Linux.</p>
Upgrade a managed virtual machine deployment	<pre>sudo ./install_viewagent.sh -A yes -M yes</pre> <p>Note After upgrading, your existing desktop pool can be reused.</p>

Uninstall Horizon 7 for Linux Machines

To uninstall Horizon 7 for Linux on a virtual machine, you must uninstall Horizon Agent and remove configuration files.

Prerequisites

Verify that the `VMwareBlastServer` process is not running. To stop this process, ensure that you log off the machine and no desktop session is active, or reboot the machine.

Procedure

- 1 Open a terminal window on the virtual machine and run the Horizon Agent uninstall script.

```
sudo /usr/lib/vmware/viewagent/bin/uninstall_viewagent.sh
```

The script stops the Horizon Agent processes, deletes the Horizon Agent service and software from installation directory `/usr/lib/vmware/viewagent`.

- 2 Manually delete the Horizon 7 for Linux configuration files at `/etc/vmware` directory.

Configuration Options for Linux Desktops

7

You can configure various options to customize the user experience using configuration files.

This chapter includes the following topics:

- [Setting Options in Configuration Files on a Linux Desktop](#)
- [Using Smart Policies](#)
- [Example Blast Settings for Linux Desktops](#)
- [Examples of Client Drive Redirection Options for Linux Desktops](#)
- [Suppress the vSphere Console Display of a Linux Desktop](#)

Setting Options in Configuration Files on a Linux Desktop

You can configure certain options by adding entries to the files `/etc/vmware/config` or `/etc/vmware/viewagent-custom.conf`.

During the installation of View Agent or Horizon Agent, the installer copies two configuration template files, `config.template` and `viewagent-custom.conf.template`, to `/etc/vmware`. In addition, if `/etc/vmware/config` and `/etc/vmware/viewagent-custom.conf` do not exist, the installer copies `config.template` to `config` and `viewagent-custom.conf.template` to `viewagent-custom.conf`. In the template files, all the configuration options are listed and documented. To set an option, simply remove the comment and change the value as appropriate.

For example, the following line in `/etc/vmware/config` enables the build to lossless PNG mode.

```
RemoteDisplay.buildToPNG=TRUE
```

After you make configuration changes, reboot Linux for the changes to take effect.

Configuration Options in /etc/vmware/config

VMwareBlastServer and its related plug-ins use the configuration file /etc/vmware/config.

Note The following table includes description for each agent-enforced policy setting for USB in the Horizon Agent configuration file. Horizon Agent uses the settings to decide if a USB can be forwarded to the host machine. Horizon Agent also passes the settings to Horizon Client for interpretation and enforcement. The enforcement is based on whether you specify the merge (**m**) modifier to apply the Horizon Agent filter policy setting in addition to the Horizon Client filter policy setting, or override the (**o**) modifier to use the Horizon Agent filter policy setting instead of the Horizon Client filter policy setting.

Table 7-1. Configuration Options in /etc/vmware/config

Option	Value/Format	Default	Description
Clipboard.Direction	0, 1, 2, or 3	2	Use this option to specify the clipboard redirection policy. Valid values are as follows: <ul style="list-style-type: none"> 0 - Disable clipboard redirection. 1 - Enable clipboard redirection in both directions. 2 - Enable clipboard redirection from the client to the remote desktop only. 3 - Enable clipboard redirection from the remote desktop to the client only.
RemoteDisplay.allowAudio	true or false	true	Set this option to enable/disable audio out.
RemoteDisplay.allowH264	true or false	true	Set this option to enable or disable H.264 encoding.
RemoteDisplay.buildToPNG	true or false	false	Graphic applications, especially graphic design applications, require pixel-exact rendering of images in the client display of a Linux desktop. You can configure the build to lossless PNG mode for images and video playback that are generated on a Linux desktop and rendered on the client device. This feature uses additional bandwidth between the client and the ESXi host. Enabling this option disables the H.264 encoding.
RemoteDisplay.enableNetworkIntelligence	true or false	true	Set this option to enable or disable the Network Intelligence feature in Linux Agent.
RemoteDisplay.enableStats	true or false	false	Enables or disables the VMware Blast display protocol statistics in mks log, such as bandwidth, FPS, RTT, and so on.
RemoteDisplay.enableUDP	true or false	true	Set this option to enable or disable UDP protocol support in Linux Agent.
RemoteDisplay.maxBandwidthKbps	An integer	4096000	Specifies the maximum bandwidth in kilobits per second (kbps) for a VMware Blast session. The bandwidth includes all imaging, audio, virtual channel, and VMware Blast control traffic. The max value is 4 Gbps (4096000).

Table 7-1. Configuration Options in /etc/vmware/config (Continued)

Option	Value/Format	Default	Description
RemoteDisplay.maxFPS	An integer	60	Specifies the maximum rate of screen updates. Use this setting to manage the average bandwidth that users consume. Valid value must be between 3 and 60. The default is 60 updates per second.
RemoteDisplay.maxQualityJPEG	available range of values: 1–100	90	Specifies the image quality of the desktop display for JPEG/PNG encoding. The high-quality settings are for areas of the screen that are more static, resulting in a better image quality.
RemoteDisplay.midQualityJPEG	available range of values: 1–100	35	Specifies the image quality of the desktop display for JPEG/PNG encoding. Use to set the medium-quality settings of the desktop display.
RemoteDisplay.minQualityJPEG	available range of values: 1–100	25	Specifies the image quality of the desktop display for JPEG/PNG encoding. The low-quality settings are for areas of the screen that change often, for example, when scrolling occurs.
RemoteDisplay.qpmaxH264	available range of values: 0–51	36	Use this option to set the H264minQP quantization parameter, which specifies the best image quality for the remote display configured to use H.264 encoding. Set the value to greater than the value set for RemoteDisplay.qpminH264.
RemoteDisplay.qpminH264	available range of values: 0–51	10	Use this option to set the H264maxQP quantization parameter, which specifies the lowest image quality for the remote display configured to use H.264 encoding. Set the value to less than the value set for RemoteDisplay.qpmaxH264.
UsbRedirPlugin.log.logLevel	error, warn, info, debug, trace, or verbose	info	Use this option to set the log level for the USB Redirection plugin.
UsbRedirServer.log.logLevel	error, warn, info, debug, trace, or verbose	info	Use this option to set the log level for the USB Redirection server.
VMWPKcs11Plugin.log.enable	true or false	false	Set this option to enable or disable the logging mode for the True SSO feature.
VMWPKcs11Plugin.log.logLevel	error, warn, info, debug, trace, or verbose	info	Use this option to set the log level for the True SSO feature.
VVC.RTAV.Enable	true or false	true	Set this option to enable/disable audio input.
VVC.ScRedir.Enable	true or false	true	Set this option to enable/disable smart card redirection.
VVC.logLevel	fatal error, warn, info, debug, or trace	info	Use this option to set the log level of the VVC proxy node.
cdserver.cacheEnable	true or false	true	Set this option to enable or disable the write caching feature from the agent towards the client side.

Table 7-1. Configuration Options in /etc/vmware/config (Continued)

Option	Value/Format	Default	Description
cdserver.forcedByAdmin	true or false	false	Set this option to control whether the client can share additional folders that are not specified with the <code>cdserver.shareFolders</code> option.
cdserver.logLevel	error, warn, info, debug, trace, or verbose	info	Use this option to set the log level for <code>vmware-CDRserver.log</code> file.
cdserver.permissions	R	RW	<p>Use this option to apply additional read/write permissions that Horizon Agent has on the folders shared by Horizon Client. For example:</p> <ul style="list-style-type: none"> ■ If the folder shared by Horizon Client has read and write permissions and you set <code>cdserver.permissions=R</code>, then Horizon Agent has only read access permissions. ■ If the folder shared by Horizon Client has only read permissions and you set <code>cdserver.permissions=RW</code>, Horizon Agent still has only read access rights. Horizon Agent cannot change the read only attribute that was set by Horizon Client. Horizon Agent can only remove the write access rights. <p>Typical uses are as follows:</p> <ul style="list-style-type: none"> ■ <code>cdserver.permissions=R</code> ■ <code>#cdserver.permissions=R</code> (for example, comment it out or delete the entry)
cdserver.sharedFolders	<i>file_path1,R;file_path2,;file_path3,R; . . .</i>	undefined	<p>Specify one or more file paths to the folders that the client can share with the Linux desktop. For example:</p> <ul style="list-style-type: none"> ■ For a Windows client: <code>C:\spreadsheets,;D:\ebooks,R</code> ■ For a non-Windows client: <code>/tmp/spreadsheets;/tmp/ebooks,;/home/finance,R</code>
mksVNCServer.useUInputButtonMapping	true or false	false	Set this option to enable the support of a left-handed mouse on Ubuntu or RHEL 7. CentOS and RHEL 6 support a left-handed mouse and you do not need to set this option.
mksVNCServer.useXExtButtonMapping	true or false	false	Set this option to enable or disable the support of a left-handed mouse on SLED 11 SP3.
mksvhan.clipboardSize	An integer	1024	Use this option to specify the clipboard maximum size to copy and paste.
vdpservice.log.logLevel	fatal error, warn, info, debug, or trace	info	Use this option to set the log level of the <code>vdpservice</code> .
viewusb.AllowAudioIn	<code>{m o}:</code> <code>{true false}</code>	undefined, which equates to true	Use this option to allow or disallow audio input devices to be redirected. Example: <code>o:false</code>

Table 7-1. Configuration Options in /etc/vmware/config (Continued)

Option	Value/Format	Default	Description
viewusb.AllowAudioOut	{m o}: {true false}	undefined, which equates to false	Set this option to allow or disallow redirection of audio output devices.
viewusb.AllowAutoDeviceSplitting	{m o}: {true false}	undefined, which equates to false	Set this option to allow or disallow the automatic splitting of composite USB devices. Example: m:true
viewusb.AllowDevDescFailsafe	{m o}: {true false}	undefined, which equates to false	Set this option to allow or disallow devices to be redirected even if Horizon Client fails to get the configuration or device descriptors. To allow a device even if it fails to get the configuration or device descriptors, include it in the Include filters, such as IncludeVidPid or IncludePath .
viewusb.AllowHIDBootable	{m o}: {true false}	undefined, which equates to true	Use this option to allow or disallow the redirection of input devices other than keyboards or mice that are available at boot time, also known as HID-bootable devices.
viewusb.AllowKeyboardMouse	{m o}: {true false}	undefined, which equates to false	Use this option to allow or disallow the redirection of keyboards with integrated pointing devices (such as a mouse, trackball, or touch pad).
viewusb.AllowSmartcard	{m o}: {true false}	undefined, which equates to false	Set this option to allow or disallow smart card devices to be redirected.
viewusb.AllowVideo	{m o}: {true false}	undefined, which equates to true	Use this option to allow or disallow video devices to be redirected.
viewusb.DisableRemoteConfig	{m o}: {true false}	undefined, which equates to false	Set this option to disable or enable the use of Horizon Agent settings when performing USB device filtering.
viewusb.ExcludeAllDevices	{true false}	undefined, which equates to false	Use this option to exclude or include all USB devices from being redirected. If set to true , you can use other policy settings to allow specific devices or families of devices to be redirected. If set to false , you can use other policy settings to prevent specific devices or families of devices from being redirected. If you set the value of ExcludeAllDevices to true on Horizon Agent, and this setting is passed to Horizon Client, the Horizon Agent setting overrides the Horizon Client setting.

Table 7-1. Configuration Options in /etc/vmware/config (Continued)

Option	Value/Format	Default	Description
viewusb.ExcludeFamily	<code>{m o}:family_name_1[;family_name_2;...]</code>	undefined	<p>Use this option to exclude families of devices from being redirected. For example: m:bluetooth;smart-card</p> <p>If you have enabled automatic device splitting, Horizon examines the device family of each interface of a composite USB device to decide which interfaces must be excluded. If you have disabled automatic device splitting, Horizon examines the device family of the whole composite USB device.</p> <p>Note Mice and keyboards are excluded from redirection by default and do not need to be excluded with this setting.</p>
viewusb.ExcludePath	<code>{m o}:bus-x1[/y1].../port-z1[;bus-x2[/y2].../port-z2;...]</code>	undefined	<p>Use this option to exclude devices at specified hub or port paths from being redirected. You must specify bus and port numbers in hexadecimal. You cannot use the wildcard character in paths.</p> <p>For example:m:bus-1/2/3_port-02;bus-1/1/1/4_port-ff</p>
viewusb.ExcludeVidPid	<code>{m o}:vid-xxx1_pid-yyy1[;vid-xxx2_pid-yyy2;...]</code>	undefined	<p>Set this option to exclude devices with specified vendor and product IDs from being redirected. You must specify ID numbers in hexadecimal. You can use the wildcard character (*) in place of individual digits in an ID.</p> <p>For example: o:vid-0781_pid-****;vid-0561_pid-554c</p>
viewusb.IncludeFamily	<code>{m o}:family_name_1[;family_name_2]...</code>	undefined	<p>Set this option to include families of devices that can be redirected.</p> <p>For example: o:storage; smart-card</p>
viewusb.IncludePath	<code>{m o}:bus-x1[/y1].../port-z1[;bus-x2[/y2].../port-z2;...]</code>	undefined	<p>Use this option to include devices at specified hub or port paths that can be redirected. You must specify bus and port numbers in hexadecimal. You cannot use the wildcard character in paths.</p> <p>For example: m:bus-1/2_port-02;bus-1/7/1/4_port-0f</p>
viewusb.IncludeVidPid	<code>{m o}:vid-xxx1_pid-yyy1[;vid-xxx2_pid-yyy2;...]</code>	undefined	<p>Set this option to include devices with specified Vendor and Product IDs that can be redirected. You must specify ID numbers in hexadecimal. You can use the wildcard character (*) in place of individual digits in an ID.</p> <p>For example: o:vid-***_pid-0001;vid-0561_pid-554c</p>

Table 7-1. Configuration Options in /etc/vmware/config (Continued)

Option	Value/Format	Default	Description
viewusb.SplitExcludeVidPid	{m o}:vid-xxx1_pid-yyy1[;vid-xxx2_pid-yyy2;...]	undefined	Use this option to exclude or include a specified composite USB device from splitting by Vendor and Product IDs. The format of the setting is vid-xxx1_pid-yyy1[;vid-xxx2_pid-yyy2;...] . You must specify ID numbers in hexadecimal. You can use the wildcard character (*) in place of individual digits in an ID. Example: m:vid-0f0f_pid-55**
viewusb.SplitVidPid	{m o}: vid-xxxx_pid-yyyy([exintf:zz[;exintf:ww]])[;...]	undefined	Set this option to treat the components of a composite USB device specified by Vendor and Product IDs as separate devices. The format of the setting is vid-xxxx_pid-yyyy(exintf:zz[;exintf:ww]) . You can use the exintf keyword to exclude components from redirection by specifying their interface number. You must specify ID numbers in hexadecimal, and interface numbers in decimal including any leading zero. You can use the wildcard character (*) in place of individual digits in an ID. Example: o:vid-0f0f_pid-*** (exintf-01);vid-0781_pid-554c(exintf:01;exintf:02) Note Horizon does not automatically include the components that you have not explicitly excluded. You must specify a filter policy such as Include VidPid Device to include those components.

Configuration Options in /etc/vmware/viewagent-custom.conf

Java Standalone Agent uses the configuration file /etc/vmware/viewagent-custom.conf.

Table 7-2. Configuration Options in /etc/vmware/viewagent-custom.conf

Option	Value	Default	Description
CDREnable	true or false	true	Use this option to enable or disable the Client Drive Redirection (CDR) feature.
HelpDeskEnable	true or false	true	Set this option to enable or disable the Help Desk Tool feature.

Table 7-2. Configuration Options in /etc/vmware/viewagent-custom.conf (Continued)

Option	Value	Default	Description
KeyboardLayoutSync	true or false	true	<p>Use this option to specify whether to synchronize a client's system locale list and current keyboard layout with Horizon Agent for Linux desktops.</p> <p>When this setting is enabled or not configured, synchronization is allowed. When this setting is disabled, synchronization is not allowed.</p> <p>This feature is supported only for Horizon Client for Windows, and only for the English, French, German, Japanese, Korean, Spanish, Simplified Chinese, and Traditional Chinese locales.</p>
LogCnt	An integer	-1	<p>Use this option to set the reserved log file count in /tmp/vmware-root.</p> <ul style="list-style-type: none"> ■ -1 - keep all ■ 0 - delete all ■ > 0 - reserved log count.
NetbiosDomain	A text string, in all caps		When configuring True SSO, use this option to set the NetBIOS name of your organization's domain.
OfflineJoinDomain	pbis or a text string	pbis	Use this option to set the instant-clone offline domain join. Currently, the PowerBroker Identity Services Open (PBISO) authentication is the only way to perform an offline domain join. If this property has a value other than pbis, the offline domain join is ignored.
RunOnceScript			<p>Use this option to rejoin the cloned virtual machine to Active Directory.</p> <p>Set the RunOnceScript option after the host name has changed. The specified script is run only once after the first host name change. The script is run with the root permission when the agent service starts and host name has been changed since the agent installation.</p> <p>For example, for the winbind solution, you must join the base virtual machine to Active Directory with winbind, and set this option to a script path. This must contain the domain rejoin command /usr/bin/net ads join -U <ADUserName>%<ADUserPassword>. After VM Clone, the operating system customization changes the host name. When the agent service starts, the script is run to join the cloned virtual machine to Active Directory.</p>
RunOnceScriptTimeout		120	<p>Use this option to set the timeout time in seconds for the RunOnceScript option.</p> <p>For example, set RunOnceScriptTimeout=120</p>
SSLCiphers	A text string	!aNULL:kECDH+AESGCM:ECDH+AESGCM:RSA+AESGCM:kECDH+AES:ECDH+AES:RSA+AES	<p>Use this option to specify the list of ciphers. You must use the format that is defined in https://www.openssl.org/docs/manmaster/man1/ciphers.html.</p>

Table 7-2. Configuration Options in /etc/vmware/viewagent-custom.conf (Continued)

Option	Value	Default	Description
SSLProtocols	A text string	TLSv1_1:TLSv1_2	Use this option to specify the security protocols. The supported protocols are TLSv1.0, TLSv1.1, and TLSv1.2.
SSODesktopType	UseGnomeClassic or UseGnomeFlashback or UseGnomeUbuntu or UseMATE or UseKdePlasma or		<p>This option specifies the desktop environment to use, instead of the default desktop environment, when SSO is enabled.</p> <p>You must first ensure that the chosen desktop environment is installed on your desktop before specifying to use it. After this option is set in an Ubuntu 14.04/16.04/18.04 desktop, the option takes effect regardless if the SSO feature is enabled or not. If this option is specified in a RHEL/CentOS 7.x desktop, the chosen desktop environment is used only if SSO is enabled.</p> <p>Note This option is not supported on RHEL/CentOS 6 and SLED 11 desktops. See Desktop Environment for more information on how to set up KDE as the default desktop environment when SSO is enabled on these desktops.</p>
SSOEnable	true or false	true	Set this option to enable/disable single sign-on (SSO).
SSOUserFormat	A text string	[username]	<p>Use this option to specify the format of the login name for single sign-on. The default is the user name only. Set this option if the domain name is also required. Typically, the login name is the domain name plus a special character followed by the user name. If the special character is the backslash, you must escape it with another backslash. Examples of login name formats are as follows:</p> <ul style="list-style-type: none"> ■ SSOUserFormat=[domain]\\[username] ■ SSOUserFormat=[domain]+[username] ■ SSOUserFormat=[username]@[domain]
EndpointVPNEnable	true or false	false	<p>Set this option to specify if the client's physical network card IP address or the VPN IP address is to be used when evaluating the endpoint IP address against the range of endpoint IP addresses used in the User Environment Manager Console. If the option is set to false, the client's physical network card IP address is used. Otherwise, the VPN IP address is used.</p>
UEMEnable	true or false	false	<p>Set this option to enable or disable User Environment Manager smart policies. If the option is set to enable, and the condition in the User Environment Manager smart policy is met, then the policies are enforced.</p>
UEMNetworkPath	A text string		<p>This option must be set to the same network path that is set in User Environment Manager Console. The path must be in the format similar to //10.111.22.333/view/LinuxAgent/UEMConfig.</p>

Note The three security options, SSLCiphers, SSLProtocols, and SSLCipherServerPreference are for the VMwareBlastServer process. When starting the VMwareBlastServer process, the Java Standalone Agent passes these options as parameters. When Blast Secure Gateway (BSG) is enabled, these options affect the connection between BSG and the Linux desktop. When BSG is disabled, these options affect the connection between the client and the Linux desktop.

Using Smart Policies

You can use Smart Policies to create policies that control the behavior of the USB redirection, clipboard redirection, and client drive redirection features on specific remote Linux desktops.

With Smart Policies, you can create policies that take effect only if certain conditions are met. For example, you can configure a policy that disables the client drive redirection feature if a user connects to a remote desktop from outside your corporate network.

Requirements for Smart Policies

To use Smart Policies, your Horizon 7 environment must meet certain requirements.

- You must install Horizon Agent 7.5 or later and VMware User Environment Manager 9.4 or later on the remote desktops that you want to manage with Smart Policies.
- Users must use Horizon Client 4.8 or later to connect to remote Linux desktops that you manage with Smart Policies.
- The UEMEnable option must be enabled and the UEMNetworkPath option must be set in the `/etc/vmware/viewagent-custom.conf` file. See [Setting Options in Configuration Files on a Linux Desktop](#).

Installing User Environment Manager

To use HorizonSmart Policies to control the behavior of remote desktop features on a remote Linux desktop, you must install User Environment Manager 9.4 or later on the remote Linux desktop.

You can download the User Environment Manager installer from the VMware Downloads page. You can install the User Environment Manager Management Console component on any desktop from which you want to manage the User Environment Manager environment.

For a linked-clone pool, you install User Environment Manager in the parent virtual machine that you use as a base image for the linked clones. For an RDS desktop pool, you install User Environment Manager on the RDS host that provides the published desktop sessions.

For User Environment Manager system requirements and complete installation instructions, see the *Installing and Configuring VMware User Environment Manager* document.

Configuring User Environment Manager

You must configure User Environment Manager before you can use it to create smart policies for remote desktop features.

To configure User Environment Manager, follow the configuration instructions in the *VMware User Environment Manager Administration Guide*.

Horizon Smart Policy Settings

You control the behavior of remote desktop features in User Environment Manager by creating a Horizon smart policy.

[Table 7-3](#) describes the settings that you can select when you use User Environment Manager to define a Horizon smart policy for remote Linux desktops.

Table 7-3. Horizon Smart Policy Settings

Setting	Description
USB redirection	Determines whether USB redirection is enabled on the remote desktop. The USB redirection feature allows users to use locally attached USB devices, such as thumb flash drives, cameras, and printers, from the remote desktop. If you use a smart policy to configure USB redirection, you must use User Environment Manager 9.5 or later.
Clipboard	<p>Determines the direction in which clipboard redirection is allowed. You can select one of these values:</p> <ul style="list-style-type: none"> ■ Disable. Clipboard redirection is disabled in both directions. ■ Allow all. Clipboard redirection is enabled. Users can copy and paste from the client system to the remote desktop and from the remote desktop to the client system. ■ Allow copy from client to agent. Users can copy and paste only from the client system to the remote desktop. ■ Allow copy from agent to client. Users can copy and paste only from the remote desktop to the client system.
Client drive redirection	<p>Determines whether client drive redirection is enabled on the remote desktop and if shared drives and folders are writeable. You can select one of these values:</p> <ul style="list-style-type: none"> ■ Disable. Client drive redirection is disabled on the remote desktop. ■ Allow all. Client drives and folders are shared with the remote desktop and are readable and writeable. ■ Read-only. Client drives and folders are shared with the remote desktop and are readable, but not writeable. <p>If you do not configure this setting, whether shared drives and folders are writeable depends on whether you have enabled the CDREnable option in the <code>/etc/vmware/viewagent-custom.conf</code> file. For more information, see Setting Options in Configuration Files on a Linux Desktop.</p>

In general, Horizon smart policy settings that you configure for remote desktop features in User Environment Manager override any equivalent registry key and group policy settings.

Adding Conditions to Horizon Smart Policy Definitions

When you define a Horizon Smart Policy in User Environment Manager, you can add conditions that must be met for the policy to take effect. For example, you can add a condition that disables the client drive redirection feature only if a user connects to the remote desktop from outside your corporate network.

Important You must add the following conditions to a Horizon Smart Policy definition in order for the supported policy settings to take effect in a remote Linux desktop. These are the only conditions that are currently supported. If other conditions are set, the end result of the condition evaluation is false.

Table 7-4. Required Conditions for Remote Linux Desktops

Condition	Description
Operating System Architecture	Checks the architecture of the operating system. The value must be set to Linux.
Endpoint IP address	Checks whether the endpoint IP address is in or not in the specified range. Empty fields at the start of the range are interpreted as 0, and the ones at the end as 255.

You can, however, set multiple Endpoint IP address conditions, as shown in the following example.

```
Operating system is Linux
AND Endpoint IP address is in range 11.22.33.44 – 11.22.33.54
OR Endpoint IP address is in range 11.22.33.66 – 11.22.33.77
```

For detailed information about adding and editing conditions in the User Environment Manager Management Console, see the *VMware User Environment Manager Administration Guide*.

Create a Horizon Smart Policy in User Environment Manager

You use the User Environment Manager Management Console to create a Horizon smart policy in User Environment Manager. When you define a Horizon smart policy, you can add conditions that must be met for the smart policy to take effect.

Prerequisites

- Install and configure User Environment Manager. See [Installing User Environment Manager](#) and [Configuring User Environment Manager](#).
- Become familiar with the conditions that you can add to Horizon Smart Policy definitions. See [Adding Conditions to Horizon Smart Policy Definitions](#).

- Enable the `UEMEnable` option and configure the `UEMNetworkPath` option in the `/etc/vmware/viewagent-custom.conf` file. See [Setting Options in Configuration Files on a Linux Desktop](#).

Note In a high-latency network, after saving your new or updated smart policy, allow User Environment Manager at least a minute to complete processing the changes before notifying the end users to connect to the affected desktops.

For complete information about using the User Environment Manager Management Console, see the *VMware User Environment Manager Administration Guide* document.

Procedure

- 1 In the User Environment Manager Management Console, select the **User Environment** tab and click **Horizon Smart Policies** in the tree view.

Existing Horizon smart policy definitions, if any, appear in the Horizon Smart Policies pane.

- 2 Right-click **Horizon Smart Policies** and select **Create Horizon Smart Policy definition** to create a new smart policy.

The Horizon Smart Policy dialog box appears.

- 3 Select the **Settings** tab and define the smart policy settings.

- a In the General Settings section, enter a name for the smart policy in the **Name** text box.

For example, if the smart policy affects the client drive redirection feature, you might name the smart policy CDR.

- b In the Horizon Smart Policy Settings section, select the remote desktop features and settings to include in the smart policy.

You can select multiple remote desktop features.

- 4 Add the conditions required to use the new smart policy with remote Linux desktops.

- a Select the **Conditions** tab, click **Add**, and select the **Operating System Architecture** condition.

- b Set the value to **Linux**.

```
Operating System is Linux
```

- c Click **Add** and select the **Endpoint IP Address** condition.

The **AND** operator is added by default.

- d In the Endpoint IP Address dialog box, set the endpoint IP address range, and click **OK**.

Following is an example of the condition statement.

```
Operating System is Linux
AND Endpoint IP address is in range 11.22.33.44 – 11.22.33.54
```

5 Click **Save** to save the smart policy.

User Environment Manager processes the Horizon smart policy each time a user connects or reconnects to the remote desktop.

User Environment Manager processes multiple smart policies in alphabetical order based on the smart policy name. Horizon smart policies appear in alphabetical order in the Horizon Smart Policies pane. If smart policies conflict, the last smart policy processed takes precedence. For example, if you have a smart policy named Sue that enables USB redirection for the user named Sue, and another smart policy named Pool that disables USB redirection for the desktop pool named Ubuntu1604, the USB redirection feature is enabled when Sue connects to a remote desktop in the Ubuntu1604 desktop pool.

Example Blast Settings for Linux Desktops

You can adjust the image quality of your remote desktop display to improve the user experience. Improving image quality is helpful in maintaining a consistent user experience when there is a bad network connection.

Example VMware Blast Extreme Protocol Settings

VMwareBlastServer and its related plug-ins use the configuration file `/etc/vmware/config`.

Table 7-5. Example Blast Configuration Options in `/etc/vmware/config`

Option name	Parameter	High-speed LAN	LAN	Dedicated WAN	Broadband WAN	Low-speed WAN	Extremely Low speed
Bandwidth settings	RemoteDisplay.maxBandwidthKbps	1000000 (1 Gbps)	1000000 (1 Gbps)	1000000 (1 Gbps)	5000 (5 Mbps)	2000 (2 Mbps)	1000 (1 Mbps)
Max FPS	RemoteDisplay.maxFPS	60	30	30	20	15	5
Audio Playback	RemoteDisplay.allowAudio	TRUE	TRUE	TRUE	TRUE	TRUE	FALSE
Display Quality (JPEG/PNG)	RemoteDisplay.maxQualityJPEG	90	90	90	70	60	50
Display Quality (JPEG/PNG)	RemoteDisplay.midQualityJPEG	35	35	35	35	35	35
Display Quality (JPEG/PNG)	RemoteDisplay.minQualityJPEG	25	25	25	20	20	20
Display Quality (H.264)	RemoteDisplay.qpmaxH264	28	36	36	36	36	42
Display Quality (H.264)	RemoteDisplay.qpminH264	10	10	10	10	10	10

Examples of Client Drive Redirection Options for Linux Desktops

Configure client drive redirection (CDR) options to determine whether a local system's shared folders and drives can be accessed from the remote Linux desktops.

Configure CDR settings by adding entries to the `/etc/vmware/config` file.

The following configuration example shares the `d:\ebooks` and `C:\spreadsheets` folders, makes both folders read-only, and prevents the client from sharing more folders.

```
cdserver.forcedByAdmin=true
cdserver.sharedFolders=d:\ebooks,;c:\spreadsheets,
cdserver.permissions=R
```

In the previous example, the comma `,` placed after **ebooks** and **spreadsheets** is mandatory for correct option parsing.

Any **"R"** included in the `cdserver.sharedFolders` option would impact all the folders listed in that setting. In the following example, the **ebooks** and **spreadsheets** folders are both read-only even if the **R** value is only placed after `/home/jsmith` folder path.

```
cdserver.sharedFolders=d:\ebooks,;c:\spreadsheets,;/home/jsmith,R
```

Suppress the vSphere Console Display of a Linux Desktop

When a user connects to a Linux desktop, the desktop can also be displayed in the vSphere console for the Linux virtual machine. You can configure Linux virtual machines to ensure that the vSphere console is blank when users connect to their desktops.

Procedure

- ◆ On the ESXi host, add the following line to the Linux virtual machine's `vmx` file.

```
RemoteDisplay.maxConnections = "0"
```

The vSphere console display remains blank even when you connect to the virtual machine when the user is logged out of the desktop.

Create and Manage Linux Desktop Pools

8

To configure Linux virtual machines for use as remote desktops, you must create a desktop pool with Linux virtual machines.

Horizon for Linux supports the following desktop pool types:

- Manual desktop pool with vCenter virtual machine
- Automated full-clone desktop pool
- Instant-clone floating desktop pool

To create a manual desktop pool with a vCenter virtual machine, you must install Horizon Agent on all virtual machines. Then, use the Connection Server desktop pool creation wizard to add the virtual machines to the desktop pool. To clone a large number of virtual machines, see [Overview of Bulk Deployment of Linux Desktops](#).

To create an automated full-clone desktop pool, you must install Horizon 7 Agent on a Linux virtual machine template. Then, use the Connection Server desktop pool creation wizard to clone full virtual machines.

To create an instant clone floating desktop pool, you must install Horizon 7 Agent on a Linux virtual machine with PBIS Open environment setup, and create a template from it. Then, use the Connection Server desktop pool creation wizard to create instant-clone floating desktop pool.

This chapter includes the following topics:

- [Create a Manual Desktop Pool for Linux](#)
- [Manage Desktop Pool for Linux](#)
- [Create an Automated Full-Clone Desktop Pool for Linux](#)
- [Create an Instant-Clone Floating Desktop Pool for Linux](#)
- [Broker PowerCLI Commands](#)

Create a Manual Desktop Pool for Linux

You can create a manual desktop pool for Linux virtual machines.

Prerequisites

- Verify that Horizon Agent is installed on the Linux guest operating systems. See [Install Horizon Agent on a Linux Virtual Machine](#).
- Verify that VMware vCenter Server is added to Horizon Connection Server .

Procedure

- 1 In View Administrator, add a manual desktop pool.
Select **Catalog > Desktop Pools > Add** .
- 2 Select **Manual Desktop Pool**.
- 3 On the User assignment page, select either dedicated or floating user assignments for the machines in the desktop pool and click **Next**.
- 4 On the Machine Source page, select **vCenter virtual machines** and click **Next**.
- 5 On the vCenter Server page, select the appropriate vCenter Server and click **Next**.
- 6 Enter the **desktop pool id**.
- 7 On the Desktop Pool Settings page, set the following options.

Option	Description
Default display protocol	VMware Blast
Allow users to choose protocol	No
3D Renderer	Manage using vSphere Client for 2D, vSGA, or vDGA desktop and NVIDIA GRID vGPU for vGPU desktop

Note The pool settings are mandatory. Else, you might fail to connect to the desktop and get a protocol error or a black screen.

- 8 On the Add vCenter Virtual Machines page, select the linux virtual machine. Click **Add** and click **Next**.

Note Do not create Windows and Linux virtual machines in the same desktop pool.

- 9 To complete the procedure, follow the prompts.

Entitle users to the machines in the desktop pool. In View Administrator, select the desktop pool, select **Entitlements > Add entitlement**, and add users or groups.

The Linux virtual machines are ready to be used as remote desktops in a Horizon 7 deployment.

Manage Desktop Pool for Linux

When you create a manual desktop pool and add Linux machines to the pool, you can manage the manual desktop pools by configuring the settings. You must add only Linux guest operating systems to the manual desktop pool. If the pool contains both Windows and Linux guest operating systems, the pool is treated as a Windows pool, and you cannot connect to the Linux desktops.

Support for Managing Operations

- Disable or Enable desktop pool
- Clone automated desktop pool
- Delete desktop pool

You can either remove virtual machines from View Manager or delete virtual machines from the disk.

Support for Remote Settings

Table 8-1. Remote Settings

Remote Setting	Options
Remote Machine Power Policy	<ul style="list-style-type: none"> ■ Take no power action ■ Ensure machines are always powered on ■ Suspend ■ Power off
Automatically logoff after disconnect	<ul style="list-style-type: none"> ■ Immediately ■ Never ■ After n minutes
Allow users to reset/restart their machines	<ul style="list-style-type: none"> ■ Yes ■ No
Allow user to initiate separate sessions from different client devices	<ul style="list-style-type: none"> ■ Yes ■ No
"Delete machine after logoff" for Automated Desktop Pool with Full Clone and Floating	<ul style="list-style-type: none"> ■ Yes ■ No

Support for View Administrator Operations

- Disconnect Session
- Logoff Session
- Reset/Restart Desktop
- Send Message

For a dedicated desktop pool, you can add or remove a user assignment for each virtual machine. For large number of operations, you must use View PowerCLI Cmdlets.

- Update-UserOwnership

- Remove-UserOwnership

Note Do not change **Remote Display Protocol** settings. This setting must always be the same as a desktop pool creation.

Setting	Option
Default display protocol	VMware Blast
Allow user to choose protocol	No
3D Renderer	<ul style="list-style-type: none"> ■ Manage using vSphere Client for 2D or vSGA or vDGA ■ NVIDIA GRID vGPU

For more information, see *View Administration* guide.

Create an Automated Full-Clone Desktop Pool for Linux

You can create an automated full-clone desktop pool for Linux virtual machines. After you create the automated full-clone desktop pool, you can use the Linux virtual machines as remote desktops in a Horizon 7 deployment.

Prerequisites

- Verify that Horizon Agent is installed on the Linux guest operating systems. See [Install Horizon Agent on a Linux Virtual Machine](#).
- If you use the Winbind solution to join the Linux virtual machine to Active Directory, you must finish configuring the Winbind solution in the virtual machine template.
- If you use the Winbind solution, you must run the domain join command on the virtual machine. Include the command in a shell script and specify the script path to the Horizon Agent option RunOnceScript in `/etc/vmware/viewagent-custom.conf`. For more information, see [Setting Options in Configuration Files on a Linux Desktop](#).
- Verify that vCenter Server is added to Horizon Connection Server.

Procedure

- 1 Create a guest customization specification.

See "Create a Customization Specification for Linux in the vSphere Web Client" in the *vSphere Virtual Machine Administration* document. When you create the specification, make sure that you specify the following settings correctly.

Setting	Value
Target Virtual Machine OS	Linux
Computer Name	Use the virtual machine name.
Domain	Specify the domain of the View environment.

Setting	Value
Network Settings	Use standard network settings.
Primary DNS	Specify a valid address.

Note For more information on Guest OS Customization Support Matrix, see <http://partnerweb.vmware.com/programs/guestOS/guest-os-customization-matrix.pdf>.

- 2 In Horizon Administrator, select **Catalog > Desktop Pools > Add**.
- 3 Select **Automated Desktop Pool** and click **Next**.
- 4 Select either dedicated or floating user assignments for the machines in the desktop pool and click **Next**.
- 5 On the vCenter Server page, select **Full virtual machines** and select the appropriate vCenter server, and click **Next**.
- 6 On the Desktop Pool Identification page, enter the desktop pool ID and click **Next**.
- 7 On the Desktop Pool Settings page, set the following options and click **Next**.

Option	Description
Default display protocol	VMware Blast
Allow users to choose protocol	No
3D Renderer	Manage using vSphere Client for 2D, vSGA, or vDGA desktop and NVIDIA GRID vGPU for vGPU desktop

Note The pool settings are mandatory. Else, you might fail to connect to the desktop and get a protocol error or a black screen.

- 8 On the Provisioning Settings page, set the **Virtual Machine Naming** options and click **Next**.

Option	Description
Specify names manually	Enter names manually.
Use a naming pattern	For example, specify LinuxVM-{n}. You must also specify the following desktop pool sizing options: <ul style="list-style-type: none"> ■ Maximum number of machines ■ Number of spare, powered-on machines

- 9 On the Storage Optimization page, select a storage management policy and click **Next**.
- 10 On the vCenter Settings page, you must click Browse and select the vCenter Server settings in sequence and click **Next**.

You cannot skip a vCenter Server setting:

- a Template
- b VM folder location
- c Host or cluster

- d Resource pool
- e Datastores

- 11 On the Advanced Storage Options page, select the appropriate storage options and click **Next**.
- 12 On the Guest Customization page, select your guest customization for Linux and click **Next**.
- 13 On the Ready to Complete page, review the details and select **Entitle users after this wizard finishes**.
- 14 Click **Finish**.
- 15 To entitle users to the machines in the desktop pool, select the desktop pool and click **Entitlements > Add entitlements** and add the users and groups.
- 16 Wait until all the Linux virtual machines in the desktop pool become available.

Create an Instant-Clone Floating Desktop Pool for Linux

You can create an instant-clone floating desktop pool for Linux virtual machines using the **Add Desktop Pool** wizard. After creating an instant-clone floating desktop pool, you can use the Linux virtual machines as remote desktops in a Horizon 7 deployment.

Prerequisites

- Familiarize yourself with the steps for creating virtual machines in vCenter Server and installing Linux operating systems. For more information, see [Create a Virtual Machine and Install Linux](#).
- Understand the steps for AD integration using the PBISO authentication solution. For more information, see the PowerBroker Identity Services Open (PBISO) Authentication section in [Integrating Linux with Active Directory](#).
- Familiarize yourself with the installation steps for Horizon 7 Agent for Linux. For more information, see [Install Horizon Agent on a Linux Virtual Machine](#).
- Understand the steps to take a snapshot of a powered off Linux VM using VMware vSphere® Web Client. See "Take a Snapshot in the VMware Host Client" in *vSphere Single Host Management - VMware Host Client*.
- Verify that vCenter Server is added to Horizon Connection Server.

Procedure

- 1 Create a Linux virtual machine (VM) with Ubuntu 14.04/16.04/18.04, or RHEL 7.1 or later installed.

Note This feature is supported only on systems with Ubuntu 14.04/16.04/18.04 or RHEL 7.1 or later.

For more information, see [Create a Virtual Machine and Install Linux](#).

- 2 Manually install Open VMware Tools (OVT) on your Ubuntu 14.04/16.04/18.04 machine using the following command:

```
apt-get install open-vm-tools
```

See [Prepare a Linux Machine for Remote Desktop Deployment](#) for additional information.

- 3 Install any dependency packages that are required for the Linux distribution.

See [Install Dependency Packages for Horizon Agent](#) for more information.

- 4 Install Horizon Agent for Linux in the Linux VM.

```
sudo ./install_viewagent.sh -A yes
```

See [Install Horizon Agent on a Linux Virtual Machine](#) for details.

- 5 Integrate your Linux VM with Active Directory.

- To use the PBISO authentication solution, perform the following steps:

- a Download PBIS Open 8.5.6 or later from <https://www.beyondtrust.com/products/powerbroker-identity-services-open/> and install it on your Linux VM.

```
sudo ./pbis-open-8.5.6.2029.linux.x86_64.deb.sh
```

- b Integrate your Linux VM with Active Directory using the information in PowerBroker Identity Services Open (PBISO) Authentication section in [Integrating Linux with Active Directory](#).

- If you choose not to use PBISO to integrate your Linux VM with Active Directory, you must set the OfflineJoinDomain option to **none** in the `/etc/vmware/viewagent-custom.conf` file. Otherwise, the creation of the instant-clone floating desktop pool fails.

- 6 If your DHCP server does not broadcast to a DNS server, specify a DNS server for your Linux system.

A new virtual network adapter is added when a new instant-cloned VM is created. Any setting in the network adapter, such as the DNS server, in the VM template is lost when the new network adapter is added to the instant-cloned VM. PBIS requires a valid DNS server and the FQDN mapping in the `/etc/hosts` is not acceptable. To avoid losing the DNS Server setting when the new network adapter is added to the cloned VM, you must specify a DNS server in your Linux system. For example, in an Ubuntu 14.04 or 16.04 system, specify the DNS server by adding the following lines in the `/etc/resolvconf/resolv.conf.d/head` file.

```
nameserver 10.10.10.10
search mydomain.org
```

- 7 (Optional) If you want to add an NFS mount in the `/etc/fstab` file of the master Linux VDI instant-clone agent, use one of the following methods.

- Add a 'soft' flag in `/etc/fstab`, such as:

```
10.111.222.333:/share    /home/nfsmount    nfs    rsize=8192,wsiz=8192,timeo=14,soft,intr,tcp
```

- If you do not want to use the 'soft' flag in `/etc/fstab`, you cannot configure the `/etc/fstab` in the master Linux VM image. You can write a power-off script to configure the `/etc/fstab` file, then specify this power-off script in the Guest Customization pane of the instant-clone desktop pool wizard in Horizon Administrator.
- 8 Shut down the Linux VM and create a master image by creating a snapshot of your powered off Linux VM using VMware vSphere® Web Client.

See "Take a Snapshot in the VMware Host Client" in *vSphere Single Host Management - VMware Host Client* for information.

- 9 In Horizon Administrator, select **Catalog > Desktop Pools > Add**.

- 10 Define the desktop pool.

- a On the Type pane, select the **Automated Desktop Pool** and click **Next**.
- b On the User Assignment pane, select **Floating**. Click **Next**.
- c Select **Instant clones** on the vCenter Server pane.

- 11 Enter the desktop pool ID on the Desktop Pool Identification pane and click **Next**.

- 12 On the Desktop Pool Settings pane, accept the default settings and enable HTML Access. Click **Next**.

- 13 Set the following **Virtual Machine Naming** options on the Provisioning Settings pane and click **Next**.

- Select **Enable provisioning** and **Stop provisioning on error**.
- In the **Naming Pattern** text box, specify a pattern that Horizon 7 uses as a prefix in all the desktop VM names, followed by a unique number. For example, specify **LinuxVM-{n}**.
- In the **Max number of machines** text box, specify the total number of machines in the pool.
- In the **Number of spare (powered on) machines** text box, specify the number of desktop VMs to keep available to users.
- Select **Provision all machines up-front** to have Horizon 7 provision the number of VMs you specify in **Max number of machines**.

- 14 Select **Use VMware Virtual SAN** for the storage management policy on the Storage Optimization pane and click **Next**.

- 15 On the vCenter Settings pane, click **Browse** for each vCenter Server setting, select the appropriate value for each setting, and click **Next**.

- 16** On the Guest Customization pane, specify the Domain setting, AD container, and any extra customization scripts that must be run after the VM is cloned. Click **Next**.

Important When you use ClonePrep power-off or post-synchronization scripts, ensure that the scripts are located in the /var/userScript folder, owned by the root user, and have the file permissions set to 700.

- 17** Select the **Entitle users after this wizard finishes** on the Ready to Complete pane and review the details.
- 18** Click **Finish**.

In Horizon Administrator, you can view the desktop VMs as they are added to the pool by selecting **Catalog > Desktop Pools**.

After you create the pool, do not delete the master image or remove it from the vCenter Server inventory if the pool exists. If you remove the master image VM from the vCenter Server inventory by mistake, you must add it back and then do a push image using the current image.

What to do next

Entitle users to access the pool. See "Add Entitlements to Desktop Pools" in *Setting Up Virtual Desktops in Horizon 7*.

Broker PowerCLI Commands

The Horizon PowerCLI cmdlets, which are used to perform various administration tasks on Connection Server and a Windows desktop, can also be used for Linux desktops.

Create a Manual Desktop Pool

```
Add-ManualPool -DefaultProtocol Blast -AllowProtocolOverride $false -threedRender usevc|vgpu -Pool_id
<pool id> [more parameters]
```

The following options and values are mandatory for the Linux desktop.

- DefaultProtocol Blast
- AllowProtocolOverride \$false
- threedRender usevc|vgpu. For a vGPU desktop, use -threedRender vgpu and for a 2D/vSGA/vDGA desktop, use -threedRender usevc .

Examples

- Create a floating Linux Desktop pool named LinuxDesktop with a virtual machine (VM), LinuxVM-01.

```
Add-ManualPool -DefaultProtocol Blast -AllowProtocolOverride $false -threedRender usevc -Pool_id
LinuxDesktop -Id (Get-DesktopVM -Name LinuxVM-01).id -Persistence NonPersistent -Vc_name
myvc.myorg.org
```

- Create a dedicated Linux vGPU desktop pool named LinuxDesktop with all VMs that begin with the VM name as LinuxVM-.

```
Get-DesktopVM | Where-Object {$_.Name.StartsWith("LinuxVM-")} | Add-ManualPool -DefaultProtocol
Blast -AllowProtocolOverride $false -Persistence Persistent -threadRender vgpu -Pool_id
LinuxDesktop
```

- Create floating Linux desktop pool LinuxDesktop with the first RHEL 6 x64 VM.

```
Get-DesktopVM | Where-Object {$_.GuestID -eq "rhel6_64Guest"} | Select-Object -Index 0 | Add-
ManualPool -DefaultProtocol Blast -AllowProtocolOverride $false -Persistence NonPersistent -
threadRender usevc -Pool_id LinuxDesktop
```

Create a Full-Clone Automated Desktop Pool

```
Add-AutomaticPool -DefaultProtocol Blast -AllowProtocolOverride $false -threadRender usevc|vgpu `
-pool_id <pool id> -Vc_id <vCenter id> `
-NamePrefix <VM Name Prefix> `
-templatePath <Virtual Machine Template Path> `
-vmFolderPath <Virtual Machine Folder Path> `
-resourcePoolPath <Resource Pool Path> `
-dataStorePaths <Datastore Path> `
-customizationSpecName <Customization Specification Name> `
[more parameters]
```

The following options and values are mandatory for Linux desktops.

- DefaultProtocol Blast
- AllowProtocolOverride \$false
- threadRender usevc|vgpu For a vGPU desktop, use -threadRender vgpu and for a 2D/vSGA desktop, use -threadRender usevc.

Example

```
Add-AutomaticPool -DefaultProtocol Blast -AllowProtocolOverride $false -threadrender usevc `
-pool_id FullClone-Linux `
-Vc_id (Get-ViewVC -serverName myvc.myorg.org).vc_id `
-NamePrefix "FullClone-{n:fixed=3}" `
-Persistence NonPersistent -deletePolicy DeleteOnUse `
-vmFolderPath "/LinuxVDI/vm/FullClone" `
-resourcePoolPath "/LinuxVDI/host/LinuxVDICluster/Resources" `
-templatePath "/LinuxVDI/vm/LinuxTemplate" `
-dataStorePaths "/LinuxVDI/host/LinuxVDICluster/datastore" `
-customizationSpecName "linux-spec" `
-maximumCount 100
```

Add or Remove Desktop Pool Entitlement

- Entitle a domain user group of domain mydomain.org to LinuxDesktop.

```
Add-PoolEntitlement -Pool_id LinuxDesktop -Sid (Get-User -Name "domain user" -Domain "mydomain.org").sid
```

- Remove the entitlement of a domain user group of mydomain.org domain from LinuxDesktop.

```
Remove-PoolEntitlement -Pool_id LinuxDesktop -Sid (Get-User -Name "domain user" -Domain "mydomain.org").sid
```

Assign or Remove User to or from the VM in Dedicated Desktop Pool

- Assign the **myuser** user to the LinuxVM-01 VM, which is in a dedicated desktop pool.

```
Update-UserOwnership -Machine_id (Get-DesktopVM -Name "LinuxVM-01").machine_id -Sid (Get-User -Name "myuser" | Where-Object {$_.cn -eq "myuser"}).sid
```

- Remove the **myuser** user from the LinuxVM-01 VM, which is in a dedicated desktop pool.

```
Remove-UserOwnership -Machine_id (Get-DesktopVM -Name "LinuxVM-01").machine_id
```

Logoff Desktop Connection

- Log out from the desktop session of myuser.

```
Get-RemoteSession -Username "mydomain.org\myuser" | Send-SessionLogoff
```

For more information on the broker PowerCLI cmdlet, see "Using View PowerCLI" in *Horizon 7 Integration*.

Bulk Deployment of Horizon 7 for Manual Desktop Pools

9

With View Administrator, you can create a pool of Windows, but not Linux, desktop machines automatically. However, you can develop scripts that automate the deployment of a pool of Linux desktop machines.

The sample scripts that are provided are for illustration purposes only. VMware does not accept any responsibility for issues that might arise when you use the sample scripts.

This chapter includes the following topics:

- [Overview of Bulk Deployment of Linux Desktops](#)
- [Overview of Bulk Upgrade of Linux Desktops](#)
- [Create a Virtual Machine Template for Cloning Linux Desktop Machines](#)
- [Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#)
- [Sample Script to Clone Linux Virtual Machines](#)
- [Sample Script to Join Cloned Virtual Machines to AD Domain](#)
- [Sample Script to Join Cloned Virtual Machines to AD Domain Using SSH](#)
- [Sample Script to Upload Configuration Files to Linux Virtual Machines](#)
- [Sample Script to Upload Configuration Files to Linux Virtual Machines Using SSH](#)
- [Sample Script to Upgrade Horizon Agent on Linux Desktop Machines](#)
- [Sample Script to Upgrade Horizon Agent on Linux Virtual Machines Using SSH](#)
- [Sample Script to Perform Operations on Linux Virtual Machines](#)

Overview of Bulk Deployment of Linux Desktops

Deploying manual desktops for Linux involve several steps. If you plan to deploy more than a few desktops, you can automate some of the steps by using PowerCLI scripts.

For some operations, you can choose to have either PowerCLI or SSH execute the commands on the Linux machine. The following table describes the differences between the two approaches.

PowerCLI	SSH
No need to install additional tools.	<ul style="list-style-type: none"> For Ubuntu, you need to install the SSH server with the command <code>sudo apt-get install openssh-server</code>. For RHEL and CentOS, <code>openssh-server</code> is installed by default but you need to ensure that the firewall settings allow ssh. Need to download the SSH client applications <code>pscp.exe</code> and <code>plink.exe</code> and put them in the same folder as the PowerCLI scripts.
Uploading files and command execution are slower.	Uploading files and command execution are faster.
Need to supply the ESXi host's administrator credentials.	No need to supply the ESXi host's administrator credentials.
Cannot handle special characters in the administrator's password when running the script to install Horizon Agent or the AD user's password when running the script to join the domain.	Can handle special characters in the administrator's password when running the script to install Horizon Agent or the AD user's password when running the script to join the domain.

Note Both PowerCLI-based and SSH-based scripts can handle special characters in the passwords for the vCenter Server administrator and the Linux administrator. PowerCLI-based scripts can also handle special characters in the ESXi host administrator's password. In all these cases, an escape character is not necessary.

For more information about vSphere PowerCLI, see <https://www.vmware.com/support/developer/PowerCLI>.

The process of bulk deploying a pool of Linux desktops involves the following steps:

- 1 Create a virtual machine template and install Horizon Agent on the virtual machine.

See [Create a Virtual Machine Template for Cloning Linux Desktop Machines](#).

- 2 Create a guest customization specification.

See "Create a Customization Specification for Linux in the vSphere Web Client" in the *vSphere Virtual Machine Administration* document. When you create the specification, make sure that you specify the following settings correctly.

Setting	Value
Target Virtual Machine OS	Linux
Computer Name	Use the virtual machine name.
Domain	Specify the domain of the View environment.
Network Settings	Use standard network settings.
Primary DNS	Specify a valid address.

Note For more information on Guest OS Customization Support Matrix, see <http://partnerweb.vmware.com/programs/guestOS/guest-os-customization-matrix.pdf>.

3 Clone virtual machines.

See [Sample Script to Clone Linux Virtual Machines](#).

4 Join the cloned VMs to the Active Directory (AD) domain if you are using the winbind solution. You can run the domain join command with example scripts below or use option RunOnceScript in `/etc/vmware/viewagent-custom.conf`, configured in the template virtual machine.

See [Sample Script to Join Cloned Virtual Machines to AD Domain](#) or [Sample Script to Join Cloned Virtual Machines to AD Domain Using SSH](#).

5 Update configuration options in virtual machines.

See [Sample Script to Upload Configuration Files to Linux Virtual Machines](#) or [Sample Script to Upload Configuration Files to Linux Virtual Machines Using SSH](#).

6 Create a desktop pool.

See [Create a Manual Desktop Pool for Linux](#).

For a sample script that performs operations such as powering on, shutting down, restarting, or deleting virtual machines, see [Sample Script to Perform Operations on Linux Virtual Machines](#). This script can delete virtual machines from vCenter Server.

Overview of Bulk Upgrade of Linux Desktops

Bulk upgrade of manual desktops for Linux involve several steps. You can automate some of the steps by using PowerCLI scripts.

Bulk Upgrade Unmanaged Desktop

To bulk upgrade the unmanaged virtual machine to managed or unmanaged virtual machine, you must use the sample upgrade script to upload the new Horizon Agent to the existing virtual machines and run upgrade command.

- If you retain the unmanaged virtual machine, your existing desktop pool can be reused.
- If you upgrade from unmanaged virtual machine to managed virtual machine, you must delete the existing desktop pool and create a new desktop pool. For more information, see [Upgrade Horizon Agent on a Linux Virtual Machine](#).

Bulk Upgrade Managed Desktop

To bulk upgrade the managed virtual machine, select one of the following methods.

Method	Description
In the template virtual machine, install or upgrade the new Horizon Agent and create a snapshot.	<ul style="list-style-type: none"> ■ The user data and profile are lost since the existing virtual machines are deleted, unless the user data and profile are located on the share server such as NFS server. ■ After the virtual machine replacement, the state of the virtual machine on View Administrator might be missing. You must restart the broker service to fix it. ■ If you are using linked clone, this method avoids duplicate data on each virtual machine.
Use the sample script of upgrade to upload the new Horizon Agent to existing virtual machines and run the upgrade command.	<ul style="list-style-type: none"> ■ User data and profile is retained. ■ If you are using linked clone, this method introduces duplicate data on each virtual machine.

Create a Virtual Machine Template for Cloning Linux Desktop Machines

Before you perform virtual machine cloning, you must create a virtual machine template that the clones are based on.

Prerequisites

- Verify that your deployment meets the requirements for supporting Linux desktops. See [System Requirements For Horizon 7 for Linux](#).
- Familiarize yourself with the steps for creating virtual machines in vCenter Server and installing guest operating systems. See "Creating and Preparing Virtual Machines" in the *Setting Up Virtual Desktops in Horizon 7* document.
- Familiarize yourself with the recommended video memory (vRAM) values for the monitors you will use with the virtual machine. See [System Requirements For Horizon 7 for Linux](#).
- Familiarize yourself with the steps for AD integration. See [Chapter 3 Setting Up Active Directory Integration for Linux Desktops](#).
- Familiarize yourself with the steps to install Horizon Agent on Linux. See [Chapter 6 Installing Horizon Agent](#).
- If required, familiarize yourself with the steps to configure options using the Horizon 7 configuration files. See [Chapter 7 Configuration Options for Linux Desktops](#).
- If you plan to set up graphics, familiarize yourself with the steps. See [Chapter 5 Setting Up Graphics for Linux Desktops](#).

Procedure

- 1 In vSphere Web Client or vSphere Client, create a new virtual machine.

2 Configure custom configuration options.

- a Right-click the virtual machine and click **Edit Settings**.

- b Specify the number of vCPUs and the vMemory size.

For recommended values, follow the guidelines in the installation guide for your Linux distribution.

For example, Ubuntu 12.04 recommends configuring 2048 MB for vMemory and 2 vCPUs.

- c Select **Video card** and specify the number of displays and the total video memory (vRAM).

Set the vRAM size in vSphere Web Client for virtual machines that use 2D or vSGA, which use the VMware driver. The vRAM size has no affect on vDGA or NVIDIA GRID vGPU machines, which use NVIDIA drivers.

For recommended values, follow the guidelines in *System Requirements for Horizon 7 for Linux*. Do not use the Video Memory Calculator.

3 Power on the virtual machine and install the Linux distribution.

- 4 Create a user with root privileges, for example, ViewUser. This user is used to install and uninstall Horizon Agent only.

- 5 Edit `/etc/sudoers` and add the line `ViewUser ALL=(ALL) NOPASSWD:ALL`.

With this line in `/etc/sudoers`, no password is required to run `sudo` as ViewUser. When you run the sample script to install Horizon Agent that is provided in this chapter, you specify ViewUser as an input.

- 6 If the Linux distribution is RHEL, CentOS, or NeoKylin, edit `/etc/sudoers` and comment out the following lines:

```
Defaults requiretty
Defaults !visiblepw
```

- 7 If the Linux distribution is not RHEL 7, CentOS 7, SLED 12, or SLES 12, install VMware Tools .

RHEL 7, CentOS 7, SLED 12, and SLES 12 have Open VM Tools installed by default.

- 8 If the Linux distribution is RHEL 7, CentOS 7, or SLES 12, install the `deployPkg` plug-in.

The instructions are at <http://kb.vmware.com/kb/2075048>.

- 9 For RHEL and CentOS, enable the Network Connection setting **Connect automatically**.

- 10 Perform the AD integration tasks.

- 11 Perform the steps to set up graphics.

- 12 Install Horizon agent.

```
sudo ./install_viewagent.sh -A yes
```

See [Chapter 6 Installing Horizon Agent](#).

- 13 Perform additional configurations using the Horizon 7 configuration files.

14 Shut down the virtual machine and create a snapshot.

Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops

The sample PowerCLI scripts to deploy Linux desktops read one input file that contains information about the desktop machines.

The input file is of type csv and contains the following information:

- Desktop virtual machine name
- Parent virtual machine name
- Guest customization specification
- Datastore where the cloned desktop machine resides
- ESXi server that hosts the desktop machine
- Parent virtual machine's snapshot that is used for cloning
- Flag that indicates whether to delete the desktop virtual machine if it exists

The following example shows what the input file may contain.

```
VMName,Parentvm,CustomSpec,Datastore,Host,FromSnapshot,DeleteIfPresent
linux-001,Ubuntu1204x64,linuxagent,datastore1,10.117.44.172,snapshot1,TRUE
linux-002,Ubuntu1204x64,linuxagent,datastore1,10.117.44.172,snapshot1,TRUE
linux-003,Ubuntu1204x64,linuxagent,datastore1,10.117.44.172,snapshot1,TRUE
linux-004,Ubuntu1204x64,linuxagent,datastore1,10.117.44.172,snapshot1,TRUE
linux-005,Ubuntu1204x64,linuxagent,datastore1,10.117.44.172,snapshot1,TRUE
```

The sample scripts assume that the name of this input file is `CloneVMs.csv` and that the file is located in the same folder as the scripts.

Sample Script to Clone Linux Virtual Machines

You can customize and use the following sample script to clone any number of virtual machines (VMs).

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at <https://docs.vmware.com/en/VMware-Horizon-7/index.html>.

Script Input

This script reads one input file, which is described in [Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#). This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server

- Clone type, which can be linked or full
- Whether to disable a vSphere VM console

Script Content

```
<#
Create Clones from a Master VM

The Tool supports creation of Full clone and linked clone from Master VM.
The parent VM is required for the linked-clone to work and the parent VMs file cannot be renamed or
moved.
#>
#----- Functions -----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}

function IsVMExists ()
{
    Param($VMExists)
    Write-Host "Checking if the VM $VMExists already Exists"
    [bool]$Exists = $false

    #Get all VMS and check if the VMs is already present in VC
    $listvm = Get-vm
    foreach ($lvm in $listvm)
    {
        if($VMExists -eq $lvm.Name )
        {
            $Exists = $true
        }
    }
    return $Exists
}

function Disable_VM_Console()
```

```

{
    Param($VMToDisableConsole)
    $vmConfigSpec = New-Object VMware.Vim.VirtualMachineConfigSpec
    $extra = New-Object VMware.Vim.optionvalue
    $extra.Key="RemoteDisplay.maxConnections"
    $extra.Value="0"
    $vmConfigSpec.extraconfig += $extra
    $vm = Get-VM $VMToDisableConsole | Get-View
    $vm.ReconfigVM($vmConfigSpec)
}

function Delete_VM()
{
    Param($VMToDelete)
    Write-Host "Deleting VM $VMToDelete"
    Get-VM $VMToDelete | where { $_.PowerState -eq "PoweredOn" } | Stop-VM -confirm:$false
    Get-VM $VMToDelete | Remove-VM -DeleteFromDisk -confirm:$false
}

#----- Main Script -----

$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
$cloneType = GetInput -prompt 'Clone Type ("linked" or "full")' -IsPassword $false
$disableVMConsole = GetInput -prompt 'Disable vSphere VM Console ("yes" or "no", recommend "yes")' -
IsPassword $false
"-----"
$csvFile = '.\CloneVMs.csv'

# Check that user passed only linked or full clone
if (($CloneType.length > 0) -and ($CloneType -ne "linked" -or $CloneType -ne "full"))
{
    write-host -ForegroundColor Red "Clone type supports only 'linked' or 'full' (case sensitive)"
    exit
}
if (($disableVMConsole.length > 0) -and ($disableVMConsole -ne "yes" -or $disableVMConsole -ne "no"))
{
    write-host -ForegroundColor Red "Disable vSphere VM Console supports only 'yes' or 'no' (case
sensitive)"
    exit
}

#check if file exists
if (!(Test-Path $csvFile))
{
    write-host -ForegroundColor Red "CSV File $CSVFile not found"
    exit
}

# Connect to the VC (Parameterize VC)
#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))

```



```

{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

#Read input CSV file
$csvData = Import-CSV $csvFile
#$csvData = Import-CSV $csvFile -
header("VMName","Parentvm","CustomSpec","Datastore","Host","FromSnapshot","DeleteIfPresent")
foreach ($line in $csvData)
{
    "`n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    $destVMName=$line.VMName
    $srcVM = $line.Parentvm
    $cSpec = $line.CustomSpec
    $targetDSName = $line.Datastore
    $destHost = $line.Host
    $srcSnapshot = $line.FromSnapshot
    $deleteExisting = $line.DeleteIfPresent
    if (IsVMExists ($destVMName))
    {
        Write-Host "VM $destVMName Already Exists in VC $vcAddress"
        if($deleteExisting -eq "TRUE")
        {
            Delete_VM ($destVMName)
        }
        else
        {
            Write-Host "Skip clone for $destVMName"
            continue
        }
    }
    $vm = get-vm $srcvm -ErrorAction Stop | get-view -ErrorAction Stop
    $cloneSpec = new-object VMware.VIM.VirtualMachineCloneSpec
    $cloneSpec.Location = new-object VMware.VIM.VirtualMachineRelocateSpec
    if ($CloneType -eq "linked")
    {
        $cloneSpec.Location.DiskMoveType =
[VMware.VIM.VirtualMachineRelocateDiskMoveOptions]::createNewChildDiskBacking
    }
    Write-Host "Using Datastore $targetDSName"
    $newDS = Get-Datastore $targetDSName | Get-View
    $CloneSpec.Location.Datastore = $newDS.summary.Datastore
    Set-VM -vm $srcVM -snapshot (Get-Snapshot -vm $srcVM -Name $srcSnapshot) -confirm:$false
    $cloneSpec.Snapshot = $vm.Snapshot.CurrentSnapshot
    $cloneSpec.Location.Host = (get-vmhost -Name $destHost).Extensiondata.MoRef
    $CloneSpec.Location.Pool = (Get-ResourcePool -Name Resources -Location (Get-VMHost -Name
$destHost)).Extensiondata.MoRef

```

```

# Start the Clone task using the above parameters
$task = $vm.CloneVM_Task($vm.parent, $destVMName, $cloneSpec)
# Get the task object
$task = Get-Task | where { $_.id -eq $task }
#Wait for the taks to Complete
Wait-Task -Task $task

$newvm = Get-vm $destVMName
$customSpec = Get-OSCustomizationSpec $cSpec
Set-vm -OSCustomizationSpec $cSpec -vm $newvm -confirm:$false
if ($disableVMConsole -eq "yes")
{
    Disable_VM_Console($destVMName)
}
# Start the VM
Start-VM $newvm
}
Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\CloneVMs.ps1
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
Clone Type<"linked" or "Full"> : linked
Disable vSphere VM Console ("yes" or "no", recommend "yes") : yes

```

The time that the cloning process takes depends on the number of desktop machines and can range from several minutes to several hours. To verify that the process is complete, from vSphere Client, make sure that the last desktop virtual machine is powered on, has its own unique host name, and VMware Tools is running.

Sample Script to Join Cloned Virtual Machines to AD Domain

You can customize and use the following sample script to join cloned virtual machines (VMs) to an Active Directory (AD) domain.

You need to run this script if you use the Winbind solution for AD integration because the step to join the domain will fail for the cloned VMs. This script runs a command to join the domain on each VM. You do not need to run this script if you use the OpenLDAP solution.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at https://www.vmware.com/support/pubs/view_pubs.html.

Script Input

This script reads one input file, which is described in [Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#). This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- Administrator login name for the ESXi host
- Administrator password for the ESXi host
- User login name for the Linux VM
- User password for the Linux VM
- Login name of an AD user that is authorized to join machines to the domain
- Password of the authorized AD user

Script Content

```
<#
.SYNOPSIS
run command "sudo /usr/bin/net ads join"

.DESCRIPTION
The tool is to run the command "sudo /usr/bin/net ads join" to join Linux to AD

.NOTES
#>
#----- Functions -----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
}
```

```

    return $input
}
#----- Handle input -----
"-----"
$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$hostAdmin = GetInput -prompt 'Your ESXi host admin user name, such as root' -IsPassword $false
$hostPassword = GetInput -prompt "Your ESXi admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"
$adUser = GetInput -prompt 'Type the AD user name to join the AD' -IsPassword $false
""
`nPlease type the AD user password."
"Plase note that special character in password may not work with the script"
$adUserPassword = GetInput -prompt 'Your AD user password' -IsPassword $true
"-----"

#$csvFile = Read-Host 'Csv File '
$csvFile = '.\CloneVMs.csv'

#----- Main Script -----

#Connect to vCenter
#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

#Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

#Handle VMs one by one
foreach ($line in $csvData)
{
    "`n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    $cmd = "sudo /usr/bin/net ads join -U $adUser%$adUserPassword"
    Write-Host "Run cmd 'sudo /usr/bin/net ads join' in VM '$VMName' with user '$guestUser'"
    Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

```

```
}

Disconnect-VIServer $vcAddress -Confirm:$false
exit
```

Script Execution

The following messages are from an execution of the script:

```
PowerCLI C:\scripts> .\ClonedVMs_JoinDomain.ps1

-----
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your ESXi host admin user name, such as root: root
Your ESXi host admin user password: *****
-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****
-----
Type the AD user name to join the AD: viewadmin
Please type the AD user password.
Please note that special character in password may not work with the script.
Your AD user password: *****
```

Sample Script to Join Cloned Virtual Machines to AD Domain Using SSH

You can customize and use the following sample script to join cloned virtual machines (VMs) to an Active Directory (AD) domain. This script uses SSH to run commands on the Linux VMs.

You need to run this script if you use the Winbind solution for AD integration because the step to join the domain will fail for the cloned VMs. This script runs a command to join the domain on each VM. You do not need to run this script if you use the OpenLDAP solution.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at https://www.vmware.com/support/pubs/view_pubs.html.

Script Input

This script reads one input file, which is described in [Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#). This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- User login name for the Linux VM

- User password for the Linux VM
- Login name of an AD user that is authorized to join machines to the domain
- Password of the authorized AD user

Script Content

```
<#
.SYNOPSIS
run command "sudo /usr/bin/net ads join" via SSH

.DESCRIPTION
The tool is to run the command "sudo /usr/bin/net ads join" to join Linux machine to AD via SSH

.NOTES
#>
#----- Functions -----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}

function Check_SSH_Client
{
    Param($IsPlink, $IsPSCP)
    if ($IsPlink)
    {
        if (Test-Path ".\plink.exe")
        {
            write-host -ForegroundColor Yellow 'SSH client "plink.exe" found'
        }
        else
        {
            write-host -ForegroundColor Red 'SSH client "plink.exe" not found, please download from its
official web site'
            exit
        }
    }
}
```

```

    }
}
if ($IsPSCP)
{
    if (Test-Path ".\pscp.exe")
    {
        write-host -ForegroundColor Yellow 'SSH client "pscp.exe" found'
    }
    else
    {
        write-host -ForegroundColor Red 'SSH client "pscp.exe" not found, please download from its
official web site'
        exit
    }
}
}

function RunCmdViaSSH
{
    Param($VM_Name, $User, $Password, $Cmd, $returnOutput = $false)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    write-host "Run cmd on $VM_Name ($IP)"
    if($returnOutput)
    {
        $command = "echo yes | .\plink.exe -ssh -l $user -pw $password $IP " + '"' + $cmd + '"'
        $output = Invoke-Expression $command
        return $output
    }
    else
    {
        echo yes | .\plink.exe -ssh -l $user -pw $password $IP "$cmd"
    }
}

function UploadFileViaSSH
{
    Param($VM_Name, $User, $Password, $LocalPath, $DestPath)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    $command = "echo yes | .\pscp.exe -l $User -pw $Password $LocalPath $IP" + ":" + "$DestPath"
    write-host "Upload file: $command"
    Invoke-Expression $command
}

#----- Handle input -----
"-----"
Check_SSH_Client -IsPlink $true -IsPSCP $false
"-----"
$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true

```

```

"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"
$adUser = GetInput -prompt 'Type the AD user name to join the AD' -IsPassword $false
""
`nPlease type the AD user password."
[Console]::ForegroundColor = "Yellow"
"Plase note that special character should be escaped. For example, $ should be \"
[Console]::ResetColor()
$adUserPassword = GetInput -prompt 'Your AD user password' -IsPassword $true
"-----"

#$csvFile = Read-Host 'Csv File '
$csvFile = '.\CloneVMs.csv'

#----- Main Script -----

#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

#Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

#Handle VMs one by one
foreach ($line in $csvData)
{
    "-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    $cmd = "sudo /usr/bin/net ads join -U $adUser%$adUserPassword"
    Write-Host "Run cmd 'sudo /usr/bin/net ads join' in VM '$VMName' with user '$guestUser'"
    RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd
}

Disconnect-VIServer $vcAddress -Confirm:$false
exit

```


Script Execution

The following messages are from an execution of the script:

```
PowerCLI C:\scripts> .\ClonedVMs_JoinDomain_SSH.ps1

-----
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****
-----
Type the AD user name to join the AD: viewadmin
Please type the AD user password.
Please note that special character should be escaped. For example, $ should be \$
Your AD user password: *****
```

Sample Script to Upload Configuration Files to Linux Virtual Machines

You can customize and use the following sample script to upload the configuration files `config` and `viewagent-custom.conf` to multiple Linux virtual machines (VMs).

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at https://www.vmware.com/support/pubs/view_pubs.html.

Script Input

This script reads one input file, which is described in [Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#). This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- Administrator login name for the ESXi host
- Administrator password for the ESXi host
- User login name for the Linux VM
- User password for the Linux VM

Script Content

```
<#
Upload the configuration files config and viewagent-custom.conf to Linux VMs
#>
#----- Functions -----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}

#----- Handle Input -----
"-----"
write-host -ForegroundColor Blue 'Please ensure your config file and viewagent-custom.conf file are
in current working directory'
$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$hostAdmin = GetInput -prompt 'Your ESXi host admin user name, such as root' -IsPassword $false
$hostPassword = GetInput -prompt "Your ESXi admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"

$csvFile = '.\CloneVMs.csv'
$setConfig = $false
$setCustomConf = $false
$config_File = "config"
$customConf_File = "viewagent-custom.conf"

#check if config file exists
if(Test-Path $config_File)
{
    $setConfig = $true
}
```

```

        write-host -ForegroundColor Yellow '"config" file found'
    }
    else
    {
        write-host -ForegroundColor Yellow '"config" file not found, skip it'
    }

    if(Test-Path $customConf_File)
    {
        $setCustomConf = $true
        write-host -ForegroundColor Yellow '"viewagent-custom.conf" file found'
    }
    else
    {
        write-host -ForegroundColor Yellow '"viewagent-custom.conf" file not found, skip it'
    }

    if (($setConfig -eq $false)-AND ($setCustomConf -eq $false))
    {
        write-host -ForegroundColor Red 'Both file not found, exit'
        exit
    }

    #Connect to vCenter
    $VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
    if([string]::IsNullOrEmpty($VC_Conn_State))
    {
        Write-Host 'Exit since failed to login vCenter'
        exit
    }
    else
    {
        Write-Host 'vCenter is connected'
    }

    #Read input CSV file
    $csvData = Import-CSV $csvFile

    $destFolder = "/home/$guestUser/"

    #Handle VMs one by one
    foreach ($line in $csvData)
    {
        "`n-----"
        $VMName = $line.VMName
        write-host -ForegroundColor Yellow "VM: $VMName`n"

        #Try to delete the configuration file from home folder on destination VM
        $cmd = "rm -rf config viewagent-custom.conf"
        Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
        $guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

        if ($setConfig)

```

```

{
    Write-Host "Upload File '$config_File' to '$destFolder' of VM '$VMName' with user '$guestUser'"
    Copy-VMGuestFile -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -LocalToGuest -Destination $destFolder -
Source $config_File

    $cmd = "sudo mv ./ $config_File /etc/vmware/";
    Write-Host "Move configuraton file: $cmd"
    Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd
}

if ($setCustomConf)
{
    Write-Host "Upload File '$customConf_File' to '$destFolder' of VM '$VMName' with user '$guestUser'"
    Copy-VMGuestFile -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -LocalToGuest -Destination $destFolder -
Source $customConf_File

    $cmd = "sudo mv ./ $customConf_File /etc/vmware/";
    Write-Host "Move configuraton file: $cmd"
    Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd
}
}
Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\UpdateOptionFile.ps1
-----
Please ensure your config file and view-agent.conf file are in current working directory.
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your ESXi host admin user name, such as root: root
Your ESXi host admin user password: *****
-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****

```

Sample Script to Upload Configuration Files to Linux Virtual Machines Using SSH

You can customize and use the following sample script to upload the configuration files `config` and `viewagent-custom.conf` to multiple Linux virtual machines (VMs). This script uses SSH to run commands on the Linux VMs.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at https://www.vmware.com/support/pubs/view_pubs.html.

Script Input

This script reads one input file, which is described in [Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#). This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- User login name for the Linux VM
- User password for the Linux VM

Script Content

```
<#
Upload the configuration files config and viewagent-custom.conf to Linux VMs using SSH
#>
#----- Functions -----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}
function Check_SSH_Client
{
    Param($IsPlink, $IsPSCP)
    if ($IsPlink)
    {
        if (Test-Path ".\plink.exe")
        {
            write-host -ForegroundColor Yellow 'SSH client "plink.exe" found'
        }
    }
}
```

```

        else
        {
            write-host -ForegroundColor Red 'SSH client "plink.exe" not found, please download from its
official web site'
            exit
        }
    }
    if ($IsPSCP)
    {
        if (Test-Path ".\pscp.exe")
        {
            write-host -ForegroundColor Yellow 'SSH client "pscp.exe" found'
        }
        else
        {
            write-host -ForegroundColor Red 'SSH client "pscp.exe" not found, please download from its
official web site'
            exit
        }
    }
}

function RunCmdViaSSH
{
    Param($VM_Name, $User, $Password, $Cmd, $returnOutput = $false)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    write-host "Run cmd on $VM_Name ($IP)"
    if($returnOutput)
    {
        $command = "echo yes | .\plink.exe -ssh -l $user -pw $password $IP " + '"' + $cmd + '"'
        $output = Invoke-Expression $command
        return $output
    }
    else
    {
        echo yes | .\plink.exe -ssh -l $user -pw $password $IP "$cmd"
    }
}

function UploadFileViaSSH
{
    Param($VM_Name, $User, $Password, $LocalPath, $DestPath)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    $command = "echo yes | .\pscp.exe -l $User -pw $Password $LocalPath $IP" + ":" + "$DestPath"
    write-host "Upload file: $command"
    Invoke-Expression $command
}

#----- Handle Input -----
"-----"

```

```

Check_SSH_Client -IsPlink $true -IsPSCP $true
"-----"
write-host -ForegroundColor Blue 'Please ensure your config file and viewagent-custom.conf file are
in current working directory'
$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"

$csvFile = '.\CloneVMs.csv'
$setConfig = $false
$setCustomConf = $false
$config_File = "config"
$customConf_File = "viewagent-custom.conf"

#check if config file exists
if(Test-Path $config_File)
{
    $setConfig = $true
    write-host -ForegroundColor Yellow '"config" file found'
}
else
{
    write-host -ForegroundColor Yellow '"config" file not found, skip it'
}

if(Test-Path $customConf_File)
{
    $setCustomConf = $true
    write-host -ForegroundColor Yellow '"viewagent-custom.conf" file found'
}
else
{
    write-host -ForegroundColor Yellow '"viewagent-custom.conf" file not found, skip it'
}

if (($setConfig -eq $false)-AND ($setCustomConf -eq $false))
{
    write-host -ForegroundColor Red 'Both file not found, exit'
    exit
}

#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

```

```

}

#Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

#Handle VMs one by one
foreach ($line in $csvData)
{
    "`n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    #Try to delete the configuration file from home folder on destination VM
    $cmd = "rm -rf config viewagent-custom.conf"
    Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd

    if ($setConfig)
    {
        Write-Host "Upload File '$config_File' to '$destFolder' of VM '$VMName' with user '$guestUser'"
        UploadFileViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -LocalPath
        $config_File -DestPath $destFolder

        $cmd = "sudo mv ./ $config_File /etc/vmware/";
        Write-Host "Move configuraton file: $cmd"
        RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd
    }

    if ($setCustomConf)
    {
        Write-Host "Upload File '$customConf_File' to '$destFolder' of VM '$VMName' with user '$guestUser'"
        UploadFileViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -LocalPath
        $customConf_File -DestPath $destFolder

        $cmd = "sudo mv ./ $customConf_File /etc/vmware/";
        Write-Host "Move configuraton file: $cmd"
        RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd
    }
}
Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\UpdateOptionFile.ps1
-----
Please ensure your config file and view-agent.conf file are in current working directory.
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator

```



```
Your vCenter admin user password: *****
```

```
-----
Your VM guest OS user name: ViewUser
```

```
Your VM guest OS user password: *****
```

Sample Script to Upgrade Horizon Agent on Linux Desktop Machines

You can customize and use the following sample script to upgrade Horizon Agent on multiple Linux virtual machines (VMs).

This script uploads the installer tar ball to each VM before installing Horizon Agent. The upload task can be time-consuming, especially when a large number of VMs is involved and the network speed is slow. To save time, you can run the script that uses SSH, or put the installer tar ball in a shared location that is available to each VM so that uploading the file is not necessary.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at https://www.vmware.com/support/pubs/view_pubs.html.

Script Input

This script reads one input file, which is described in [Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#). This script also interactively asks for the following information:

- Acceptance of Horizon Agent EULA (end user license agreement)
- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- Administrator login name for the ESXi host
- Administrator password for the ESXi host
- User login name for the Linux guest operating system
- User password for the Linux guest operating system
- Horizon Agent tar ball path
- Upgrade to managed VM
- Install the Smartcard redirection feature

Script Content

```
<#
Upload the Linux Agent installer tar ball and re-install
#>

#-----
```

```

Functions-----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}
#-----Handle
input-----
"-----"
$acceptEULA = GetInput -prompt 'Accept Linux View Agent EULA in tar bundle ("yes" or "no")' -
IsPassword $false
if ($acceptEULA -ne "yes")
{
    write-host -ForegroundColor Red "You need accept the EULA with 'yes'(case sensitive)"
    exit
}
$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$hostAdmin = GetInput -prompt 'Your ESXi host admin user name, such as root' -IsPassword $false
$hostPassword = GetInput -prompt "Your ESXi admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"
$agentInstaller = GetInput -prompt 'Type the View Agent tar ball path' -IsPassword $false
"-----"
$UpgradeToManagedVM = GetInput -prompt 'Upgrade to managed VM ("yes" or "no")' -IsPassword $false
if (($UpgradeToManagedVM -ne "yes") -AND $UpgradeToManagedVM -ne "no")
{
    write-host -ForegroundColor Red "You need select 'yes' or 'no'(case sensitive)"
    exit
}
$installSmartcard = GetInput -prompt 'Install the Smartcard redirection feature ("yes" or "no")' -
IsPassword $false
if (($installSmartcard -ne "yes") -AND $installSmartcard -ne "no")
{
    write-host -ForegroundColor Red "You need select 'yes' or 'no'(case sensitive)"
}

```

```

    exit
}
"-----"

# $csvFile = Read-Host 'Csv File '
$csvFile = '.\CloneVMs.csv'

# check if file exists
if (!(Test-Path $agentInstaller))
{
    write-host -ForegroundColor Red "installer File not found"
    exit
}

# check if file exists
if (!(Test-Path $csvFile))
{
    write-host -ForegroundColor Red "CSV File not found"
    exit
}
#-----
Functions-----
function GetSourceInstallerMD5()
{
    $agentInstallerPath = Convert-Path $agentInstaller;
    $md5 = New-Object -TypeName System.Security.Cryptography.MD5CryptoServiceProvider;
    $md5HashWithFormat =
[System.BitConverter]::ToString($md5.ComputeHash([System.IO.File]::ReadAllBytes($agentInstallerPath)));
    $md5Hash = ($md5HashWithFormat.replace("-", "")).ToLower();
    return $md5Hash;
}

#-----
Main-----
# Get installer MD5Sum
$installerMD5Hash = GetSourceInstallerMD5;

# Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

# Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

# Handle VMs one by one

```

```

foreach ($line in $csvData)
{
    "`n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    $cmd = "rm -rf VMware-*--linux-*"
    Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

    #Upload installer tar ball to Linux VM
    Write-Host "Upload File '$agentInstaller' to '$destFolder' of VM '$VMName' with user '$guestUser'"
    Copy-VMGuestFile -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -LocalToGuest -Destination $destFolder -
Source $agentInstaller

    #Check the uploaded installer md5sum
    $cmd = "md5sum VMware-*--linux-*"
    Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    $output = Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

    if($output.Contains($installerMD5Hash))
    {
        Write-Host $VMName": Uploaded installer's MD5Sum matches the local installer's MD5Sum";
        Write-Host $VMName": Extract the installer and do installation";
        $cmd = "tar -xzvf VMware-*--linux-*.tar.gz"
        Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

        $cmd = "sudo setenforce 0";
        Write-Host "Set the selinux to permissive mode: $cmd"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

        $cmd = "sudo killall /usr/lib/vmware/viewagent/VMwareBlastServer/VMwareBlastServer"
        Write-Host "Stop VMwareBlastServer before upgrading: $cmd"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

        #Run the upgrade command.
        $cmd = "cd VMware-*--linux-* && sudo ./install_viewagent.sh -A yes -m $installSmartcard -M
$UpgradeToManagedVM"
        Write-Host "Run upgrade cmd in VM '$VMName' with user '$guestUser': $cmd"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

        $cmd = "sudo shutdown -r +1&"
        Write-Host "Reboot to apply the View Agent installation"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd
    }
    else

```

```

    {
        Write-Host $VMName": Uploaded installer's MD5Sum does NOT match the local installer's MD5Sum";
        Write-Host $VMName": Skip the installation. Please check your network and VMware Tools status";
        exit;
    }
}
Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\InstallAgent.ps1
-----
Accept Linux Horizon Agent EULA in tar bundle ("yes" or "no"): yes
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your ESXi host admin user name, such as root: root
Your ESXi host admin user password: *****
-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****
-----
Type the Horizon Agent tar ball path. Please take care of the installer arch: .\VMware-viewagent-linux-
x86_64-x.y.z-1234567.tar.gz
-----
Upgrade to managed VM ("yes" or "no"): yes
Install the Smartcard redirection feature ("yes" or "no"): no

```

Sample Script to Upgrade Horizon Agent on Linux Virtual Machines Using SSH

You can customize and use the following sample script to upgrade Horizon Agent on multiple Linux virtual machines (VMs). This script uses SSH to run commands on the Linux VMs.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at https://www.vmware.com/support/pubs/view_pubs.html.

Script Input

This script reads one input file, which is described in [Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#). This script also interactively asks for the following information:

- Acceptance of Horizon Agent EULA (end user license agreement)
- IP address of the vCenter Server
- Administrator login name for the vCenter Server

- Administrator password for the vCenter Server
- Administrator login name for the ESXi host
- Administrator password for the ESXi host
- User login name for the Linux guest operating system
- User password for the Linux guest operating system
- Horizon Agent tar ball path
- Upgrade to managed VM
- Install the Smartcard redirection feature

Script Content

```
<#
Upload the Linux Agent installer tar ball and re-install
#>

#-----
Functions-----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}
function Check_SSH_Client
{
    Param($IsPlink, $IsPSCP)
    if ($IsPlink)
    {
        if (Test-Path ".\plink.exe")
        {
            write-host -ForegroundColor Yellow 'SSH client "plink.exe" found'
        }
        else
        {

```

```

        write-host -ForegroundColor Red 'SSH client "plink.exe" not found, please download from its
official web site'
        exit
    }
}
if ($IsPSCP)
{
    if (Test-Path ".\pscp.exe")
    {
        write-host -ForegroundColor Yellow 'SSH client "pscp.exe" found'
    }
    else
    {
        write-host -ForegroundColor Red 'SSH client "pscp.exe" not found, please download from its
official web site'
        exit
    }
}

function RunCmdViaSSH
{
    Param($VM_Name, $User, $Password, $Cmd, $returnOutput = $false)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    write-host "Run cmd on $VM_Name ($IP)"
    if($returnOutput)
    {
        $command = "echo yes | .\plink.exe -ssh -l $user -pw $password $IP " + '"' + $cmd + '"'
        $output = Invoke-Expression $command
        return $output
    }
    else
    {
        echo yes | .\plink.exe -ssh -l $user -pw $password $IP "$cmd"
    }
}

function UploadFileViaSSH
{
    Param($VM_Name, $User, $Password, $LocalPath, $DestPath)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    $command = "echo yes | .\pscp.exe -l $User -pw $Password $LocalPath $IP" + ":" + "$DestPath"
    write-host "Upload file $LocalPath to VM $VM_Name with user $User"
    Invoke-Expression $command
}

#-----Handle
input-----
"-----"
Check_SSH_Client -IsPlink $true -IsPSCP $true

```

```

"-----"
$acceptEULA = GetInput -prompt 'Accept Linux View Agent EULA in tar bundle ("yes" or "no")' -
IsPassword $false
if ($acceptEULA -ne "yes")
{
    write-host -ForegroundColor Red "You need accept the EULA with 'yes'(case sensitive)"
    exit
}
$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"
$agentInstaller = GetInput -prompt 'Type the View Agent tar ball path' -IsPassword $false
"-----"
$UpgradeToManagedVM = GetInput -prompt 'Upgrade to managed VM ("yes" or "no")' -IsPassword $false
if (($UpgradeToManagedVM -ne "yes") -AND $UpgradeToManagedVM -ne "no")
{
    write-host -ForegroundColor Red "You need select 'yes' or 'no'(case sensitive)"
    exit
}
$installSmartcard = GetInput -prompt 'Install the Smartcard redirection feature ("yes" or "no")' -
IsPassword $false
if (($installSmartcard -ne "yes") -AND $installSmartcard -ne "no")
{
    write-host -ForegroundColor Red "You need select 'yes' or 'no'(case sensitive)"
    exit
}
}
"-----"

#$csvFile = Read-Host 'Csv File '
$csvFile = '.\CloneVMs.csv'

#check if file exists
if (!(Test-Path $agentInstaller))
{
    write-host -ForegroundColor Red "installer File not found"
    exit
}

#check if file exists
if (!(Test-Path $csvFile))
{
    write-host -ForegroundColor Red "CSV File not found"
    exit
}
}
#-----
Functions-----
function GetSourceInstallerMD5()
{
    $agentInstallerPath = Convert-Path $agentInstaller;
    $md5 = New-Object -TypeName System.Security.Cryptography.MD5CryptoServiceProvider;
    $md5HashWithFormat =

```



```

[System.BitConverter]::ToString($md5.ComputeHash([System.IO.File]::ReadAllBytes($agentInstallerPath)));
    $md5Hash = ($md5HashWithFormat.replace("-", "").ToLower());
    return $md5Hash;
}

#-----
Main-----
#Get installer MD5Sum
$installerMD5Hash = GetSourceInstallerMD5;

#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

#Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

#Handle VMs one by one
foreach ($line in $csvData)
{
    "`n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    $cmd = "rm -rf VMware-*linux-*"
    Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd

    #Upload installer tar ball to Linux VM
    Write-Host "Upload File '$agentInstaller' to '$destFolder' of VM '$VMName' with user '$guestUser'"
    UploadFileViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -LocalPath
$agentInstaller -DestPath $destFolder

    #Check the uploaded installer md5sum
    $cmd = "md5sum VMware-*linux-*"
    Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    $output = RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd -
$returnOutput $true

    if($output.Contains($installerMD5Hash))
    {
        Write-Host $VMName": Uploaded installer's MD5Sum matches the local installer's MD5Sum";
        Write-Host $VMName": Extract the installer and do installation";
    }
}

```

```

$cmd = "tar -xzf VMware-*linux-*.tar.gz"
Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd

$cmd = "sudo setenforce 0";
Write-Host "Set the selinux to permissive mode: $cmd"
RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd

$cmd = "sudo killall /usr/lib/vmware/viewagent/VMwareBlastServer/VMwareBlastServer"
Write-Host "Stop VMwareBlastServer before upgrading: $cmd"
RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd

#Run the upgrade command.
$cmd = "cd VMware-*linux-* && sudo ./install_viewagent.sh -r yes -A yes -m $installSmartcard -
M $UpgradeToManagedVM"
Write-Host "Run upgrade cmd in VM '$VMName' with user '$guestUser': $cmd"
RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd
Write-Host -ForegroundColor Yellow "Linux Agent installer will reboot the Linux VM after
upgrade, and you may hit the ssh connection closed error message, which is expectation"
}
else
{
    Write-Host $VMName": Uploaded installer's MD5Sum does NOT match the local installer's MD5Sum";
    Write-Host $VMName": Skip the installation. Please check your network and VMware Tools status";
    exit;
}
}
Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\InstallAgent.ps1
-----
Accept Linux Horizon Agent EULA in tar bundle ("yes" or "no"): yes
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****
-----
Type the Horizon Agent tar ball path. Please take care of the installer arch: .\VMware-viewagent-linux-
x86_64-x.y.z-1234567.tar.gz
-----
---
Upgrade to managed VM ("yes" or "no"): yes
Install the Smartcard redirection feature ("yes" or "no"): no

```

Sample Script to Perform Operations on Linux Virtual Machines

You can customize and use the following sample script to perform operations on multiple Linux virtual machines (VMs). The operations include powering on, powering off, shutting down, restarting, and deleting the VMs.

This script can delete virtual machines from vCenter Server but not from View.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at https://www.vmware.com/support/pubs/view_pubs.html.

Script Input

This script reads one input file, which is described in [Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#). This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- Action to perform, which can be power-on, power-off, shut down guest, restart VM, restart VM guest, or delete VM.
- The wait time, in seconds, between operations on the VMs.

Script Content

```
<#
.DESCRIPTION
The Tool supports:
1. Power off VMs
2. Power on VMs
3. Shutdown VMs
4. Restart VMs
5. Restart VM guest
6. Delete VMs from Disk
.NOTES
#>

#----- Functions -----

function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
```

```

        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}

function IsVMExists ($VMExists)
{
    Write-Host "Checking if the VM $VMExists Exists"
    [bool]$Exists = $false

    #Get all VMS and check if the VMs is already present in VC
    $listvm = Get-vm
    foreach ($lvm in $listvm)
    {
        if($VMExists -eq $lvm.Name )
        {
            $Exists = $true
            Write-Host "$VMExists is Exist"
        }
    }
    return $Exists
}

function Delete_VM($VMToDelete)
{
    Write-Host "Deleting VM $VMToDelete"
    Get-VM $VMToDelete | where { $_.PowerState -eq "PoweredOn" } | Stop-VM -confirm:$false
    Get-VM $VMToDelete | Remove-VM -DeleteFromDisk -confirm:$false
}

#----- Handle input -----
"-----"
$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$action = GetInput -prompt 'Select action: 1). Power On 2). Power Off 3) Shutdown VM Guest 4). Restart VM 5). Restart VM Guest 6). Delete VM' -IsPassword $false
$sleepTime = GetInput -prompt 'Wait time (seconds) between each VM' -IsPassword $false
"-----"
[Console]::ForegroundColor = "Yellow"
switch ($action)
{
    1
    {
        "Your selection is 1). Power On"
    }
}

```

```

    }
    2
    {
        "Your selection is 2). Power Off"
    }
    3
    {
        "Your selection is 3) Shutdown"
    }
    4
    {
        "Your selection is 4). Restart VM"
    }
    5
    {
        "Your selection is 5). Restart VM Guest"
    }
    6
    {
        "Your selection is 6). Delete VM"
    }
    default
    {
        "Invalid selection for action: $action"
        exit
    }
}
[Console]::ResetColor()
$csvFile = '.\CloneVMs.csv'

#check if file exists
if (!(Test-Path $csvFile))
{
    write-host -ForegroundColor Red "CSV File not found"
    exit
}
"-----"

#----- Main -----
#Read input CSV file
Disconnect-VIServer $vcAddress -Confirm:$false
#Connect-VIServer $vcAddress -ErrorAction Stop -user $vcAdmin -password $vcPassword
Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
$csvData = Import-CSV $csvFile

foreach ($line in $csvData)
{
    $VMName = $line.VMName
    switch ($action)
    {
        1
        {
            Get-VM $VMName | Start-VM -Confirm:$false
        }
        2
    }
}

```

```

    {
        Get-VM $VMName | Stop-VM -Confirm:$false
    }
    3
    {
        Get-VM $VMName | Shutdown-VMGuest -Confirm:$false
    }
    4
    {
        Get-VM $VMName | Restart-VM -Confirm:$false
    }
    5
    {
        Get-VM $VMName | Restart-VMGuest -Confirm:$false
    }
    6
    {
        if (IsVMExists ($VMName))
        {
            Delete_VM ($VMName)
        }
    }
    default{}
}
Start-Sleep -s $sleepTime
}

Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\VMOperations.ps1
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****

-----
Select action: 1). Power On 2). Power Off 3) Shutdown VM Guest 4). Restart VM 5). Restart VM Guest 6).
Delete VM: 1
Wait time (seconds) between each VM: 20
-----

Your selection is 6). Delete VM

```

For the operations power on, restart VM, and restart VM guest, specify a wait time between virtual machines of at least 20 seconds to avoid a boot storm situation, which might cause some operations to fail.

Troubleshooting Linux Desktops

10

Certain issues might arise when you manage Linux desktops. You can follow various procedures to diagnose and fix problems.

This chapter includes the following topics:

- [Using Horizon Help Desk Tool in Horizon Console](#)
- [Collect Diagnostic Information for Horizon 7 for Linux Machine](#)
- [Troubleshooting Copy and Paste between Remote Desktop and Client Host](#)
- [View Agent Fails to Disconnect on an iPad Pro Horizon Client](#)
- [SLES 12 SP1 Desktop Does Not Auto-Refresh](#)
- [SSO Fails to Connect to a PowerOff Agent](#)
- [Unreachable VM After Creating a Manual Desktop Pool for Linux](#)

Using Horizon Help Desk Tool in Horizon Console

Horizon Help Desk Tool is a Web application that you can use to get the status of Horizon 7 user sessions and to perform troubleshooting and maintenance operations.

In Horizon Help Desk Tool, you can look up user sessions to troubleshoot problems and perform desktop maintenance operations such as restart or reset desktops.

To configure Horizon Help Desk Tool, you must meet the following requirements:

- Horizon Enterprise edition license or Horizon Apps Advanced edition license for Horizon 7. To verify that you have the correct license, see the *Horizon 7 Administration* document.
- An event database to store information about Horizon 7 components. For more information about configuring an event database, see the *Horizon 7 Installation* document.
- The Help Desk Administrator role or the Help Desk Administrator (Read Only) role to log in to Horizon Help Desk Tool. For more information on these roles, see the *Horizon 7 Administration* document.
- Enable the timing profiler on each Connection Server instance to view logon segments.

Use the following `vdadmin` command to enable the timing profiler on each Connection Server instance:

```
vdadmin -I -timingProfiler -enable
```

Use the following `vdadmin` command to enable the timing profiler on a Connection Server instance that uses a management port:

```
vdadmin -I -timingProfiler -enable -server {ip/server}
```

- Enable the `HelpDeskEnable` option in the `/etc/vmware/viewagent-custom.conf` configuration file.

Start Horizon Help Desk Tool in Horizon Console

Horizon Help Desk Tool is integrated into Horizon Console. You can search for a user that you want to troubleshoot problems for in Horizon Help Desk Tool.

Procedure

- 1 In Horizon Console, enter a user name in the User Search field.
Horizon Console displays a list of users in the search results. The search can return up to 100 matching results.
- 2 Select a user name.
The user information appears in a user card.

What to do next

To troubleshoot problems, click the related tabs in the user card.

Troubleshooting Users in Horizon Help Desk Tool

In Horizon Help Desk Tool, you can view basic user information in a user card. You can click tabs in the user card to get more details about specific components.

The user details can sometimes appear in tables. You can sort these user details by table columns.

- To sort a column by ascending order, click the column once.
- To sort a column by descending order, click the column twice.
- To not sort the column, click the column thrice.

Basic User Information

Displays basic user information such as user name, phone number, and email address of the user and the connected or disconnected status of the user. If the user has a desktop session, the status of the user is connected. If the user does not have any desktop sessions, the status of the user is disconnected.

You can click the email address to send a message to the user.

Sessions

The **Sessions** tab displays information about desktop sessions that the user is connected to.

You can use the **Filter** text box to filter desktop sessions.

Note The **Sessions** tab does not display session information for sessions that access VMs from vSphere Client or ESXi.

The **Sessions** tab includes the following information:

Table 10-1. Sessions tab

Option	Description
State	Displays information about the state of the desktop session. <ul style="list-style-type: none"> ■ Appears green, if the session is connected. ■ L, if the session is a local session or a session running in the local pod.
Computer Name	Name of the desktop session. Click the name to open the session information in a card. You can click the tabs in the session card to view additional information: <ul style="list-style-type: none"> ■ The Details tab displays the user information such as the VM information, CPU, or memory usage. ■ The Processes tab displays information about CPU and memory related processes.
Protocol	Display protocol for the desktop session.
Type	Displays whether the desktop is a published desktop or a virtual machine desktop.
Connection Time	The time the session connected to Connection Server.
Session Duration	The duration of time the session remained connected to Connection Server.

Desktops

The **Desktops** tab displays information about the published desktops or virtual desktops that the user is entitled to use.

Table 10-2. Desktops

Option	Description
State	Displays information about the state of the desktop session. <ul style="list-style-type: none"> ■ Appears green, if the session is connected.
Desktop Pool Name	Name of the desktop pool for the session.

Table 10-2. Desktops (Continued)

Option	Description
Desktop Type	Displays whether the desktop is a published desktop or virtual machine desktop. Note Does not display any information if the session is running in a different pod in the pod federation.
Type	Displays information about the type of desktop entitlement. ■ Local, for a local entitlement.
vCenter	Displays the name of the virtual machine in vCenter Server. Note Does not display any information if the session is running in a different pod in the pod federation.
Default Protocol	Default display protocol for the desktop session.

Activities

The **Activities** tab displays the event log information about the user's activities. You can filter activities by a time range such as the Last 12 hours or Last 30 Days or by administrator name. Click **Help Desk Event Only** to filter only by Horizon Help Desk Tool activities. Click the refresh icon to refresh the event log. Click the export icon to export the event log as a file.

Note The event log information is not displayed for users in a Cloud Pod Architecture environment.

Table 10-3. Activities

Option	Description
Time	Select a time range. Default is the last 12 hours. ■ Last 12 Hours ■ Last 24 Hours ■ Last 7 Days ■ Last 30 Days ■ All
Admins	Name of the administrator user.
Message	Displays messages for a user or administrator that are specific to the activities that the user or administrator performed.
Resource Name	Displays information about the desktop pool or virtual machine name on which the activity was performed.

Session Details for Horizon Help Desk Tool

The session details appear on the **Details** tab when you click a user name in the **Computer Name** option on the **Sessions** tab. You can view details for Horizon Client, the virtual or published desktop, and CPU and memory details.

Client

Displays information that depends on the type of Horizon Client and includes details such as user name, version of Horizon Client, IP address of the client machine, and the operating system of the client machine.

Note If you upgraded Horizon Agent, you must also upgrade Horizon Client to the latest version. Else, no version is displayed for Horizon Client. For more information about upgrading Horizon Client, see the *Horizon 7 Upgrades* document.

VM

Displays information about virtual desktops or published desktops.

Table 10-4. VM Details

Option	Description
Computer Name	Name of the desktop session.
Agent Version	Horizon Agent version.
OS Version	Operating System version.
Connection Server	The Connection Server that the session connects to.
Pool	Name of the desktop pool.
vCenter	IP address of vCenter Server.
Session State	State of the desktop session. The session states can be connected or disconnected.
Session Duration	The time the session remained connected to Connection Server.
State Duration	The time the session remained in the same state.
Logon Time	The logon time of the user who logged in to the session.
Logon Duration	The duration of time that the user is logged on the Linux desktop.

User Experience Metrics

Displays performance details for a virtual or published desktop session that uses the VMware Blast display protocol. To view these performance details, click **More**. To refresh these details, click the refresh icon.

Table 10-5. Blast Display Protocol Details

Option	Description
Frame Rate	The frame rate, in frames per second, in a Blast session.
Skype Status	For Linux desktop sessions, this option appears as N/A .

Table 10-5. Blast Display Protocol Details (Continued)

Option	Description
Blast Session Counters	<ul style="list-style-type: none"> ■ Estimated Bandwidth (Uplink). Estimated bandwidth for an uplink signal. ■ Packet Loss (Uplink). Percentage of packet loss for an uplink signal.
Blast Imaging Counters	<ul style="list-style-type: none"> ■ Transmitted Bytes. Total number of bytes for imaging data that have been transmitted for a Blast session. ■ Received Bytes. Total number of bytes for imaging data that have been received for a Blast session.
Blast Audio Counters	<ul style="list-style-type: none"> ■ Transmitted Bytes. Total number of bytes for audio data that have been transmitted for a Blast session. ■ Received Bytes. Total number of bytes for audio data that have been received for a Blast session.
Blast CDR Counters	<ul style="list-style-type: none"> ■ Transmitted Bytes. Total number of bytes for Client Drive Redirection data that have been transmitted for a Blast session. ■ Received Bytes. Total number of bytes for Client Drive Redirection data that have been received for a Blast session.

CPU and Memory Usage and Network and Disk Performance

Displays charts for CPU and memory usage of the virtual or published desktop and the network or disk performance for the Blast display protocol.

Note Following a start or a restart of Horizon Agent on the desktop, the performance charts might not display the timeline immediately. The timeline appears after a few minutes.

Table 10-6. CPU Usage

Option	Description
Session CPU	CPU usage of the current session.
Host CPU	CPU usage of the virtual machine to which the session is assigned.

Table 10-7. Memory Usage

Option	Description
Session Memory	Memory usage of the current session.
Host Memory	Memory usage of the virtual machine to which the session is assigned.

Table 10-8. Network Performance

Option	Description
Latency	Displays a chart for the latency for the PCoIP or Blast session. The latency time is the Round-Trip Time in milliseconds. The performance counter that tracks this latency time is VMware Blast Session Counters > RTT .

Table 10-9. Disk Performance

Option	Description
Read	The number of read Input/Output (I/O) operations per second.
Write	The number of write I/O operations per second.
Disk Latency	Displays a chart for the disk latency. The disk latency is the time in milliseconds from the Input/Output Operations Per Second (IOPS) data retrieved from the Windows performance counters.
Average Read	Average number of random read I/O operations per second.
Average Write	Average number of random write I/O operations per second.
Average Latency	Average latency time in milliseconds from the IOPS data retrieved from the Windows performance counters.

Session Logon Segments

Displays the logon duration and usage segments that are created during logon.

Table 10-10. Session Logon Segments

Option	Description
Logon duration	The length of time calculated from the time the user clicks the desktop pool to the time when the user logged on to the Linux desktop.
Session Logon Time	The length of time that the user was logged in to the session.
Logon Segments	<p>Displays the segments that are created during logon.</p> <ul style="list-style-type: none"> ■ Brokering. Total time for Connection Server to process a session connect or reconnect. Calculated from the time the user clicks the desktop pool to the time when the tunnel connection is set up. Includes the times for Connection Server tasks such as user authentication, machine selection, and machine preparation for setting up the tunnel connection. ■ Interactive. Total time for Horizon Agent to process a session connect or reconnect. Calculated from the time when Blast Extreme uses the tunnel connection to the time when the user logged on to the Linux desktop. ■ Protocol Connection. Total time taken for the PCoIP or Blast protocol connection to complete during the logon process. ■ Logon Script. Total time taken for a logon script to execute from start to completion. ■ Authentication. Total time for Connection Server to authenticate the session. ■ VM Start. Total time taken to start a VM. This time includes the time for booting the operating system, resuming a suspended machine, and the time it takes Horizon Agent to signal that it is ready for a connection.

Session Processes for Horizon Help Desk Tool

The session processes appear on the **Processes** tab when you click a user name in the **Computer Name** option on the **Sessions** tab.

Processes

For each session, you can view additional details about CPU and memory related processes. For example, if you notice that the CPU and memory usage for a session is abnormally high, you can view the details for the process on the **Processes** tab.

Table 10-11. Session Process Details

Option	Description
Process Name	Name of the session process. For example, chrome.exe.
CPU	CPU usage of the process in percent.
Memory	Memory usage of the process in KB.

Table 10-11. Session Process Details (Continued)

Option	Description
Disk	Memory disk IOPs. Calculated using the following formula: (Total I/O bytes of current time) - (Total I/O bytes one second before the current time). This calculation can display a value of 0 KB per second if the Task Manager displays a positive value.
Username	User name of the user who owns the process.
Host CPU	CPU usage of the virtual machine to which the session is assigned.
Host Memory	Memory usage of the virtual machine to which the session is assigned.
Processes	Count of processes in the virtual machine
Refresh	The refresh icon refreshes the list of processes.
End Process	Ends a process that is running. Note You must have the Help Desk Administrator role to end a process. To end a process, select a process and click the End Process button.

Troubleshoot Linux Desktop Sessions in Horizon Help Desk Tool

In Horizon Help Desk Tool, you can troubleshoot Linux desktop sessions based on a user's connection status.

Prerequisites

- Start Horizon Help Desk Tool.

Procedure

- 1 On the user card, click the **Sessions** tab.

A performance card appears that displays CPU and memory usage and includes information about Horizon Client, and the virtual or published desktop.

- 2 Choose a troubleshooting option.

Option	Action
Send Message	Sends a message to the user on the published desktop or virtual desktop. You can choose the severity of the message to include Warning, Info, or Error. Click Send Message and enter the type of severity and the message details, and then click Submit .
Restart	Initiates the Restart process on the virtual desktop. This feature is not available for a published desktop session. Click Restart VDI .

Option	Action
Disconnect	Disconnect the desktop or application session. Click More > Disconnect .
Log Off	Initiates the log off process for a published desktop or virtual desktop. Click More > Log Off .
Reset	Initiates a reset of the virtual machine. This feature is not available for a published desktop. Click More > Reset VM . Note The user can lose unsaved work.

Collect Diagnostic Information for Horizon 7 for Linux Machine

You can collect diagnostic information to help VMware Technical Support diagnose and resolve issues with a Horizon 7 for Linux machine. You create a Data Collection Tool (DCT) bundle that gathers the machine's configuration information and logs into a compressed tarball.

Procedure

- 1 Log in to the Linux virtual machine as a user with the required privileges.
- 2 Open a command prompt and run the `dct-debug.sh` script.

```
sudo /usr/lib/vmware/viewagent/bin/dct-debug.sh
```

The script generates a tarball that contains the DCT bundle. For example:

```
ubuntu-12-vdm-sdct-20150201-0606-agent.tgz
```

The tarball is generated in the directory from which the script was executed (the current working directory).

Troubleshooting Copy and Paste between Remote Desktop and Client Host

Copy and Paste between the remote desktop and client host takes more than three seconds for maximum supported data of 1 MB. This issue does not occur if you copy and paste a small data size.

Problem

When you configure 1 vCPU and 1 GB memory for SLED 11 SP3/SP4 desktop, it might take more than three seconds to copy and paste between the remote desktop and local client host.

Cause

The delay in copy and paste might occur due to the old operating system APIs of SLED 11 SP3/SP4.

Solution

- ◆ Configure two vCPUs and 2 GB memory for SLED 11 SP3/SP4.

View Agent Fails to Disconnect on an iPad Pro Horizon Client

The SUSE View Agent connection fails to disconnect after a restart or shutdown on a iPad Pro Horizon Client.

Problem

When you restart or shutdown a SUSE virtual machine on an iPad Pro Horizon Client, the desktop does not respond. The View Agent fails to disconnect.

Cause

SUSE machine might not be sending messages correctly to Horizon Client after a restart or shutdown operation.

Solution

- ◆ Disconnect the desktop connection manually from iPad Pro Horizon Client.

SLES 12 SP1 Desktop Does Not Auto-Refresh

SLES 12 SP1 does not auto-refresh in a multi-monitor mode when you drag a GNOME terminal.

Problem

When you start SLES 12 SP1 in a multi-monitor mode and return to the window mode, the desktop does not refresh automatically when you drag a GNOME terminal.

Cause

The GNOME terminal does not respond to the drag operation.

Solution

- 1 End the GNOME Shell session.

```
kill -9 <process id of gnome-shell>
```

- 2 Restart the GNOME Shell session again.

SSO Fails to Connect to a PowerOff Agent

Single Sign-On (SSO) does not connect to a PowerOff agent.

Problem

When you log in as a broker and connect to an agent, SSO fails to connect to the PowerOff agent.

Solution

- ◆ Manually log in to the desktop, or disconnect and reconnect to the agent again.

Unreachable VM After Creating a Manual Desktop Pool for Linux

The virtual machine state is not responding.

Problem

The virtual machine status might be Waiting for Agent or Unreachable after you create a Manual Desktop Pool.

Cause

There might be several user error configuration or setup causes for the virtual machine state to be Unreachable or Waiting for Agent.

- Verify that the option `machine.id` exists in the virtual machines vmx configuration file.

If it does not exist, then verify that the virtual machine was added to the desktop pool correctly. Else recreate the desktop pool to let the broker rewrite the option to the vmx configuration file.

- Verify that the VMware Tool or Open VM Tool is installed correctly.

If the steps to install VMware Tool or Open VM Tool were not performed correctly, the `vmware-rpctool` command might not exist under `PATH` in the Linux virtual machine. You must follow the guide to install VMware Tool or Open VM Tool.

Run the command after you finish installing.

```
#vmware-rpctool "machine.id.get"
```

The `machine.id` values are listed from the virtual machines vmx configuration file.

- Verify if the FQDN of the broker can be resolved to the IP Address in the agent Linux virtual machine.