

VMware Skyline Collector Installation and Configuration Guide

VMware Skyline Collector 2.1.0



vmware®

You can find the most up-to-date technical documentation on the VMware website at:

<https://docs.vmware.com/>

If you have comments about this documentation, submit your feedback to

docfeedback@vmware.com

VMware, Inc.
3401 Hillview Ave.
Palo Alto, CA 94304
www.vmware.com

Copyright © 2019 VMware, Inc. All rights reserved. [Copyright and trademark information.](#)

Contents

- 1** About VMware Skyline Collector Installation and Configuration Guide 4
- 2** Skyline Collector Overview 5
- 3** Skyline Collector System Requirements 6
- 4** Skyline Collector User Accounts and Permissions 8
 - Skyline Collector Accounts 8
 - Product UserAccount Permissions 8
- 5** Skyline Collector Installation and Registration 11
 - Get Started with VMware Skyline 11
 - Create an Organization 11
 - Associate Support Entitlement 12
 - Download Skyline Collector 12
 - Skyline CollectorInstallation 12
 - Install the Client Integration Plug-In 13
 - Deploy OVF Template 14
 - Power on the Skyline Collector 15
 - Access the User Interface 16
 - Skyline CollectorConfiguration 16
 - Network Connectivity 17
 - Customer Experience Improvement Program (CEIP) 17
 - Collector Registration 17
 - Continue Configuration 18
 - Collector Name 19
 - Auto-Upgrade 19
 - ConfigurevCenter Server 20
 - ConfigureNSX Manager(Optional) 21
 - Configure Horizon View (Optional) 22
 - Configure vRealize Operations (Optional) 23
 - Migrate Existing Skyline Collectors 24
 - Access Skyline Advisor 24

About VMware Skyline Collector Installation and Configuration Guide

1

The VMware Skyline Collector Installation and Configuration Guide provide information about the VMware[®] Skyline[™] Collector system requirements and instructions for installing and configuring the Skyline Collector.

Intended Audience

This information is intended for anyone who wants to install, configure, or update the VMware Skyline Collector. It is written for VMware[®] vSphere[®] administrators.

VMware Technical Publications Glossary

VMware Technical Publications provides a glossary of terms that might be unfamiliar to you. For definitions of terms as they are used in VMware technical documentation, visit <https://www.vmware.com/support/pubs/>

Skyline Collector Overview

VMware[®] Skyline™ Collector is a VMware[®] virtual appliance that collects diagnostic data about your VMware[®] vSphere[®] and VMware[®] NSX[®] environments that enhances the product supportability through VMware's Global Services Support delivery.

Use of Skyline Collector requires registration with VMware.

The registration function includes:

- Agreeing to the Customer Experience Improvement Program (CEIP) - Enhanced Support
 - To keep your data safe, the registration function uses secure, private, and transparent approach.
- Authentication with VMware's My VMware Customer Portal.
- Customer Support Entitlement validation.

VMware Skyline enables an improved support experience for Production Support and Premier Services customers.

Skyline Collector System Requirements

3

To install Skyline Collector, ensure that your system meets the required hardware and software requirements.

Supported Web Browsers

The following web browsers are supported for accessing the Skyline Collector User Interface and Skyline Collector Appliance Management Interface (VAMI).

- Microsoft Edge
- Mozilla Firefox
- Google Chrome

Compatibility

- VMware vCenter Server 6.0, 6.5, 6.7
- VMware ESXi 6.0, 6.5, 6.7
- VMware NSX for vSphere 6.1, 6.2, 6.3, 6.4
 - Configuration of NSX for vSphere is optional.

Skyline Collector Resource Requirements

You can run the Skyline Collector on any system that meets the minimum system requirements.

Table: Hardware Requirements for the Skyline Collector virtual appliance

Number of vCPUs	Memory	Disk Space
2	8 GB	87 GB (1.1 GB initial if thin provisioned)

Networking Requirements

Skyline Collector uses network connections to collect and transfer support information securely.

Skyline Collector needs access to all vCenter Server and NSX Manager collection endpoints within the environment to collect product information data. It also needs access to the Internet to upload data. An HTTP proxy server can be used to proxy connectivity to the Internet, but access to vCenter Server and NSX Manager must be direct.

The table below shows the default networking connectivity requirements.

Table: External Network Connectivity Requirements

Machine	Connection To	Connection Type	Protocol	Port
VMware Skyline Collector	vcsa.vmware.com	HTTPS	TCP/IP	443
VMware Skyline Collector	vapp-updates.vmware.com	HTTPS	TCP/IP	443

Table : Internal Network Connectivity Requirements

Machine	Connection To	Connection Type	Protocol	Port
Skyline Collector	vCenter Server	HTTPS	TCP/IP	443
Skyline Collector	ESXi	HTTPS	TCP/IP	443
Skyline Collector	PSC/SSO Service provider 5.5	HTTPS	TCP/IP	7444
Skyline Collector	PSC/SSO Service provider 6.0 / 6.5	HTTPS	TCP/IP	443
Skyline Collector	NSX Manager	HTTPS	TCP/IP	443
Web browser	Skyline Collector	HTTPS	TCP/IP	443
Web browser	Skyline Collector (VAMI)	HTTPS	TCP/IP	5480

Note The tables contain the default port values and might not match a customized environment.

Skyline Collector User Accounts and Permissions

4

This section details the Skyline Collector user accounts and permissions needed to add vCenter Server and NSX Manager to the Skyline Collector.

This chapter includes the following topics:

- [Skyline Collector Accounts](#)
- [Product User Account Permissions](#)

Skyline Collector Accounts

There are two built-in Skyline Collector accounts - admin and root.

admin

The admin account is the primary account to interact with the Skyline Collector. This account is used to log into the Skyline Collector user interface. The password for the admin account is set during the initial configuration of the appliance.

root

The root account must only be used for updating the appliance through the Virtual Appliance Management Interface (VAMI). The VAMI can be accessed at the following address:

https://skyline_collector_ip_address_or_fqdn:5480. The password for the root account is set during the deployment of the virtual appliance using the Deploy OVF Template wizard within vCenter Server.

Using the root account to log in to Skyline Collector through the console must only be performed when troubleshooting in coordination with VMware Global Support Services (GSS). Logging on and changing information inside the appliance with the root account is not supported.

Product User Account Permissions

Skyline Collector requires the specific permissions to successfully add a vCenter Server or NSX Manager to the Skyline Collector for the purpose of providing proactive support.

vCenter Server User Account Permissions

- A user account with the following vCenter Server permissions is required to configure vCenter Server for the product use data collection.
 - vCenter Server built-in read-only role
 - Global.Licenss
 - Global.Diagnostics
 - Global.Health
 - Global.Settings

For detailed instructions for how to create a user account with the above permissions, please see [Knowledge Base Article 59661](#).

NSX Manager User Account Permissions

- An account with the following permissions in NSX Manager will be required to configure NSX Manager for product usage data collection.
 - NSX Manager built-in Auditor role.
 - Access to query information through APIs. Instructions for how to create a user with API privileges within NSX Manager can be found within [VMware Knowledge Base Article 2150736](#).

Note While VMware continues to recommend that an account with the NSX Manager built-in **Auditor** role be used, the **Auditor** role does not have permission to collect NSX Edge support log bundles using Skyline Log Assist.

If you want to enable the collection of NSX Edge support log bundles with Skyline Log Assist, you must use an account with the NSX Manager built-in **NSX Administrator** role when adding an NSX Manager to Skyline Collector.

For detailed instructions for how to create a user account with the above permissions, please see [Knowledge Base Article 59661](#).

Refer to the documentation specific to your version of NSX for vSphere to set up a user account with these privileges.

Horizon View User Account Permissions

A user account with the following Horizon View permissions is required to add Horizon View to the Skyline Collector.

- Horizon 7 Administrators (read-only) predefined role.

The Horizon 7 Administrators (read-only) predefined role has the following user capabilities within Horizon 7.

- View, but not modify, global settings and inventory objects.
- View, but not modify, ThinApp applications and settings.
- Run all PowerShell commands and command line utilities, including `vdmexport` but excluding `vdmadmin`, `vdmimport` and `lvmutil`.

More information about the predefined Administrator roles in Horizon View can be found [here](#).

vRealize Operations User Account Permissions

A user account with the following vRealize Operations Manager permissions is required to add Horizon View to the Skyline Collector.

- vRealize Operations Manager read-only role.

More information about the vRealize Operation Manager Roles and Permissions can be found [here](#).

Skyline Collector Installation and Registration

5

Download, Install, and Register Skyline Collector with VMware.

This chapter includes the following topics:

- [Get Started with VMware Skyline](#)
- [Create an Organization](#)
- [Skyline Collector Installation](#)
- [Skyline Collector Configuration](#)
- [Migrate Existing Skyline Collectors](#)
- [Access Skyline Advisor](#)

Get Started with VMware Skyline

Get started with Skyline Collector using the getting started wizard.

Procedure

- 1 Open a web browser and enter the URL for the VMware Skyline Getting Started page. <https://skyline.vmware.com/get-started>. You will be re-directed to the VMware Cloud Services log in page.
- 2 Log In to VMware Cloud Services.
 - a Enter your **My VMware email address**.
 - b Enter your **My VMware password**.

Create an Organization

Create an Organization within VMware Cloud Services.

Procedure

- 1 Enter a **Organization Name**.

2 Enter an **Organization Address**.

- a Click **Add Address**.
- b Select a Country.
- c Enter your street address on Address Line 1. Use Address Line 2 if additional space is needed.
- d Enter your **City**.
- e Enter your **State/Province**.
- f Enter your **Zip/Postal Code**.
- g Select the box **I agree to the VMware Cloud Services Terms of Service**.

3 Click **Continue**. Now continue with the VMware Skyline get-started wizard.

Associate Support Entitlement

Attach your current Production Support or Premier Services Support Entitlement to Skyline.

Prerequisites

- Previously created an Organization within VMware Cloud Services.

Procedure

- 1 Click **Associate SupportEntitlement**.
- 2 Click **Proceed to Next Step**.

This step successfully associates support entitlement to Skyline.

Download Skyline Collector

You must download the Skyline Collector virtual appliance from the download center.

Procedure

- 1 Download [Skyline Collector](#).

To access the Skyline Collector download page, you have to enter your My VMware user name and password .

- 2 After you download Skyline Collector, click **Proceed to Next Step**.

Skyline CollectorInstallation

Deploy the Skyline Collector using the vCenter Server OVF deployment wizard.

The Skyline Collector is distributed as a virtual appliance in Open Virtualization Appliance (OVA) format. You can deploy the Skyline Collector appliance using the vCenter Server OVF deployment wizard.

An appliance is a pre-configured virtual machine that typically includes a pre-installed guest operating system and other software.

After you deploy the Skyline Collector, you can access the Skyline Collector user interface using a web browser and browsing to the IP address or fully qualified domain name of the deployed appliance.

Procedure

- 1 Install the Client Integration Plug-In.

The Client Integration Plug-in provides access to the virtual machine's console in the vSphere Web Client and provides access to other vSphere infrastructure features. The Client Integration Plug-in also lets you deploy virtual appliances and log in to the vSphere Client using Windows session credentials.

- 2 Deploy the Skyline Collector virtual appliance.

The Skyline Collector is distributed as an appliance in OVA format that you can deploy using the vSphere Client.

- 3 Power on the Skyline Collector and Access the User Interface.

To use the Skyline Collector, first power it on and retrieve the IP address of the virtual appliance.

Install the Client Integration Plug-In

The Client Integration Plug-in provides access to a virtual machine's console in the vSphere Client and provides access to other vSphere infrastructure features. The Client Integration Plug-in also let you deploy Virtual Appliances and log in to the vSphere Client using Windows session credentials.

Prerequisites

You must use the Client Integration Plug-in to deploy OVF or OVA templates and transfer files with the datastore browser. You can also use the Client Integration Plug-in to connect virtual devices that reside on a client computer to a virtual machine.

Install the Client Integration Plug-in only once to enable all the functionality the plug-in delivers. You must close the web browser before installing the plug-in.

Procedure

- 1 In the vSphere Client, navigate to the link to download the Client Integration Plug-in.

Table : Client Integration Plug-in

Option	Description
vSphere Client login page	<ul style="list-style-type: none"> ■ Open a Web browser and type the URL for the vSphere Web Client. ■ At the bottom of the vSphere Web Client login page, click Download Client Integration Plug-in. <p>Note If the Client Integration Plug-In is already installed on your system, you will not see the link to download the plug-in. If you uninstall the Client Integration Plug-In, the link to download it displays on the vSphere Client login page.</p>
OVF deployment wizard	<ul style="list-style-type: none"> ■ Select a host in the inventory. ■ Select Actions and navigate to Deploy OVF Template. ■ Click Download Client Integration Plug-In.

- 2 If the browser blocks the installation either by issuing certificate errors or by running a pop-up blocker, follow the Help instructions for your browser to resolve the problem.

If you are using Google Chrome and having issues with the Client Integration Plug-in, see [Knowledge Base Article 2130672](#).

Deploy OVF Template

You can deploy Skyline Collector using the Deploy OVF Template wizard in vCenter Server.

Skyline Collector is distributed as a virtual appliance in OVA format. Use the vSphere Client to deploy Skyline Collector within your environment.

Prerequisites

- Verify that your system meets the minimum hardware and software requirements. See [Skyline Collector System Requirements](#).
- Download the Skyline Collector.

Procedure

- 1 Log in to the vSphere Client with an account that has virtual machine deploy permissions.
- 2 In the vSphere Client, select an inventory object that is a valid parent object of a virtual machine such as a data center, folder, cluster, resource pool, or host.
- 3 Click **Actions**. Navigate to **Deploy OVF Template**. You can access the **Actions** menu by right-clicking on the selected object (data center, folder, cluster, resource pool, or host) or by selecting **Actions** in the top-center of the vSphere Client.
- 4 Enter the URL or select Local File and Browse to the Skyline Collector OVA, and click **Next**.
- 5 Enter a name for Skyline Collector and select a deployment location, such as a data center or folder, and click **Next**.
- 6 Select a host, cluster, or resource pool for where to run Skyline Collector, and click **Next**.
- 7 Review the template details and click **Next**.
- 8 Read the VMware End User License Agreement (EULA) and click **Accept**, then click **Next**.
- 9 Select a location to store the Skyline Collector virtual disk files.
 - a Select the virtual disk format from the dropdown. The Skyline Collector supports thick provisioned lazy zeroed, thick provisioned eager zeroed, and thin provision.
 - b Select a VM storage policy, if applicable.
 - c Select the datastore, or datastore cluster, for where to store the Skyline Collector virtual disk files.
 - d Select **Next**.

Table : Disk Provisioning

Option	Description
Thick Provisioned Lazy Zeroed	Creates a virtual disk in a default thick format. Space required for the virtual disk is allocated when the virtual disk is created. Existing data on the physical device is not erased during creation but is zeroed out on first write from the virtual machine.
Thick Provision Eager Zeroed	A type of thick virtual disk that supports clustering features such as Fault tolerance. Space required for the virtual disk is allocated upon creation. In contrast to the lazy zeroed format, the data existing on the physical device is zeroed out when the virtual disk is created. Creating disks in this format might take much longer than creating other types of disks.
Thin Provision	Use this format to save hard disk space. For the thin disk, you provision as much data store space as the disk requires based on the value that you enter for the disk size. However, the thin disk starts small, and at first, uses only as much datastore space as the disk needs for its initial operations.

- 10 Select a network that provides the appropriate network access as described in [Networking Requirements](#).
 - a Select a **Destination Network** from the drop-down menu for the Skyline Collector.
 - b Select a **IP Protocol** from the drop-down menu. The Skyline Collector supports IPv4 and IPv6.
 - c Select **Next**.
- 11 Customize the deployment of the Skyline Collector. Customization includes creating a root password and entering static IP address information (optional).
 - a A root password is required. The password must be at least 8 characters long.
 - b To configure a dynamic IP address, leave all networking properties boxes empty. To configure a static IP address, enter the information specific to your network. The appliance must be able to resolve the hostnames for vCenter Server, Single Sign-On authentication, and any additional product endpoints (NSX Manager).
 - c Click **Next** after finishing customizing the template.
- 12 Review the configuration data you provided for the Skyline Collector. Click **Finish** to complete the Deploy OVF Template wizard.

Power on the Skyline Collector

To use the Skyline Collector, you must first power it on and get the IP address of the virtual appliance.

Procedure

- 1 Log in to the vSphere Client.
- 2 Right-click on the **Skyline Collector** virtual appliance, select **Power**, and select **Power On**.
- 3 View the IP address of the Skyline Collector on the Summary tab within the vSphere Client. You might need to refresh the vSphere Client to view the IP address of the Skyline Collector after powering it on.

Note A browser security warning appears the first time you browse to the user interface. The warning is an expected behavior.

Note

Access the User Interface

Log in to the Skyline Collector user interface.

This section describes how to access the Skyline Collector user interface.

Prerequisites

- The Skyline Collector IP address or fully qualified domain name (FQDN).

Procedure

- 1 Open a web browser and enter the URL for the Skyline Collector `https://skyline_collector_fully_qualified_domain_name_or_ip_address`.
- 2 Log in to the user interface using the following default values. Click **Log In**.

Username	<code>admin</code>
Password	<code>default</code>

- 3 You are forced to change this password at the first login. The new password must meet the following character requirements:
 - Minimum of eight characters
 - One lowercase letter
 - One uppercase letter
 - One special character (!@#\$%)
 - One number
- 4 Click **Change** after entering a new password. You must relogin to the Skyline Collector user interface after changing the password.
- 5 Select **Login Again** to return to the login screen.
- 6 Return to the Skyline Organization page within VMware Cloud Services and select **Proceed to Next Step**.

Skyline Collector Configuration

To create a registration token, register your Skyline Collector with the Skyline Organization you created in the previous step .

Prerequisites

- Created Organization within VMware Cloud Services.
- Deployed the Skyline Collector within vCenter Server.

Procedure

- 1 Click **Create New Token**. Copy the token to your clipboard for use during the initial configuration of the Skyline Collector.
- 2 Return to the Skyline Collector User Interface. If you have been logged-out, log in using the **admin** account.

Network Connectivity

Configure network connectivity from the Skyline Collector to VMware.

Skyline Collector uploads encrypted product usage data to VMware over the Internet. If required by your organization, an HTTP proxy server can be configured between Skyline Collector and the Internet.

Procedure

- 1 To configure a Proxy Server, toggle the Use a Proxy Server switch to **Yes**. If not, leave the Use a Proxy Server switch set to No and proceed to Step 6.
- 2 Enter the Proxy Server **fully_qualified_domain_name_or_ip_address**.
- 3 Enter the **Proxy Server Port**.
- 4 Enter the **Proxy Server Username** (optional).
- 5 Enter the **Proxy Server Password** (optional).
- 6 Click **Add Proxy Configuration**.
- 7 Click **Continue**.

Customer Experience Improvement Program (CEIP)

Agree to participate in the Customer Experience Improvement Program (CEIP).

Collection of product usage data by the Skyline Collector is subject to acceptance in VMware's Customer Experience Improvement Program (CEIP). Additional information regarding the CEIP can be found at <https://www.vmware.com/solutions/trustvmware/ceip.html>.

Procedure

- ◆ After reviewing the CEIP details, Click **Agree and Continue**.

Collector Registration

Use the registration token previously created to register your Skyline Collector with your Skyline Organization.

Prerequisites

- Created an Organization within VMware Cloud Services.
- Deployed the Skyline Collector within vCenter Server.

Procedure

- 1 **Type**, or **paste**, your registration token in the space provided next to Collector Registration Token.
- 2 Click **Register Collector**.
- 3 Click **Continue**.

Collector Successfully Registered.

Continue Configuration

Prepare for adding vCenter Server and NSX Manager to Skyline Collector.

You are now ready to add vCenter Server, NSX Manager, Horizon View, and vRealize Operations to the Skyline Collector. You can request or create appropriate accounts or credentials now. You can complete this step later without having to complete the previous steps.

Prerequisites

- For vCenter Server, An account with the following permissions is required.
 - Built-in vCenter Server read-only role
 - Global. License
 - Global. Diagnostics
 - Global. Health
 - Global. Settings
- For NSX Manager, a user account with the following permissions is required.
 - Built-in NSX Manager Auditor role

- Access to query information through APIs.

Note

- **Note** While VMware continues to recommend that an account with the NSX Manager built-in **Auditor** role be used, the **Auditor** role does not have permission to collect NSX Edge support log bundles using Skyline Log Assist.

If you want to enable the collection of NSX Edge support log bundles with Skyline Log Assist, you must use an account with the NSX Manager built-in **NSX Administrator** role when adding an NSX Manager to Skyline Collector.

For detailed instructions for how to create a user account with the preceding permissions, please see [Knowledge Base Article 59661](#).

- For Horizon View, a user account with the following permissions is required.
 - Horizon 7 Administrators (read-only) predefined role.
 - For vRealize Operations, a user account with the following permissions is required.
 - vRealize Operations Manager Administrators role.
-

Procedure

- ◆ Click **Continue**.

Collector Name

Create a friendly name for the Skyline Collector for ease of troubleshooting.

A friendly name describes the environment you are configuring the Skyline Collector to collect data from. This name is used to make it easier for VMware GSS to communicate information about the Skyline Collector with you.

Example: East-Production, City Name, Test/Dev

Procedure

- 1 Enter a **Friendly Name**.
- 2 Click **Set Friendly Name**.
- 3 Click **Continue**.

Auto-Upgrade

Enable automatic upgrades for the Skyline Collector.

The Skyline Collector supports the ability to automatically install upgrades, if available. Auto-Upgrade checks for and installs updates to the Skyline Collector at a specific time and day of the week that you specify.

Prerequisites

- The Skyline Collector must be able to receive update notifications from vapp-updates.vmware.com. For more details regarding networking requirements, see [Networking Requirements](#)

Procedure

- 1 To enable Auto-Upgrade, toggle the Enable Collector Auto-Upgrade switch to **Yes**. If you do not want to enable Auto-Upgrade, skip to Step 4.
- 2 Choose your auto-upgrade configuration.
 - a From the **dropdown menu**, choose a day of the week for the Skyline Collector to check for and install updates, if available.
 - b From the **dropdown menu**, choose a time of the day for the Skyline Collector to check for and install updates, if available.
- 3 Click **Set Upgrade Configuration** to save your settings.
- 4 Click **Continue**.

After each collector auto-upgrade, an email notification will be sent to the My VMware email address used during the initial configuration.

Configure vCenter Server

Add a vCenter Server to the Skyline Collector.

Prerequisites

- A user account with the following vCenter Server permissions is required to configure vCenter Server for the product use data collection.
 - vCenter Server built-in read-only role
 - Global.License
 - Global.Diagnostics
 - Global.Health
 - Global.Settings

For detailed instructions for how to create a user account with the above permissions, please see [Knowledge Base Article 59661](#).

Procedure

- 1 Enter the vCenter Server details.
 - a Enter the vCenter Server or **fully-qualified domain name (FQDN)** or **IP address**.
 - b Enter the vCenter Server read-only user account **username**.
 - c Enter the **password** for the user account specified in the previous step.

- 2 If you are using an external Platform Services Controller (PSC), Single-Sign On (SSO) provider or have a custom SSO domain, toggle the Use Custom SSO Configuration switch to **Yes**.
 - a Enter the PSC/SSO server or **fully-qualified domain name (FQDN)** or **IP address**.
 - b If you are using the default PSC/SSO provider configuration, you do not need to complete the **Advanced Options (optional)** fields. Complete the **SSO Admin URL**, **SSO STS URL** and **Lookup Service URL** only if you specified a custom configuration during the deployment of your PSC or SSO provider.

For additional details regarding your PSC/SSO provider configuration, please see the vCenter Server vpxd.cfg file.

- In vCenter Server Appliance 6.x, the vpxd.cfg file is located at /etc/vmware-vpx/.
 - In Windows Server, the vpxd.cfg file is located at C:\ProgramData\VMware\VMware VirtualCenter\vpxd.cfg.
 - In vCenter Server 6.0, the vpxd.cfg file is located at C:\ProgramData\VMware\vCenterServer\cfg\vmware-vpx.
- c If you do not want to collect product usage data from all data centers connected to the vCenter Server you are configuring, toggle the Collect from all Datacenters switch to **No**, then click **Add**. An invalid certificate warning may appear. This is expected, click **Continue**. Select the **checkbox** next to each data center that you want to collect product usage data for. When finished selecting data centers, click **Enable Selected Datacenters**.
- 3 Click **Add** to complete the addition of vCenter Server to the Skyline Collector for product usage data collection.
 - 4 Click **Continue**.

You will now receive proactive findings for the vCenter Server added to Skyline Collector. You can add additional vCenter Server to the Skyline Collector within the Skyline Collector User Interface.

Note Disabling product usage data collection from all data centers may prohibit VMware from providing an optimal support experience.

Configure NSX Manager(Optional)

Add a NSX Manager to the Skyline Collector.

If NSX is deployed within your environment, you can add an NSX Manager to the Skyline Collector now to enable to receive findings and recommendations for NSX.

This step can be skipped if you do not have NSX deployed within in your environment, or do not want to add an NSX Manager to the Skyline Collector now.

Prerequisites

- An account with the following permissions in NSX Manager requires to configure NSX Manager for the product usage data collection.
 - NSX Manager built-in Auditor role.
 - Access to query information through APIs. Instructions for how to create a user with API privileges within NSX Manager can be found within [VMware Knowledge Base Article 2150736](#).

Note While VMware recommends an account with the NSX Manager built-in **Auditor** role be used, the **Auditor** role does not have permission to collect NSX Edge support log bundles using Skyline Log Assist.

If you want to enable the collection of NSX Edge support log bundles with Skyline Log Assist, you must use an account with the NSX Manager built-in **NSX Administrator** role when adding an NSX Manager to Skyline Collector.

For detailed instructions for how to create a user account with the preceding permissions, see [Knowledge Base Article 59661](#).

Procedure

- 1 Enter the NSX Manager details.
 - a Enter the NSX Manager **fully-qualified domain name (FQDN)** or **IP address**.
 - b Enter an NSX Manager user account **username**.
 - c Enter the NSX Manager user account **password**.
- 2 To add this NSX Manager to the Skyline Collector, click **Add**.
- 3 Click **Continue**.

You receive findings for the NSX Manager added to Skyline Collector. You can add additional NSX Managers to the Skyline Collector within the Skyline Collector User Interface.

Configure Horizon View (Optional)

Add a Horizon View Connection Server to the Skyline Collector.

If Horizon View is deployed within your environment, you can add a Horizon View Connection Server to the Skyline Collector now to enable to receive proactive findings and recommendations for Horizon View.

This step can be skipped if you do not have Horizon View deployed within in your environment, or do not want to add a Horizon View Connection Server to the Skyline Collector now.

Prerequisites

A user account with the following Horizon View permissions is required to add Horizon View to the Skyline Collector.

- Horizon 7 Administrators (read-only) predefined role.

The Horizon 7 Administrators (read-only) predefined role has the following user capabilities within Horizon 7.

- View, but not modify, global settings and inventory objects.
- View, but not modify, ThinApp applications and settings.
- Run all PowerShell commands and command-line utilities, including `vdmexport` but excluding `vdmadmin`, `vdmimport` and `lmvutil`.

More information about the predefined administrator roles in Horizon View can be found [here](#).

Procedure

- 1 Enter the Horizon View Connection Server details.
 - a Enter the Horizon View Connection Server **fully-qualified domain name** or **IP address**.
 - b Enter a Horizon View Connection Server user account **username**.
 - c Enter the Horizon View Connection Server user account **password**.
- 2 Click **Add** to complete the process of adding the Horizon View Connection Server to the Skyline Collector.

You receive proactive findings for the Horizon View Connection Server added to Skyline Collector. You can add additional Horizon View Connection Servers to the Skyline Collector within the Skyline Collector User Interface.

Configure vRealize Operations (Optional)

Add a vRealize Operations Manager to the Skyline Collector.

If vRealize Operations is deployed within your environment, you can add a vRealize Operations Manager to the Skyline Collector now to enable to receive proactive findings and recommendations for vRealize Operations.

This step can be skipped if you do not have vRealize Operations deployed within in your environment, or do not want to add a vRealize Operations Manager to the Skyline Collector now.

Prerequisites

A user account with the following vRealize Operations Manager permissions is required to add vRealize Operations Manager to the Skyline Collector.

- vRealize Operations Manager read-only role.

More information about the vRealize Operation Manager Roles and Permissions can be found [here](#).

Procedure

- 1 Enter the vRealize Operations Manager details.
 - a Enter the vRealize Operations Manager **fully-qualified domain name** or **IP address**.
 - b Enter a vRealize Operations Manager user account **username**.
 - c Enter the vRealize Operations Manager user account **password**.
- 2 Click **Add** to complete the process of adding the vRealize Operations Manager to Skyline Collector.

You will now receive proactive findings for the vRealize Operations Manager added to the Skyline Collector. You can add additional vRealize Operations Managers to the Skyline Collector within the Skyline Collector User Interface.

What to do next

You can review your endpoints, modify endpoints, or add endpoints within the VMware Skyline Collector user interface. Refer to the VMware Skyline Collector User Guide for more information. Click **Finish** to complete the Initial Configuration of the Skyline Collector.

Migrate Existing Skyline Collectors

If you have existing Skyline Collectors, migrate them to your Skyline Organization you created in the previous step.

Prerequisites

- Existing Skyline Collectors deployed within your environment running version 1.4 or earlier.

Procedure

- 1 Return to the Skyline Organization wizard within VMware Cloud Services.
- 2 Migrate an existing Skyline Collectors to your Skyline Organization by clicking **Migrate** next to each Skyline Collector.
- 3 After migrating all Skyline Collectors, click **Proceed to Next Step**.

Access Skyline Advisor

View your active findings, transfer support log bundles, and manage your Skyline Collectors.

Prerequisites

- Created Organization within VMware Cloud Services.
- Deployed the Skyline Collector within vCenter Server.
- Registered Skyline Collectors in Organization within VMware Cloud Services.

Procedure

- 1 You can access Skyline Advisor directly using this link: <https://skyline.vmware.com/advisor>.
 - a We recommend bookmarking this link for later use.
- 2 You can now close the Skyline Organization wizard page within VMware Cloud Services.