

Getting Started

Update 1

Modified on 03 SEP 2017

vRealize Log Insight 4.0



vmware®

You can find the most up-to-date technical documentation on the VMware website at:

<https://docs.vmware.com/>

If you have comments about this documentation, submit your feedback to

docfeedback@vmware.com

VMware, Inc.
3401 Hillview Ave.
Palo Alto, CA 94304
www.vmware.com

Copyright © 2014–2017 VMware, Inc. All rights reserved. [Copyright and trademark information.](#)

Contents

About Getting Started for vRealize Log Insight	4
Updated Information for Getting Started	5
1 Before You Install vRealize Log Insight	6
Supported Log Files and Archive Formats in vRealize Log Insight	6
Security Requirements	7
Product Compatibility	7
Minimum Requirements	8
Sizing the vRealize Log Insight Virtual Appliance	10
Integrating vRealize Log Insight and vRealize Operations Manager	11
Life Cycle of an Event	12
Key Aspects of the Event Life Cycle	13
2 Installing vRealize Log Insight	14
Deploy the vRealize Log Insight Virtual Appliance	14
Start a New vRealize Log Insight Deployment	16
Join Existing Deployment	18
3 The Customer Experience Improvement Program	20

About Getting Started for vRealize Log Insight

Getting Started for vRealize Log Insight provides information about deploying and configuring VMware® vRealize™ Log Insight™, including how to size the vRealize Log Insight virtual appliance to receive log messages from your environment.

Use this information when you want to plan or install your deployment. This information is written for experienced Linux and Windows system administrators who are familiar with virtual machine technology and data center operations.

Updated Information for Getting Started

Getting Started for vRealize Log Insight is updated with each release of the product or when necessary.

This table provides the update history of *Getting Started* for vRealize Log Insight.

Revision	Description
002032-1	<ul style="list-style-type: none">■ This revision includes updated information about the Customer Experience Improvement Program. See Chapter 3 The Customer Experience Improvement Program.■ This revision includes revised topics about the life-cycle of an event. See Life Cycle of an Event and Key Aspects of the Event Life Cycle. Note that the maximum size for buckets in version 4.0 has been changed to .5GB.
002032	Initial release.

Before You Install vRealize Log Insight

1

To start using vRealize Log Insight in your environment, you must deploy the vRealize Log Insight virtual appliance and apply several basic configurations.

This chapter includes the following topics:

- [Supported Log Files and Archive Formats in vRealize Log Insight](#)
- [Security Requirements](#)
- [Product Compatibility](#)
- [Minimum Requirements](#)
- [Sizing the vRealize Log Insight Virtual Appliance](#)
- [Integrating vRealize Log Insight and vRealize Operations Manager](#)
- [Life Cycle of an Event](#)
- [Key Aspects of the Event Life Cycle](#)

Supported Log Files and Archive Formats in vRealize Log Insight

You can use vRealize Log Insight to analyze unstructured or structured log data.

vRealize Log Insight accepts data from the following sources:

- Sources that support sending log streams with the syslog protocol.
- Sources that write log files and can run the vRealize Log Insight agent.
- Sources that can post log data with HTTP or HTTPS through the REST API. See <https://www.vmware.com/go/loginsight/api>.
- Historic data that was archived by vRealize Log Insight.

The vSphere log parser allows you to import vSphere log bundles in vRealize Log Insight.

Note Although vRealize Log Insight can handle historic data and real-time data simultaneously, you are advised to deploy a separate instance of vRealize Log Insight to process imported log files.

See [Import a Log Insight Archive into vRealize Log Insight](#) in *Administering vRealize Log Insight*.

Security Requirements

To ensure that your virtual environment is protected from external attacks, you must observe certain rules.

- Always install vRealize Log Insight in a trusted network.
- Always save vRealize Log Insight support bundles in a secure location.

IT decision makers, architects, administrators, and others who must familiarize themselves with the security components of vRealize Log Insight must read the security topics in *Administering vRealize Log Insight*.

These topics provide concise references to the security features of vRealize Log Insight. Topics include the product external interfaces, ports, authentication mechanisms, and options for configuration and management of security features.

For information about securing your virtual environment, see the *VMware vSphere Security Guide* and the Security Center on the VMware Web site.

Product Compatibility

vRealize Log Insight collects data over the syslog protocol and HTTP, can connect to vCenter Server to collect events, tasks, and alarms data, and can integrate with vRealize Operations Manager to send notification events and enable launch in context . Check the *VMware vRealize Log Insight Release Notes* for latest updates on supported product versions.

Virtual Appliance Deployment

You must deploy the vRealize Log Insight virtual appliance using vSphere. Always use a vSphere Client to connect to a vCenter Server. The vRealize Log Insight virtual appliance should be deployed on an ESX/ESXi host version 4.1 or later that is managed by vCenter Server version 4.1 or later.

Syslog Feeds

vRealize Log Insight collects and analyses syslog data over the following ports and protocols.

- 514/UDP
- 514/TCP
- 1514/TCP (SSL)

You must configure environment components such as operating systems, applications, storage, firewalls, and network devices to push their syslog feeds to vRealize Log Insight.

API Feeds

The vRealize Log Insight Ingestion API collects data over the following port and protocol.

- 9000/TCP

- 9543/TCP (SSL)

vSphere Integration

You can configure vRealize Log Insight to pull data for tasks, events, and alarms that occurred in one or more vCenter Server instances. vRealize Log Insight uses the vSphere API to connect to vCenter Server systems and collect data.

You can configure ESXi hosts to forward syslog data to vRealize Log Insight.

For compatibility information with specific versions of vCenter Server and ESXi, see the [VMware Product Interoperability Matrixes](#)

For information about connecting to a vSphere environment, see [Connect vRealize Log Insight to a vSphere Environment](#).

vRealize Operations Manager Integration

vRealize Log Insight and vRealize Operations Manager vApp or Installable can be integrated in two independent ways.

All supported versions of vCenter Operations Manager 6.0 and later, support Notifications as well as Launch in Context.

- vRealize Log Insight can send notification events to vRealize Operations Manager.
See [Configure Log Insight to Send Notification Events to vRealize Operations Manager](#).
- The launch in context menu of vRealize Operations Manager can display actions related to vRealize Log Insight.
See [Enable Launch in Context for Log Insight in vRealize Operations Manager](#).

Minimum Requirements

VMware distributes vRealize Log Insight as a virtual appliance in OVA file format. Various resources and applications must be available for the virtual appliance to run successfully. For the most up-to-date information about requirements, check the latest release notes.

Virtual Hardware

During deployment of the vRealize Log Insight virtual appliance you can select from preset configuration sizes according to the ingestion requirements for your environment. These are certified size combinations of compute and disk resources, though you can add extra resources afterward. A small configuration, described in the following table, consumes the least resources while remaining supported. An extra small configuration is also available, but it is suitable only for demos.

For complete resources requirements based on ingestion requirements, see [Sizing the vRealize Log Insight Virtual Appliance](#)

Table 1-1. Preset Values for Small Configurations

Resources	Minimum Requirement
Memory	8GB
vCPU	4
Storage Space	510GB

Supported Browsers

You can use one of the following browsers to connect to the vRealize Log Insight web user interface. More recent browser versions also work with vRealize Log Insight, but have not been validated.

Important Cookies must be enabled in your browser.

- Mozilla Firefox 45.0 and above
- Google Chrome 51.0 and above
- Safari 9.1 and above
- Internet Explorer 11.0 and above

Note Internet Explorer Document mode must be set to **Standards Mode**. Other modes are not supported. **Browser Mode:** Compatibility View is not supported.

Account Passwords

Type	Requirements
Root	<p>Unless you specify a root password or use guest customization during the deployment of the OVA, the default credentials for the root user on the vRealize Log Insight virtual appliance are root/blank. You are prompted to change the root account password when you first access the vRealize Log Insight virtual appliance console.</p> <p>Note SSH is disabled until you set the root password.</p>
User Account	<p>User accounts that you create in vRealize Log Insight 3.3 and later require a strong password. The password must be at least 8 characters long and contain one uppercase character, one lowercase character, one number and one special character.</p>

Integration Requirements

Product	Requirement
vCenter Server	To pull events, tasks, and alarms data from a vCenter Server, you must provide a set of user credentials for that vCenter Server. The minimum role required to register and unregister vRealize Log Insight with a vCenter Server is Read-only , which must be set at the vCenter Server level and propagated to child objects. To configure ESXi hosts that a vCenter Server manages, vRealize Log Insight requires additional privileges.
vSphere ESXi	vSphere ESXi 6.0 Update 1 or later is required to establish SSL connections to vRealize Log Insight.
vRealize Operations Manager	To enable notification events and the launch in context functionality in a vRealize Operations Manager instance, you must provide user credentials for that vRealize Operations Manager instance.

Network Port Requirements

The following network ports must be externally accessible.

Port	Protocol
80/TCP	HTTP
443/TCP	HTTPS
514/UDP, 514/TCP	Syslog
1514/TCP	Syslog
9000/TCP	vRealize Log Insight Ingestion API
9543/TCP	vRealize Log Insight Ingestion API (SSL)

Sizing the vRealize Log Insight Virtual Appliance

By default, the vRealize Log Insight virtual appliance uses the preset values for small configurations, which have 4 vCPUs, 8GB of virtual memory, and 510GB of disk space provisioned. vRealize Log Insight uses 100GB of the disk space to store raw data, index, metadata, and other information.

Standalone Deployment

You can change the appliance settings to meet the needs of the environment for which you intend to collect logs during deployment.

vRealize Log Insight provides preset VM sizes that you can select from to meet the ingestion requirements of your environment. These are certified size combinations of compute and disk resources, though you can add extra resources afterward. A small configuration consumes the least resources while remaining supported. An extra small configuration is suitable only for demos.

Option	Log Ingest Rate	vCPUs	Memory	IOPS	Syslog Connections	Events per Second
Extra Small	6GB/day	2	4GB	75	20	400
Small	30GB/day	4	8GB	500	100	2000

Option	Log Ingest Rate	vCPUs	Memory	IOPS	Syslog Connections	Events per Second
Medium	75GB/day	8	16GB	1000	250	5000
Large	225GB/day	16	32GB	1500	750	15,000

Note You can use a syslog aggregator to increase the number of syslog connections that send events to vRealize Log Insight. However, the maximum number of events per second is fixed and does not depend on the use of a syslog aggregator. A vRealize Log Insight instance cannot be used as a syslog aggregator.

The sizing is based on the following assumptions.

- Each vCPU is at least 2GHz.
- Each ESXi host sends up to 10 messages per second with an average message size of 170 bytes/message. This is roughly equivalent to 150MB/day/host.

Note For large installations, you must upgrade the virtual hardware version of the vRealize Log Insight virtual machine. vRealize Log Insight supports virtual hardware version 7 or later. Virtual hardware version 7 can support up to 8 vCPUs. Therefore, you must upgrade to virtual hardware version 8 or later for ESXi 5.x if you plan to provision 16 vCPUs. You use the vSphere Client to upgrade the virtual hardware. If you want to upgrade virtual hardware to the latest version, read and understand the information in the VMware knowledge base article [Upgrading a virtual machine to the latest hardware version \(1010675\)](#).

Cluster Deployment

Use a medium configuration, or larger, for the master and worker nodes in a vRealize Log Insight cluster. The number of events per second increases linearly with the number of nodes. For example, in a cluster of 3-12 nodes (2 nodes are not supported), the net in a 12 node cluster is 180,000 events per second (EPS) or 2.7 TB of events per day.

Reducing the Memory Size

If you want to use the **Extra Small** version of the appliance on your laptop, but the laptop does not have enough memory, you can reduce the memory size to 2GB.

Integrating vRealize Log Insight and vRealize Operations Manager

To enable integration between vRealize Log Insight and vRealize Operations Manager, configuration must be performed in both products.

Procedure

- 1 Install the vRealize Log Insight Management Pack into vRealize Operations Manager.

The vRealize Log Insight Management Pack is required for the Launch in Context functionality between the two products. The vRealize Log Insight Management Pack is available with the vRealize Operations Manager download file or on the VMware Solution Exchange website.

- 2 Configure vRealize Log Insight to connect to vRealize Operations Manager.
- 3 Configure vRealize Log Insight alerts to forward information to vRealize Operations Manager.
See [Configure vRealize Log Insight to Send Notification Events to vRealize Operations Manager](#) in *Administering vRealize Log Insight*.
- 4 Enable vRealize Operations Launch In Context to query logs in vRealize Log Insight.
See [Enable Launch in Context for vRealize Log Insight in vRealize Operations Manager](#) in *Administering vRealize Log Insight*.

Life Cycle of an Event

The end-to-end life cycle of a log message or event includes multiple stages as the data flows in and out of vRealize Log Insight from agent read, parse, ingestion, indexing (buckets), alerting, query, archive (bucket seal and ship), and deletion.

An event transitions through the following stages.

- 1 It is generated on a device (outside of vRealize Log Insight).
- 2 It is picked up and sent to vRealize Log Insight (inside and/or outside vRealize Log Insight) in one of the following ways:
 - By a vRealize Log Insight agent using ingestion API or syslog
 - Through a third-party agent such as rsyslog, syslog-ng or log4j using syslog
 - By custom writing to ingestion API (such as log4j appender)
 - By custom writing to syslog (such as log4j appender)
- 3 The event is received by vRealize Log Insight.
 - If you are using the integrated load balancer (ILB), the event is directed to a single node that is responsible for processing the event.
 - If the event is declined, the client handles declines by means of UDP drops, TCP with protocol settings, or CFAPI with a disk-backed queue.
 - If the event is accepted, the client is notified.
- 4 The event is passed through the vRealize Log Insight ingestion pipeline, from which the following steps occur:
 - A keyword index is created or updated. The index is stored in proprietary format on local disk.
 - Machine learning is applied to cluster events.
 - The event is stored in compressed proprietary format on the local disk in a bucket .
- 5 The event is queried.
 - Keyword and glob queries are matched against the keyword index
 - Regex is matched against compressed events

- 6 The event is archived.
 - Bucket seal and marked as archived
- 7 The event is deleted.
 - Buckets are deleted in a FIFO model

Key Aspects of the Event Life Cycle

As an event ages, there are key aspects of event storage and management during the event life cycle to be aware of.

Event Storage

Each event is stored in a single on-disk bucket. When working with buckets, be aware of the following behaviors and characteristics.

- Buckets can reach a maximum size of .5GB. When a bucket reaches .5GB, it is sealed and can no longer be written to and is marked as to be archived. After a sealed bucket is archived, it is marked as archived. This means an event may be retained locally and in the archives at the same time.
- Buckets are not replicated across vRealize Log Insight nodes. If you lose a node then you lose the data on that node.
- All buckets are stored on the `/storage/core` partition.
- vRealize Log Insight deletes old buckets when available space on the `/storage/core` partition is less than 3%. Deletion is done using a FIFO model.

Note A near-full `/storage/core` partition is usual and expected. That partition should never reach 100% because vRealize Log Insight manages that partition. However, you should not attempt to store data on that partition as it may interfere with the old bucket delete process.

Event Management

Be aware of the following characteristics and behaviors of vRealize Log Insight events and event management.

- After an event is deleted locally it can no longer be queried unless it is imported from the archive using the command-line interface.
- After all events for a machine learning cluster are deleted from vRealize Log Insight, the cluster is removed.
- vRealize Log Insight automatically rebalances all incoming events fairly across nodes in the cluster. For example, even if a node is explicitly sent to an event, it may not be the node to ingest the event.
- Event metadata is stored in a proprietary format on a single vRealize Log Insight node and not in a database.
- An event can exist locally on a node as well as on the archive.

Installing vRealize Log Insight

vRealize Log Insight is delivered as a virtual appliance that you must deploy in your vSphere environment.

After reviewing [Sizing the vRealize Log Insight Virtual Appliance](#), proceed to [Deploy the vRealize Log Insight Virtual Appliance](#). Whether you have a single node deployment or a cluster deployment, follow the standard OVF deployment procedure described in this section.

This chapter includes the following topics:

- [Deploy the vRealize Log Insight Virtual Appliance](#)
- [Start a New vRealize Log Insight Deployment](#)
- [Join Existing Deployment](#)

Deploy the vRealize Log Insight Virtual Appliance

Download the vRealize Log Insight virtual appliance. VMware distributes the vRealize Log Insight virtual appliance as an .ova file. Deploy the vRealize Log Insight virtual appliance by using the vSphere Client.

Prerequisites

- Verify that you have a copy of the vRealize Log Insight virtual appliance .ova file.
- Verify that you have permissions to deploy OVF templates to the inventory.
- Verify that your environment has enough resources to accommodate the minimum requirements of the vRealize Log Insight virtual appliance. See [Minimum Requirements](#).
- Verify that you have read and understand the virtual appliance sizing recommendations. See [Sizing the Log Insight Virtual Appliance](#).

Procedure

- 1 In the vSphere Client, select **File > Deploy OVF Template**.
- 2 Follow the prompts in the **Deploy OVF Template** wizard.
- 3 On the Select Configuration page, select the size of the vRealize Log Insight virtual appliance based on the size of the environment for which you intend to collect logs.

Small is the minimum requirement for production environments.

vRealize Log Insight provides preset VM sizes that you can select from to meet the ingestion requirements of your environment. These are certified size combinations of compute and disk resources, though you can add extra resources afterward. A small configuration consumes the least resources while remaining supported. An extra small configuration is suitable only for demos.

Option	Log Ingest Rate	vCPUs	Memory	IOPS	Syslog Connections	Events per Second
Extra Small	6GB/day	2	4GB	75	20	400
Small	30GB/day	4	8GB	500	100	2000
Medium	75GB/day	8	16GB	1000	250	5000
Large	225GB/day	16	32GB	1500	750	15,000

Note You can use a syslog aggregator to increase the number of syslog connections that send events to vRealize Log Insight. However, the maximum number of events per second is fixed and does not depend on the use of a syslog aggregator. A vRealize Log Insight instance cannot be used as a syslog aggregator.

Note If you select **Large**, you must upgrade the virtual hardware on the vRealize Log Insight virtual machine after the deployment.

4 On the Select Storage page, select a disk format.

- **Thick Provision Lazy Zeroed** creates a virtual disk in a default thick format. Space required for the virtual disk is allocated when the virtual disk is created. The data remaining on the physical device is not erased during creation, but is zeroed out on demand at a later time, on first write from the virtual appliance.
- **Thick Provision Eager Zeroed** creates a type of thick virtual disk that supports clustering features such as Fault Tolerance. Space required for the virtual disk is allocated at creation time. In contrast to the flat format, the data remaining on the physical device is zeroed out when the virtual disk is created. It might take much longer to create disks in this format than to create other types of disks.

Important Deploy the vRealize Log Insight virtual appliance with thick provisioned eager zeroed disks whenever possible for better performance and operation of the virtual appliance.

- **Thin Provision** creates a disk in thin format. The disk grows as the data saved on it grows. If your storage device does not support thick provisioning disks or you want to conserve unused disk space on the vRealize Log Insight virtual appliance, deploy the virtual appliance with thin provisioned disks.

Note Shrinking disks on the vRealize Log Insight virtual appliance is not supported and might result in data corruption or data loss.

- 5 (Optional) On the Setup networks page, set the networking parameters for the vRealize Log Insight virtual appliance.

If you do not provide network settings, such as an IP address, DNS servers, and gateway information, vRealize Log Insight utilizes DHCP to set those settings.

Caution Do not specify more than two domain name servers. If you specify more than two domain name servers, all configured domain name servers are ignored in the vRealize Log Insight virtual appliance.

Use a comma-separated list to specify domain name servers.

- 6 (Optional) On the Customize template page, set network properties if you are not using DHCP.
- 7 (Optional) On the Customize template page, select Other Properties and set the root password for the vRealize Log Insight virtual appliance.

The root password is required for SSH. You can also set this password through the VMware Remote Console.

- 8 Follow the prompts to complete the deployment.

For information on deploying virtual appliances, see the *User's Guide to Deploying vApps and Virtual Appliances*.

After you power on the virtual appliance, an initialization process begins. The initialization process takes several minutes to complete. At the end of the process, the virtual appliance restarts.

- 9 Navigate to the **Console** tab and check the IP address of the vRealize Log Insight virtual appliance.

IP Address Prefix	Description
https://	The DHCP configuration on the virtual appliance is correct.
http://	The DHCP configuration on the virtual appliance failed. <ol style="list-style-type: none"> a Power off the vRealize Log Insight virtual appliance. b Right-click the virtual appliance and select Edit Settings. c Set a static IP address for the virtual appliance.

What to do next

- If you want to configure a standalone vRealize Log Insight deployment, see [Configure New Log Insight Deployment](#).

The vRealize Log Insight Web interface is available at `https://log-insight-host/` where *log-insight-host* is the IP address or host name of the vRealize Log Insight virtual appliance.

Start a New vRealize Log Insight Deployment

When you access the vRealize Log Insight Web interface for the first time after the virtual appliance deployment or after removing a worker node from a cluster, you must complete the initial configuration steps.

All settings that you modify during the initial configuration are also available in the Administration Web user interface.

For information about the trace data that vRealize Log Insight might collect and send to VMware when you participate in the Customer Experience Improvement Program, see [Chapter 3 The Customer Experience Improvement Program](#).

Prerequisites

- In the vSphere Client, note the IP address of the vRealize Log Insight virtual appliance. For information about locating the IP address, see [Deploy the vRealize Log Insight Virtual Appliance](#).
- Verify that you are using a supported browser. See [Minimum Requirements](#).
- Verify that you have a valid license key. You can request an evaluation or permanent license key through your account on My VMware™ at <https://my.vmware.com/>.
- If you want to use local, vCenter Server, or Active Directory credentials to integrate vRealize Log Insight with vRealize Operations Manager, verify that these users are imported in vRealize Operations Manager Custom user interface. For instructions about configuring LDAP, see the [vRealize Operations Manager documentation](#).

Procedure

- 1 Use a supported browser to navigate to the Web user interface of vRealize Log Insight.
The URL format is `https://log_insight-host/`, where `log_insight-host` is the IP address or host name of the vRealize Log Insight virtual appliance.
The initial configuration wizard opens.
- 2 Click **Start New Deployment**.
- 3 Set the password for the Admin user and click **Save and Continue**.
Optionally, you can provide an email address for the admin user.
- 4 Enter the license key, click **Add License Key**, and click **Save and Continue**.
- 5 On the General Configuration page, type the email address to receive system notifications from vRealize Log Insight.
- 6 If you are using webhooks to send notifications to vRealize Operations or a third-party application, enter a spaces-separated list of URLs in the **Send HTTP Post System Notifications To** field.
- 7 (Optional) To leave the Customer Experience Improvement Program, deselect the **Join the VMware Customer Experience Program** option. Click **Save and Continue**.
- 8 (Optional) Select the **Always Use English** option to ensure that the user interface and content is always displayed in English.

- 9 On the Time Configuration page, set how time is synchronized on the vRealize Log Insight virtual appliance and click **Test**.

Option	Description
NTP server (recommended)	By default, vRealize Log Insight is configured to synchronize time with public NTP servers. If an external NTP server is not accessible due to firewall settings, you can use the internal NTP server of your organization. Use commas to separate multiple NTP servers.
ESX/ESXi host	If no NTP servers are available, you can sync the time with the ESXi host where you deployed the vRealize Log Insight virtual appliance.

- 10 Click **Save and Continue**.

- 11 Specify the properties of an SMTP server to enable outgoing alert and system notification emails.

To verify that the SMTP configuration is correct, type a valid email address and click **Test**. vRealize Log Insight sends a test email to the address that you provided.

- 12 Click **Save and Continue**.

After the vRealize Log Insight process restarts, you are redirected to the **Dashboards** tab of vRealize Log Insight.

What to do next

- Go to the **Administration** page by selecting the drop-down menu icon  in the navigation bar and use the **vSphere Integration** page to configure vRealize Log Insight to pull tasks, events, and alerts from vCenter Server instances, and to configure ESXi hosts to send syslog feeds to vRealize Log Insight.

Join Existing Deployment

After you deploy and set up a standalone vRealize Log Insight node, you can deploy a new vRealize Log Insight instance and add it to the existing node to form a vRealize Log Insight cluster.

vRealize Log Insight can scale out by using multiple virtual appliance instances. This enables linear scaling of the ingestion throughput, increases query performance and allows for ingestion high availability. In cluster mode, vRealize Log Insight provides master and worker nodes. Both master and worker nodes are responsible for a subset of data. Master nodes can query all subsets of data and aggregate the results.

Important It is highly recommended that you configure a minimum of three nodes in a vRealize Log Insight cluster to provide ingestion, configuration, and user space High Availability.

Prerequisites

- In the vSphere Client, note the IP address of the worker vRealize Log Insight virtual appliance.
- Verify that you have the IP address or host name of the master vRealize Log Insight virtual appliance.
- Verify that you have an administrator account on the master vRealize Log Insight virtual appliance.

- Verify that the versions of the vRealize Log Insight master and worker nodes are in sync. Do not add an older version vRealize Log Insight worker to a newer version vRealize Log Insight master node.
- You must synchronize the time on the vRealize Log Insight virtual appliance with an NTP server. See [Synchronize the Time on the Log Insight Virtual Appliance](#).
- For information on supported browser versions, see the [vRealize Log Insight Release Notes](#).

Procedure

- 1 Use a supported browser to navigate to the Web user interface of the vRealize Log Insight worker.
The URL format is `https://log_insight-host/`, where `log_insight-host` is the IP address or host name of the vRealize Log Insight worker virtual appliance.
The initial configuration wizard opens.
- 2 Click **Join Existing Deployment**.
- 3 Enter the IP address or host name of the vRealize Log Insight master and click **Go**.
The worker sends a request to the vRealize Log Insight master to join the existing deployment.
- 4 Click the **Click here to access the Cluster Management page** link.
- 5 Log in as an administrator.
The Cluster page loads.
- 6 Click **Allow**.
The worker joins the existing deployment and vRealize Log Insight begins to operate in a cluster.

What to do next

- To add another worker, deploy a new vRealize Log Insight instance and add it to the cluster using the startup wizard.
- Repeat the procedure to add a minimum of two vRealize Log Insight worker nodes.

The Customer Experience Improvement Program

3

This product participates in VMware's Customer Experience Improvement Program ("CEIP").

Details regarding the data collected through CEIP and the purposes for which it is used by VMware are set forth at the Trust & Assurance Center at <http://www.vmware.com/trustvmware/ceip.html>. To join or leave the CEIP for this product, please see "Join or Leave the VMware Customer Experience Improvement Program" in *Administering vRealize Log Insight*.