

VMware Horizon Client for Mac User Guide

SEP 2019

VMware Horizon Client for Mac 5.2



vmware®

You can find the most up-to-date technical documentation on the VMware website at:

<https://docs.vmware.com/>

If you have comments about this documentation, submit your feedback to

docfeedback@vmware.com

VMware, Inc.
3401 Hillview Ave.
Palo Alto, CA 94304
www.vmware.com

Copyright © 2010-2019 VMware, Inc. All rights reserved. [Copyright and trademark information.](#)

Contents

VMware Horizon Client for Mac User Guide 5

1 How Do I Log In? 6

2 Connecting to Remote Desktops and Published Applications 7

- Set the Certificate Checking Mode 7
- Allowing Access to macOS Accessibility Features 8
- Configure Horizon Client to Select a Smart Card Certificate 8
- Connect to a Remote Desktop or Published Application 9
- Connecting to a Server When Horizon Client Starts 11
- Hide the VMware Horizon Client Window 11
- Add Horizon Client to the Dock 12
- Autoconnect to a Remote Desktop 12
- Searching for Remote Desktops and Published Applications 13
- Switch Remote Desktops or Published Applications 13
- Open a Recent Remote Desktop or Published Application 14
- Using a Touch Bar with Server, Desktop, and Application Connections 15
- Configure Horizon Client to Forget the Server User Name and Domain 15
- Log Off or Disconnect 15
- Disconnecting From a Server 17

3 Using Remote Desktops and Published Applications 18

- Share Access to Local Folders and Drives with Client Drive Redirection 18
- Clicking URL Links That Open Outside of Horizon Client 21
- Using a Touch Bar with Remote Desktops and Published Applications 22
- Copying and Pasting Text and Images 22
- Dragging and Dropping 23
 - Dragging Text and Images 23
 - Dragging Files and Folders 24
 - Tips for Using the Drag and Drop Feature 24
- Using Published Applications 25
 - Saving Documents in a Published Application 26
 - Use a Local IME with Published Applications 26
 - Configure Reconnect Behavior for Published Applications 27
 - Enable Multi-Session Mode for Published Applications 27
 - Run Published Applications from the Applications Folder 28
- Using the Session Collaboration Feature 29
 - Invite a User to Join a Remote Desktop Session 29

Manage a Collaborative Session	31
Join a Collaborative Session	31
Modify the Horizon Client Shortcuts for Windows Actions	32
4 Using Server, Remote Desktop, and Published Application Shortcuts	34
Reordering Shortcuts	34
Dragging Shortcuts and URIs	34
Select a Favorite Remote Desktop or Published Application	35
Removing a Server Shortcut from the Home Window	36
5 Using External Devices	37
Printing From a Remote Desktop or Published Application	37
Enabling Virtual Printing in Horizon Client	37
Set Printing Preferences for the Virtual Printing Feature	38
Using USB Printers	39
Use USB Redirection to Connect USB Devices	39
USB Redirection Limitations	42
Create Keyboard Shortcut Mappings	42
Considerations for Mapping Operating System Keyboard Shortcuts	44
Modify the Horizon Client Mouse Shortcut Mappings	44
Monitors and Screen Resolution	45
Using Full-Screen Mode with Multiple Monitors	45
Using Remote Desktops with Split View	46
Using a High-Resolution Mac with Retina Display	46
Using DPI Synchronization	46
Select Specific Monitors to Display a Remote Desktop	47
Select Specific Monitors to Display Published Applications	48
Using Exclusive Mode	48
Customize the Display Resolution and Display Scaling for a Remote Desktop	49
Using the Real-Time Audio-Video Feature for Webcams and Microphones	49
When You Can Use a Webcam with the Real-Time Audio-Video Feature	50
Select a Default Microphone on the Mac Client	50
Allowing Access to Webcams and Microphones	51
6 Upgrade Horizon Client Online	52
7 Troubleshooting Horizon Client	53
Restart a Remote Desktop	53
Reset Remote Desktops or Published Applications	53
Uninstalling Horizon Client	54
Connecting to a Server in Workspace ONE Mode	54

VMware Horizon Client for Mac User Guide

This document, *VMware Horizon Client for Mac User Guide*, explains how to use VMware Horizon[®] Client[™] for Mac to connect to and use remote desktops and published applications.

Horizon Client communicates with a server, which acts as a broker between the client device and remote desktops and published applications. You enter credentials into Horizon Client, the server authenticates your credentials, and then the server finds the remote desktops and published applications that you are entitled to use.

For information about the software installed on your remote desktops, contact your system administrator.

This document assumes that Horizon Client for Mac is already installed and configured on your Mac. For information about installing and configuring Horizon Client for Mac, see the *VMware Horizon Client for Mac Installation and Setup Guide* document.

How Do I Log In?

Before you can log in and connect to a remote desktop or published application, a system administrator at your company must set up your user account. If your system administrator has not set up your user account, you cannot use Horizon Client or HTML Access.

If Horizon Client prompts you for a server name and domain name, your system administrator must tell you the server name to type and the domain to select. At some companies, Horizon Client connects to the correct server and selects the correct domain automatically.

If you do not know your user name or password or how to reset your password, contact the system administrator at your company.

When you are ready to log in and get started, see [Connect to a Remote Desktop or Published Application](#).

Connecting to Remote Desktops and Published Applications

2

Horizon Client makes it easy to work on remote desktops and published applications from your local client device, giving you on-the-go access from any location.

This chapter includes the following topics:

- [Set the Certificate Checking Mode](#)
- [Allowing Access to macOS Accessibility Features](#)
- [Configure Horizon Client to Select a Smart Card Certificate](#)
- [Connect to a Remote Desktop or Published Application](#)
- [Connecting to a Server When Horizon Client Starts](#)
- [Hide the VMware Horizon Client Window](#)
- [Add Horizon Client to the Dock](#)
- [Autoconnect to a Remote Desktop](#)
- [Searching for Remote Desktops and Published Applications](#)
- [Switch Remote Desktops or Published Applications](#)
- [Open a Recent Remote Desktop or Published Application](#)
- [Using a Touch Bar with Server, Desktop, and Application Connections](#)
- [Configure Horizon Client to Forget the Server User Name and Domain](#)
- [Log Off or Disconnect](#)
- [Disconnecting From a Server](#)

Set the Certificate Checking Mode

Server certificate checking occurs for connections between Horizon Client and a server. A certificate is a digital form of identification, similar to a passport or a driver's license. Your system administrator might ask you to set the certificate checking mode in Horizon Client to make sure that you can successfully connect to a server.

At some companies, an administrator might set the certificate checking mode and prevent you from changing it in Horizon Client.

Procedure

- 1 In the **Applications** folder, double-click **VMware Horizon Client**.
- 2 Select **VMware Horizon Client > Preferences** from the menu bar.
- 3 Select the certificate checking mode.

Option	Description
Never connect to untrusted servers	This setting means that you cannot connect to the server if any of the certificate checks fail. An error message lists the checks that failed.
Warn before connecting to untrusted servers	This setting means that you can click Continue to ignore the warning if a certificate check fails because the server uses a self-signed certificate. For self-signed certificates, the certificate name is not required to match the server name that you entered in Horizon Client. You can also receive a warning if the certificate has expired.
Do not verify server identity certificates	This setting means that no certificate checking occurs.

- 4 (Optional) If your environment includes an SSL proxy server, select the **Allow connection via an SSL Proxy** check box.

This setting allows certificate checking for remote desktop and published application connections through an SSL proxy server. You cannot enable this setting if you select **Do not verify server identity certificates**.

- 5 To save your changes, click **OK**.

What to do next

If you receive a certificate error after setting the certificate checking mode, contact your system administrator.

Allowing Access to macOS Accessibility Features

If the client system is running macOS Mojave (10.14), you must grant Horizon Client access to the system's accessibility features for optimal performance of the keyboard and mouse inside remote desktops and published applications.

When you first start Horizon Client on a macOS Mojave (10.14) client system, Horizon Client prompts you to grant access to the system's accessibility features. If you do not grant access at that time, you can grant access later by going to System Preferences, selecting **Security & Privacy**, clicking the **Privacy** tab, and selecting **Accessibility**.

Configure Horizon Client to Select a Smart Card Certificate

You can configure a Horizon Client setting to select a local certificate, or the certificate on a smart card, when you connect to a server. If you do not configure this setting, you must manually select a certificate.

Prerequisites

For your setting to take effect, a Horizon administrator must configure smart card authentication on the server and only one certificate must be available on your client system or smart card.

If you have multiple certificates, Horizon Client always prompts you to select a certificate, regardless of how you configure this setting.

Procedure

- 1 In the **Applications** folder, double-click **VMware Horizon Client**.
- 2 Select **VMware Horizon Client > Preferences** from the menu bar.
- 3 Click **General** in the Preferences dialog box.
- 4 Select **Automatically select certificate**.
- 5 Close the Preferences dialog box.

Your changes take effect when the dialog box is closed.

Connect to a Remote Desktop or Published Application

To connect to a remote desktop or published application, you must provide the name of a server and supply credentials for your user account.

Prerequisites

Obtain the following information from your system administrator:

- Instructions about whether to turn on a VPN (virtual private network) connection.
- Server name to use for connecting to the server.
- If the port is not 443, the port number to use for connecting to the server.
- Credentials for logging in, such as an Active Directory user name and password, RSA SecurID user name and passcode, RADIUS authentication user name and passcode, or smart card personal identification number (PIN).
- Domain name for logging in.
- Instructions about whether you can use Touch ID authentication.

If your administrator instructs you to configure the certificate checking mode, see [Set the Certificate Checking Mode](#).

If you use smart card authentication, you can configure Horizon Client to use a local certificate automatically, or to use the certificate on your smart card. See [Configure Horizon Client to Select a Smart Card Certificate](#).

Procedure

- 1 If a VPN connection is required, turn on the VPN.

- 2 In the **Applications** folder, double-click **VMware Horizon Client**.
- 3 Click **Continue** to start remote desktop USB and printing services, or click **Cancel** to use Horizon Client without remote desktop USB and printing services.

If you click **Continue**, you must provide system credentials. If you click **Cancel**, you can enable remote desktop USB and printing services later.

Note The prompt to start remote desktop USB and printing services appears the first time you start Horizon Client. It does not appear again, regardless of whether you click **Cancel** or **Continue**.

- 4 Connect to a server.

Option	Description
Connect to a new server	Click the New Server icon on the Horizon Client Home window, enter the server name and port number (if necessary) as instructed by your system administrator, and click Connect . An example of using a non-default port is <code>view.company.com:1443</code> .
Connect to an existing server	Double-click the server shortcut on the Horizon Client Home window.

- 5 If you are prompted for RSA SecurID credentials or RADIUS authentication credentials, enter the user name and passcode and click **Login**.
- 6 If you are prompted for a user name and password, supply Active Directory credentials.
 - a Type the user name and password as instructed by your system administrator.
 - b Select a domain as instructed by your system administrator.

If the **Domain** drop-down menu is hidden, you must type the user name as *username@domain* or *domain\username*.
 - c (Optional) Select the **Remember this password** check box if this feature is enabled and if the server certificate can be fully verified.
 - d (Optional) Select the **Enable Touch ID** check box to enable Touch ID authentication.

If Touch ID is enabled and you are logging in for the first time, your Active Directory credentials are stored securely on your Mac for future use.
 - e Click **Login**.

You might see a message that you must confirm before the login dialog box appears.
- 7 If you are prompted for Touch ID authentication, place your finger on the Touch ID sensor.

- 8 (Optional) If multiple display protocols are configured for a remote desktop, select the protocol to use.

VMware Blast provides better battery life and is the best protocol for high-end 3D and mobile device users.

Option	Description
Select a display protocol for a remote desktop	Select the remote desktop name, press Control-click, and select the display protocol from the context menu. Alternatively, you can select Settings from the context menu and select the display protocol from the Connect Via drop-down menu in the Settings dialog box.
Select a display protocol for a published application	Select the published application name, press Control-click, select Settings from the context menu, and select the display protocol from the Preferred protocol drop-down menu in the Settings dialog box.

- 9 Double-click a remote desktop or published application to connect to it.

If you are connecting to a published desktop, and if the published desktop is already set to use a different display protocol, you are prompted to either use the protocol that is set or have the system log you off the remote operating system so that a connection can be made with the protocol that you selected.

Note If you are entitled to only one remote desktop on the server, Horizon Client connects automatically to that remote desktop.

If a Horizon administrator has enabled the client drive redirection feature, the Sharing dialog box might appear. From the Sharing dialog box, you can allow or deny access to files on your local system. For more information, see [Share Access to Local Folders and Drives with Client Drive Redirection](#).

After you connect to a server for the first time, Horizon Client connects to that server automatically the next time you start Horizon Client. To disable this feature, see [Connecting to a Server When Horizon Client Starts](#).

Connecting to a Server When Horizon Client Starts

After you connect to a server for the first time, Horizon Client connects automatically to that server the next time you start Horizon Client.

To disable this feature, select the server shortcut on the Horizon Client Home window, press Control-click, and deselect the **Always connect at launch** setting.

If there are other server shortcuts on the Horizon Client Home window, you can enable the **Always connect at launch** setting for a different server. You can enable the **Always connect at launch** setting for only one server at a time.

Hide the VMware Horizon Client Window

You can hide the VMware Horizon Client window after you open a remote desktop or published application.

Procedure

- ◆ To hide the VMware Horizon Client window after you open a remote desktop or published application, click the **Close** button in the corner of the VMware Horizon Client window.

The VMware Horizon Client icon remains in the Dock.

- ◆ To configure a setting that always hides the VMware Horizon Client window after you open a remote desktop or published application, perform these steps before you connect to a server.
 - a Select **VMware Horizon Client > Preferences** from the menu bar and click **General** in the Preferences dialog box.
 - b Select **Hide client window after desktop/application launched**.
 - c Close the Preferences dialog box.

Your changes take effect when the dialog box is closed.

- ◆ To show the VMware Horizon Client window after it has been hidden, select **Window > Open Selection Window** from the menu bar, or right-click the VMware Horizon Client icon in the Dock and select **Show All Windows**.

Add Horizon Client to the Dock

You can add Horizon Client to the Dock on the Mac client system.

Procedure

- 1 In the **Applications** folder, select **VMware Horizon Client**.
- 2 Drag the **VMware Horizon Client** icon to the Dock.
- 3 To configure the Dock icon to open Horizon Client at login or to show the icon in the Finder, right-click the icon on the Dock, select **Options**, and select the appropriate command from the context menu.

When you quit Horizon Client, the application shortcut remains in the Dock.

Autoconnect to a Remote Desktop

You can configure a server to open a particular remote desktop when you connect to that server. You cannot configure a server to open a published application.

If you are entitled to only one remote desktop on the server, Horizon Client always opens that remote desktop when you connect to the server.

Prerequisites

Obtain credentials for connecting to the server, such as a user name and password, RSA SecurID user name and passcode, RADIUS authentication user name and passcode, or smart card personal identification number (PIN).

Procedure

- 1 On the Horizon Client Home window, double-click the server icon.
- 2 If prompted, supply your credentials.
- 3 Click the **Settings** button (gear icon) in the upper-right corner of the desktop and application selection window.
- 4 Select the remote desktop in the left pane of the Settings dialog box.
- 5 Select **Autoconnect to this desktop**.

Searching for Remote Desktops and Published Applications

After you connect to a server, the available remote desktops and published applications on that server appear in the desktop and application selection window. You can search for a particular remote desktop or published application by typing in the window.

When you begin to type, Horizon Client highlights the first matching remote desktop or published application name. To connect to a highlighted remote desktop or published application, press the Enter key. If you continue to type after the first match is found, Horizon Client continues to search for matching remote desktops and published applications. If Horizon Client finds multiple matching remote desktops or published applications, you can press the Tab key to switch to the next match. If you stop typing for two seconds and then begin to type again, Horizon Client assumes that you are starting a new search.

Switch Remote Desktops or Published Applications

If you are connected to a remote desktop, you can switch to another remote desktop. You can also connect to a published application while you are connected to a remote desktop.

Procedure

- ◆ Select a remote desktop or published application from the same server or from a different server.

Option	Action
Choose a different remote desktop or published application on the same server	<p>Perform one of the following actions:</p> <ul style="list-style-type: none"> ■ To keep the current remote desktop and also connect to another remote desktop, select Window > VMware Horizon Client from the menu bar and double-click the shortcut for the other remote desktop. That remote desktop opens in a new window so that you have multiple remote desktops open. You can switch between remote desktops from the Window menu on the menu bar. ■ To close the current remote desktop and connect to another remote desktop, select Connection > Disconnect from the menu bar and double-click the shortcut for the other remote desktop. ■ To open another published application, double-click the shortcut for the other published application. That published application opens in a new window. You now have multiple published applications open, and you can switch between them by clicking in an application window.
Choose a different remote desktop or published application on a different server	<p>If you are entitled to multiple remote desktops or published applications, so that the desktop and application selection window is open, click the Disconnect from Server button in the left side of the toolbar in the desktop and application selection window and disconnect from the server. If you are entitled to only one remote desktop or published application, and the desktop and application selection window is not open, you can select File > Disconnect from Server from the menu bar and then connect to a different server.</p>

Open a Recent Remote Desktop or Published Application

You can open recent remote desktops and published applications in Horizon Client.

Recent remote desktops and published applications appear in the order in which they were opened. If you are not already connected to the server when you open a recent remote desktop or published application, the server login screen appears and you must provide your credentials.

Prerequisites

To use this feature, you must have previously opened a remote desktop or published application. If you plan to open a recent desktop or published application from the Dock, VMware Horizon Client must be in the Dock. See [Add Horizon Client to the Dock](#).

Procedure

- ◆ To open a remote desktop or published application from the Dock, Ctrl-click **VMware Horizon Client** in the Dock and select the remote desktop or published application from the menu.
- ◆ To open a remote desktop or published application from the **File** menu, start Horizon Client, select **File > Open Recent**, and select the remote desktop or published application from the menu.

Using a Touch Bar with Server, Desktop, and Application Connections

If the Mac has a Touch Bar, you can use the Touch Bar to add a server, disconnect from a server, or connect to a recent remote desktop or published application. This feature requires macOS Sierra (10.12) or later.

Before you connect to a server, you can touch the plus (+) icon to add a server. After you connect to a server, you can touch the **Disconnect** icon to disconnect from the server.

If you previously connected to a remote desktop or published application, its name appears on the Touch Bar before you connect to a server. You can touch the remote desktop or application name to log in to the server and start the remote desktop or published application.

You can add, remove, and reorder the items in the Horizon Client app Touch Bar by selecting **VMware Horizon Client > Customize Touch Bar**.

For information about using the Touch Bar after you connect to a remote desktop or published application, see [Using a Touch Bar with Remote Desktops and Published Applications](#).

Configure Horizon Client to Forget the Server User Name and Domain

By default, Horizon Client stores the user name and domain that you enter when you log in to a server. For increased security, you can configure Horizon Client so that it never remembers the server user name and domain.

Procedure

- 1 Select **VMware Horizon Client > Preferences** from the menu bar.
- 2 Click **General** in the Preferences dialog box.
- 3 Deselect **Remember username and domain**.
- 4 Close the Preferences dialog box.

Your changes take effect when the dialog box is closed.

Log Off or Disconnect

If you disconnect from a remote desktop without logging off, applications in the remote desktop might remain open. You can also disconnect from a server and leave published applications running.

You can log off from a remote desktop even if you do not have the remote desktop open. This feature has the same result as sending Ctrl+Alt+Del to the remote desktop and then clicking **Log Off**.

Note The Windows key combination Ctrl+Alt+Del is not supported in remote desktops. Instead, select **Connection > Send Ctrl-Alt-Del** from the menu bar. Alternatively, press Fn-Control-Option-Delete on an Apple keyboard.

Procedure

- ◆ Disconnect from a remote desktop without logging off.

Option	Action
Disconnect and quit Horizon Client	<ol style="list-style-type: none"> Click the Close button in the corner of the window, or select File > Close from the menu bar. Select VMware Horizon Client > Quit VMware Horizon Client from the menu bar.
Disconnect and remain in Horizon Client	Click the Disconnect button in the toolbar, or select Connection > Disconnect from the menu bar.

Note A Horizon administrator can configure a remote desktop to log off when it is disconnected. In this case, any open applications in the remote desktop are closed.

- ◆ Log off and disconnect from a remote desktop.

Option	Action
From within the remote desktop	Use the Windows Start menu to log off.
From the menu bar	<p>Select Connection > Log Off from the menu bar.</p> <p>If you use this procedure, files that are open on the remote desktop are closed without being saved first.</p>

- ◆ Disconnect from a published application.

Option	Action
Disconnect from the server and leave the published application running	<p>Perform one of the following actions:</p> <ul style="list-style-type: none"> Click the Disconnect from Server button in the left side of the toolbar in the desktop and application selection window. Select File > Disconnect from Server from the menu bar.
Close the published application and disconnect from the server	<ol style="list-style-type: none"> Quit the published application in the usual manner, for example, click the Close button in the corner of the application window. Click the Disconnect from Server button in the left side of the toolbar in the desktop and application selection window, or select File > Disconnect from Server from the menu bar.

- ◆ Log off when you do not have a remote desktop open.

If you use this procedure, files that are open on the remote desktop are closed without first being saved.

Option	Action
From the Home window	<ul style="list-style-type: none">a Double-click the server shortcut and supply credentials.b Select the remote desktop and select Connection > Log Off from the menu bar.
From the desktop and application selection window	Select the remote desktop and select Connection > Log Off from the menu bar.

Disconnecting From a Server

After you have finished using a remote desktop or published application, you can disconnect from the server.

To disconnect from a server, click the **Disconnect from Server** icon in the upper-left corner of the Horizon Client menu bar.

Using Remote Desktops and Published Applications

3

Horizon Client includes additional features to help you use remote desktops and published applications on your local client device.

This chapter includes the following topics:

- [Share Access to Local Folders and Drives with Client Drive Redirection](#)
- [Clicking URL Links That Open Outside of Horizon Client](#)
- [Using a Touch Bar with Remote Desktops and Published Applications](#)
- [Copying and Pasting Text and Images](#)
- [Dragging and Dropping](#)
- [Using Published Applications](#)
- [Using the Session Collaboration Feature](#)
- [Modify the Horizon Client Shortcuts for Windows Actions](#)

Share Access to Local Folders and Drives with Client Drive Redirection

With the client drive redirection feature, you can share folders and drives on the local client system with remote desktops and published applications.

Shared drives can include mapped drives and USB storage devices.

The client drive redirection feature does not support sharing Microsoft OneDrive, Google Drive, and enterprise file storage.

In a Windows remote desktop, shared folders and drives appear in the **This PC** folder or in the **Computer** folder, depending on the Windows operating system version. In a published application, such as Notepad, you can browse to and open a file in a shared folder or drive.

You can turn on the ability to open local files in published applications directly from your local file system. If you select a local file and press Control-click, the **Open With** menu lists the available published applications. You can also open a local file by dragging it into the published application window or Dock icon.

If you set a published application as the default application for files that have a certain file extension, all files on your local file system that have that file extension are registered with the server. You can also turn on the ability to run published applications from the Applications folder.

Note If a filename contains characters that are invalid in the Windows file system, you cannot open the file in a published application. For example, you cannot open a file named test2<.txt in Notepad.

The client drive redirection settings apply to all remote desktops and published applications.

Prerequisites

To share folders and drives with a remote desktop or published application, a Horizon administrator must enable the client drive redirection feature.

Procedure

- 1 Open the Preferences dialog box and display the Sharing panel.

Option	Description
From the desktop and application selection window	Select VMware Horizon Client > Preferences and click Sharing .
From the Sharing dialog box that appears when you connect to a remote desktop or published application	Click the Preferences > Sharing link in the dialog box.
From within a remote desktop operating system	Select VMware Horizon Client > Preferences from the menu bar and click Sharing .

- 2 Configure the client drive redirection settings.

Option	Action
Share a specific folder or drive with remote desktops and published applications	Click the plus (+) button, browse to and select the folder or drive to share, and click Add . Note If a USB device is already connected to a remote desktop or published application with the USB redirection feature, you cannot share a folder on the USB device.
Stop sharing a specific folder or drive	Select the folder or drive in the Folder list and click the minus (-) button.
Give remote desktops and published applications access to files in your home directory	Select the Allow access to <i>home-directory</i> check box.

Option	Action
Share USB storage devices with remote desktops and published applications	<p>Select the Allow access to removable storage check box. The client drive redirection feature shares all USB storage devices inserted in your client system and all FireWire and Thunderbolt-connected external drives automatically. Selecting a specific device to share is not necessary.</p> <hr/> <p>Note USB storage devices already connected to a remote desktop or published application with the USB redirection feature are not shared.</p> <hr/> <p>If this check box is deselected, you can use the USB redirection feature to connect USB storage devices to remote desktops and published applications.</p>
Do not show the Sharing dialog box when you connect to a remote desktop or published application	<p>Select the Do not show dialog when connecting to a desktop or application check box.</p> <p>If this check box is deselected, the Sharing dialog box appears the first time you connect to a remote desktop or published application. For example, if you log in to a server and connect to a remote desktop, you see the Sharing dialog box. If you then connect to another remote desktop or published application, you do not see the dialog box. To see the dialog box again, you must disconnect from the server and log in again.</p>

3 Configure settings for published applications.

- a Click the **Settings** button (gear icon) in the upper-right corner of the desktop and application selector window and select **Applications** in the left pane.
- b To turn on the ability to open local files with published applications from the local file system, select **Open local files in hosted applications**.
- c To turn on the ability to run published applications from the Applications folder on the client system, select **Run hosted applications from your local Applications folder**.

What to do next

Verify that you can see the shared folders from within the remote desktop or published application.

- In a Windows remote desktop, open File Explorer and look in the **This PC** folder, or open Windows Explorer and look in the **Computer** folder, depending on the Windows operating system version.
- In a published application, select **File > Open** or **File > Save As** and navigate to the folder or drive.

The folders and drives that you selected for sharing might use one (or more) of the following naming conventions.

Naming Convention	Example
<i>folder-name on desktop-name</i>	jsmith on JSMITH-W03
<i>folder-name (drive-number:)</i>	jsmith (Z:)
<i>folder-name on desktoptop-name (drive-number:)</i>	jsmith on JSMITH-W03 (Z:)

For some Horizon Agent versions, a redirected folder can have two entrances, such as under **Devices and drives** and **Network locations** in Windows 10, and both entrances can appear at the same time. If all the volume labels (from A: through Z:) are already in use, the redirected folder has only one entrance.

Clicking URL Links That Open Outside of Horizon Client

A Horizon administrator can configure URL links that you click inside a remote desktop or published application to open in the default browser on the local client system. The URL link might be to a Web page, a phone number, an email address, or another type of link. This feature is called URL Content Redirection.

A Horizon administrator can also configure URL links that you click inside a browser or application on the local client system to open in a remote desktop or published application. If Horizon Client is not already open you click the URL link, it starts and prompts you to log in.

A Horizon administrator might set up the URL Content Redirection feature for security purposes. For example, if you are at work and click a link that points to a URL outside your company network, the link might be more safely opened in a published application. An administrator can configure which published application opens the link.

Each company configures its own URL Content Redirection policies. If you have questions about how the URL Content Redirection feature behaves at your company, contact your system administrator.

Responding to URL Content Redirection Prompts

The first time you start Horizon Client and connect to a server on which the URL Content Redirection feature is configured, Horizon Client prompts you to open the VMware Horizon URL Filter application when you click a link for redirection. Click **Open** to allow the URL to be redirected.

Depending on how the URL Content Redirection feature is configured, Horizon Client might display an alert message that asks you to change your default Web browser to VMware Horizon URL Filter. If you see this prompt, click the **Use "VMware Horizon URL Filter"** button to allow VMware Horizon URL Filter to become the default browser. This prompt appears only once, unless you change your default browser after clicking **Use "VMware Horizon URL Filter"**.

Horizon Client might also display an alert message that asks you to select an application when you click a URL. If you see this prompt, you can click **Choose Application** to search for an application on the local client system, or click **Search App Store** to search for and install a new application. If you click **Cancel**, the URL is not opened.

Using URL Content Redirection with Chrome

If the Chrome browser prompts you to enable the VMware Horizon URL Content Redirection Helper extension, click **Enable Extension** to use the URL Content Redirection feature with the Chrome browser. If you click **Remove from Chrome**, the extension is removed and URLs clicked in Chrome are not redirected. You can still install the extension manually from the Chrome Web Store.

The first time a URL is redirected from the Chrome browser on the client system, you are prompted to open the URL in Horizon Client. If you select the **Remember my choice for VMware Horizon Client links** check box (recommended) and then click **Open VMware Horizon Client**, this prompt does not appear again.

Using a Touch Bar with Remote Desktops and Published Applications

You can use a Touch Bar to interact with remote desktops and published applications. This feature requires macOS Sierra (10.12) or later.

After you connect to a remote desktop, you can use icons on the Touch Bar to perform the following tasks.

- Disconnect, log out, restart or reset, and send Ctrl+Alt+Delete to the remote desktop.
- Enter or exit full-screen mode.
- Bring the desktop and application selection window to the foreground.
- View a list of all the currently open remote desktops and published applications.
- Switch to another open remote desktop or published application.

You can add, remove, and reorder the items in the Horizon Client app Touch Bar by selecting **VMware Horizon Client > Customize Touch Bar**.

Note The log out, reset, and restart features are available only if a Horizon administrator has enabled them. If the remote desktop is in exclusive mode, you cannot use the Touch Bar to enter or exit full-screen mode or bring the desktop and application selection window to the foreground.

After you connect to a published application, the following icons appear on the Touch Bar.



From left to right, you can use these icons to perform the following tasks:

- Display a list of function keys.
- View the list of open windows for the current published application. You can click a window title to switch to that window.
- Zoom (toggles between maximize and restore).
- Hide all windows of the current published application.
- Minimize the current published application window.
- Bring the application selection window to the foreground.
- View a list of all currently open remote desktops and published applications. You can click the remote desktop or published application to bring it to the foreground.

Copying and Pasting Text and Images

By default, you can copy and paste from the client system to a remote desktop or published application. You can also copy and paste from a remote desktop or published application to the client system, or

between two remote desktops or published applications, if a Horizon administrator enables these features.

You can copy and paste text and images, including Rich Text Format (RTF).

For example, to copy text on the client system, select the text and press Command-C. To paste the text into a remote desktop, press Command-V in the remote desktop.

The copy and paste feature has the following limitations.

- You cannot copy and paste files between a remote desktop and the file system on the local client computer.
- If you are copying formatted text, some of the data is text and some of the data is formatting information. If you copy a large amount of formatted text or text and an image, when you attempt to paste the text and image, you might see some or all the plain text, but no formatting or image. This problem occurs because the three types of data are sometimes stored separately. For example, depending on the type of document, images might be stored as images or as RTF data.
- If the text and RTF data together use less than the maximum clipboard size, the formatted text is pasted. Often, the RTF data cannot be truncated, so that if the text and formatting use more than the maximum clipboard size amount, the RTF data is discarded, and the plain text is pasted.
- If you are unable to paste all the formatted text and images that you selected in one operation, you might need to copy and paste smaller amounts in each operation.

Dragging and Dropping

The drag and drop feature works differently depending on how a Horizon administrator configures the feature.

For example, you might be able to drag and drop files, folders, text, rich text, and images between the client system and remote desktops and published applications, or you might be able to drag and drop only text, rich text, and images from the client system to an open application in a remote desktop.

Dragging Text and Images

You can drag text and images from the client system to an open application in a remote desktop or a published application. For example, you can drag text from a browser on the client system and drop it into the WordPad application in a remote desktop. Depending on how the drag and drop feature is configured, you might also be able to drag text and images from an open application in a remote desktop or a published application to the client system.

The following data formats are supported.

- Plain Text (NSPasteboardTypeString)
- Rich Text (NSPasteboardTypeRTF)
- Image (kUTTypeImage)

A Horizon administrator can configure drag and drop behavior. A Horizon administrator can also disable this feature.

Dragging Files and Folders

Depending on how a Horizon administrator has configured the drag and drop feature, you might be able to drag and drop files and folders between the Mac client system and remote desktops and published applications. You can drag and drop multiple files and folders at the same time. A progress bar shows the status of the drag and drop operation.

If you drag a file or folder between the client system and a remote desktop, the file or folder appears in the file system on the target system. If you drag a file and drop it into an open application, such as Notepad, the text appears in the application. If you drag a file into a new email message, the file becomes an attachment to the email message.

By default, dragging and dropping from the client system to remote desktops and published applications is enabled, and dragging and dropping from remote desktops and published applications to the client system is disabled. A Horizon administrator can configure the drag and drop direction.

Tips for Using the Drag and Drop Feature

When using the drag and drop feature, follow these tips.

Note Depending on how a Horizon administrator configures the drag and drop feature, some tips might not apply to your environment.

- You must use the VMware Blast or PCoIP display protocol.
- When a drag and drop operation is in progress, you cannot start a new drag and drop operation until after the first drag and drop operation has finished.
- You cannot drag and drop between remote desktops.
- You cannot drag and drop between published applications.
- If you drag and drop a file or folder between the client system and a remote desktop, the file or folder appears in the file system on the target system. If you drag a file and drop it into an open application, such as Notepad, the text appears in the application. If you drag a file into a new email message, the file becomes an attachment to the email message.
- You can drag and drop multiple files and folders at the same time. A progress bar shows the status of the drag and drop operation.
- By default, dragging and dropping from the client system to remote desktops and published applications is enabled, and dragging and dropping from remote desktops and published applications to the client system is disabled.
- When you drag a file from the client system and drop it into a published application, you cannot click **Save as** to copy the file back to a different file on the client system. You can click **Save** to copy the file back to the same file on the client system.

- If you drag a file from the client system to an application in a remote desktop, the file is copied to the remote desktop and you can only edit the copy of the file.
- If you are dragging formatted text, some of the data is text and some of the data is formatting information. If you drag a large amount of formatted text, or text and an image, when you attempt to drop the text and image, you might see some or all the plain text, but no formatting or image. This problem occurs because the three types of data are sometimes stored separately. For example, depending on the type of document, images might be stored as images or as RTF data.
- If you are dragging both plain text and RTF data, and the total data size is less than the drag and drop size threshold, the formatted text is copied. Because RTF data cannot be truncated, if the total data size is greater than the drag and drop size threshold, the RTF data is discarded and only the plain text (or part of the plain text) is copied.
- If you are unable to drag all the formatted text and images in one operation, you might need to drag smaller amounts in each operation.

Using Published Applications

You can use many Mac functions with published applications.

- When you run a published application, its icon appears in the Dock. You can maximize a minimized published application by clicking its icon in the Dock.
- You can keep, open, and quit a published application from its context menu in the Dock. If you select **Keep in Dock**, the published application icon remains in the Dock, even after you close all application windows.
- You can open a published application by clicking its icon in the Dock.
- You can open local files in published applications and run published applications from the Applications folder on the client system. To enable these features, see [Share Access to Local Folders and Drives with Client Drive Redirection](#).
- Flashing Windows taskbar items are forwarded to Horizon Client. For example, if the published application is an IM client and you receive a new message, a flashing red dot appears on the IM client icon in the Dock.
- You can start voice dictation, minimize, and zoom a published application from the menu bar.
- You can use the Exposé feature to see open published applications, and you can press Command-Tab to switch between open published applications.
- You can use standard Mac keyboard shortcuts to interact with published applications. For example, you can press Command-W to close an individual application window and Command-S to save the current file. You can also use standard Mac keyboard shortcuts to copy, cut, and paste text between applications on the Mac and published applications. You can customize keyboard shortcut mappings. See [Create Keyboard Shortcut Mappings](#).

- If a published application creates a Windows System Tray item, that item appears in the notification area on the menu bar on the Mac client system. You can interact with this item from the notification area on the Mac in the same way that you interact with it from the System Tray on a Windows system.

Note When you reclick a redirected System Tray item in the notification area on the Mac, the context menu does not disappear.

Saving Documents in a Published Application

With certain published applications, such as Microsoft Word or WordPad, you can create and save documents. Where these documents are saved depends on your company's network environment. For example, your documents might be saved to a home share mounted on your local computer.

Contact your system administrator to find out where documents created in published applications are saved in your environment.

Use a Local IME with Published Applications

If you use non-English keyboards and locales, you can use an IME (input method editor) that is installed in the local client system to send non-English characters to a published application.

You can use the **Input** menu in the menu bar on the Mac or keyboard shortcuts to switch to a different IME. You do not need to install an IME on the server that hosts the published application.

Note On a Mac, an IME is called an input source.

When this feature is enabled, the local IME is used. If an IME is installed and configured on the server that hosts the published application, that remote IME is ignored.

Prerequisites

- Verify that one or more IMEs are installed in the client system.

Procedure

- 1 In the Horizon Client desktop and application selection window, Control-click a published application and select **Settings**.
- 2 In the Remote Applications pane, select the **Extend the local IME to hosted applications** check box.
- 3 Use the local IME as you might use it with locally installed applications.

The **Input** menu appears in the menu bar on the Mac client. When you use a published application, you can switch to a different language or IME by using the **Input** menu or keyboard shortcuts. Key combinations that perform certain actions, such as Command-C to copy and Command-V to paste, work correctly.

Configure Reconnect Behavior for Published Applications

If you disconnect from a server without closing a published application, Horizon Client prompts you to reopen that published application the next time you connect to the server. You can change this behavior by modifying the Reconnect Behavior setting in Horizon Client.

Prerequisites

Obtain credentials for connecting to the server, such as a user name and password, RSA SecurID user name and passcode, RADIUS authentication user name and passcode, or smart card personal identification number (PIN).

Procedure

- 1 On the Horizon Client **Home** window, double-click the server icon.
- 2 If prompted, supply your credentials.
- 3 Click the **Settings** button (gear icon) in the upper-right corner of the desktop and application selection window.
- 4 Select **Applications** in the left pane of the Settings dialog box.
- 5 Select an application reconnect behavior option.

These options determine how Horizon Client behaves when a user connects to the server and published applications are still running.

Option	Description
Ask to reconnect to open applications	Horizon Client shows the message You have one or more remote applications running. Would you like to open them now? You can respond by clicking Reconnect to Applications or Not Now . You can also select the Don't show this message again check box to suppress the message in the future. This setting is enabled by default.
Reconnect automatically to open applications	Horizon Client immediately reopens any running published applications.
Do not ask to reconnect and do not automatically reconnect	Horizon Client does not prompt you to reopen running published applications, nor does it reopen running published applications. This setting has the same effect as the Don't show this message again check box.

The new setting takes effect the next time you connect to the server.

Enable Multi-Session Mode for Published Applications

When multi-session mode is enabled for a published application, you can use multiple sessions of the same published application when you log on to the server from different client devices.

For example, if you open a published application in multi-session mode on client A, and then open the same published application on client B, the published application remains open on client A and a new session of the published application opens on client B. By comparison, when multi-session mode is disabled (single-session mode), the published application session on client A disconnects and reconnects on client B.

The multi-session mode feature has the following limitations.

- Multi-session mode does not work for applications that do not support multiple instances, such as Skype for Business.
- If the application session is disconnected while you are using a published application in multi-session mode, you are logged off automatically and any unsaved data is lost.
- If the Mac client system goes to sleep while you are connected to a published application in multi-session mode, the published application session is not resumed.
- You cannot use the same published application in both single-session mode and multi-session mode. For example, if you are using a published application in single-session mode, you must quit the application before you can change it to multi-session mode.

Prerequisites

A Horizon administrator must enable multi-session mode for the published application. You cannot enable or change the multi-session mode for a published application unless a Horizon administrator allows it.

Procedure

- 1 Connect to a server.
- 2 Click the **Settings** button (gear icon) in the upper-right corner of the desktop and application selector window and select **Multi-Launch**.

If no published applications are available to use in multi-session mode, the **Multi-Launch** setting does not appear.

- 3 Select the published applications that you want to use in multi-session mode.

If a Horizon administrator has enforced multi-session mode for a published application, you cannot change this setting.

Run Published Applications from the Applications Folder

You can configure Horizon Client so that published applications appear in the Applications folder on the client system.

If a Horizon administrator has configured one or more category folders for a published application, you can optionally configure Horizon Client to show the published application in those folders in the Applications folder on the client system.

Prerequisites

Connect to a server.

Procedure

- 1 Click the **Settings** button (gear icon) in the upper-right corner of the desktop and application selector window and select **Applications** in the left pane.
- 2 To turn on the ability to run published applications from the Applications folder on the client system, select **Run hosted applications from your local Applications folder**.
- 3 (Optional) To show the category folders that are configured for published applications in the Applications folder, select **Allow automatic shortcuts from the server**.

Using the Session Collaboration Feature

You can use the Session Collaboration feature to invite other users to join an existing remote desktop session.

Invite a User to Join a Remote Desktop Session

When the Session Collaboration feature is enabled for a remote desktop, you can invite other users to join an existing remote desktop session.

By default, you can send Session Collaboration invitations by email, in an instant message (Windows remote desktops only), or by copying a link to the clipboard and forwarding the link to users. To use the email invitation method, an email application must be installed. To use the IM invitation method for a Windows remote desktop, Skype for Business must be installed and configured. You can invite only users that belong to a domain that the server allows for authentication. You can invite up to five users by default.

For information about how the Session Collaboration feature behaves at your company, contact your system administrator.

The Session Collaboration feature has the following limitations.

- If you have multiple monitors, only the primary monitor is shown to session collaborators.
- You must select the VMware Blast display protocol when you create a remote desktop session. The Session Collaboration feature does not support PCoIP or RDP sessions.
- Anonymous collaboration is not supported. Session collaborators must be identifiable through Horizon-supported authentication mechanisms.
- Session collaborators must have Horizon Client 4.7 or later for Windows, Mac, or Linux installed, or they must use HTML Access 4.7 or later.
- If a session collaborator has an unsupported version of Horizon Client, an error message appears when the user clicks a collaboration link.
- You cannot use the Session Collaboration feature to share published application sessions.

Prerequisites

To invite users to join a remote desktop session, a Horizon administrator must enable the Session Collaboration feature.

Procedure

- 1 Connect to a remote desktop for which the Session Collaboration feature is enabled.

You must use the VMware Blast display protocol.

- 2 In the system tray in the remote desktop, click the **VMware Horizon Collaboration** icon, for example,



The collaboration icon might look different, depending on the operating system version.

- 3 When the VMware Horizon Collaboration dialog box opens, enter the user name (for example, **testuser** or **domain\testuser**) or the email address of the user that you want to join the remote desktop session.

The first time you enter the user name or email address of a particular user, you must click **Look up "user"**, enter a comma (,), or press the **Enter** key to validate the user. For Windows remote desktops, the Session Collaboration feature remembers the user the next time you enter the user's user name or email address.

You can invite up to five users by default. A Horizon administrator can change the maximum number of users that you can invite.

- 4 Select an invitation method.

Not all invitation methods might be available.

Option	Action
Email	Copies the collaboration invitation to the clipboard and opens a new email message in the default email application. An email application must be installed to use this invitation method.
IM	(Windows remote desktops only) Copies the collaboration invitation to the clipboard and opens a new window in Skype for Business. Press Ctrl+V to paste the link into the Skype for Business window. Skype for Business must be installed and configured to use this invitation method.
Copy Link	Copies the collaboration invitation to the clipboard. You must manually open another application, such as Notepad, and press Ctrl+V to paste the invitation.

After you send an invitation, the VMware Horizon Collaboration icon also appears on the desktop and the Session Collaboration user interface turns into a dashboard that shows the current state of the collaboration session and enables you to take certain actions.

When a session collaborator accepts your invitation to join a Windows remote desktop session, the Session Collaboration feature notifies you and a red dot appears on the VMware Horizon Collaboration icon in the system tray. When a session collaborator accepts your invitation to join a Linux remote desktop session, a notification appears in the primary session desktop.

What to do next

Manage the collaborative session in the VMware Horizon Collaboration dialog box. See [Manage a Collaborative Session](#).

Manage a Collaborative Session

After you send a session collaboration invitation, the Session Collaboration user interface turns into a dashboard that shows the current state of the collaborative session and enables you to take certain actions.

A Horizon administrator can configure a remote desktop to prevent the hand off of control to a session collaborator.

Prerequisites

Start a collaborative session. See [Invite a User to Join a Remote Desktop Session](#).

Procedure

- 1 In the remote desktop, click the **VMware Horizon Collaboration** icon in the system tray.
The names of all session collaborators appear in the Name column and their status appears in the Status column.
- 2 Use the VMware Horizon Session Collaboration dashboard to manage the collaborative session.

Option	Action
Revoke an invitation or remove a collaborator	Click Remove in the Status column.
Hand off control to a session collaborator	After the session collaborator joins the session, toggle the switch in the Control column to On . To resume control of the session, double-click or press any key. The session collaborator can also give back control by toggling the switch in the Control column to Off , or by clicking the Give Back Control button.
Add a collaborator	Click Add Collaborators .
End the collaborative session	Click End Collaboration . All active collaborators are disconnected. In Windows remote desktops, you can also end the collaborative session by clicking the Stop button next to the VMware Horizon Session Collaboration icon. The Stop button is not available in Linux remote desktops.

Join a Collaborative Session

To join a collaborative session, you can click the link in a collaboration invitation. The link might be in an email or instant message, or in a document that the session owner forwards to you. Alternatively, you can log in to the server and double-click the icon for the collaborative session in the remote desktop and application selector window.

This procedure describes how to join a collaborative session from a collaboration invitation.

You cannot use the following remote desktop features in a collaborative session.

- USB redirection
- Real-Time Audio-Video (RTAV)
- Multimedia redirection

- Client drive redirection
- Smart card redirection
- Virtual Printing
- Microsoft Lync redirection
- File redirection and Keep in Dock functionality
- Clipboard redirection

You cannot change the remote desktop resolution in a collaborative session.

Prerequisites

To join a collaborative session, you must have Horizon Client 4.7 for Windows, Mac, or Linux installed on the client system, or you must use HTML Access 4.7 or later.

Procedure

- 1 Click the link in the collaboration invitation.

Horizon Client opens on the client system.

- 2 Enter your credentials to log in to Horizon Client.

After you are successfully authenticated, the collaborative session begins and you can see the session owner's remote desktop. If the session owner transfers mouse and keyboard control to you, you can use the remote desktop.

- 3 To return mouse and keyboard control to the session owner, click the **VMware Horizon Collaboration** icon in the system tray and toggle the switch in the Control column to **Off**, or click the **Give Back Control** button.
- 4 To leave the collaborative session, click **Options > Disconnect**.

Modify the Horizon Client Shortcuts for Windows Actions

Horizon Client includes preconfigured shortcut mappings for common Windows actions, including Toggle Full Screen, Quit, Hide Application, Cycle Through Windows, and Cycle Through Windows in Reverse. It also includes a preconfigured shortcut mapping for Toggle Exclusive Mode. You can enable or disable the default shortcuts. You cannot create shortcuts or delete the default shortcuts.

Procedure

- 1 Select **VMware Horizon Client > Preferences** and click **Keyboard & Mouse**.
- 2 Select the **Horizon Shortcuts** tab.

3 Modify the default shortcuts.

Option	Action
Enable a shortcut	Select the On check box next to the shortcut. When you enable a shortcut, Horizon Client does not send the shortcut to the remote desktop or published application.
Disable a shortcut	Deselect the On check box next to the shortcut. When you disable a shortcut, Horizon Client sends the shortcut to the remote desktop or published application. Note The behavior of the shortcut on the remote desktop or published application can be unpredictable.
Restore the default settings	Click Restore Defaults . Any changes that you made are deleted and the default settings are restored.

4 Close the Preferences dialog box.

Your changes take effect immediately. You do not need to restart open remote desktops or published applications to make the changes take effect.

Using Server, Remote Desktop, and Published Application Shortcuts

4

You can reorder and drag and drop server, remote desktop, and published application shortcuts. You can also select favorite remote desktop and published application shortcuts and remove server shortcuts from the Horizon Client Home window.

This chapter includes the following topics:

- [Reordering Shortcuts](#)
- [Dragging Shortcuts and URIs](#)
- [Select a Favorite Remote Desktop or Published Application](#)
- [Removing a Server Shortcut from the Home Window](#)

Reordering Shortcuts

You can reorder server, remote desktop, and published application shortcuts.

Each time you connect to a server, Horizon Client saves a server shortcut to the Home window. You can reorder these server shortcuts by selecting a shortcut and dragging it to a new position on the Home window.

After you connect to a server, the available remote desktops and published applications on that server appear in the desktop and application selection window. Remote desktop shortcuts appear first, followed by published application shortcuts. Remote desktop shortcuts and published application shortcuts are arranged alphabetically and cannot be rearranged.

When you are in the Favorites view (you clicked the **Favorites** button in the upper-right corner of the desktop and application selection window), you can reorder remote desktop and published application shortcuts by selecting a shortcut and dragging it to a new position on the window.

Dragging Shortcuts and URIs

You can drag server, remote desktop, and published application shortcuts and Uniform Resource Identifiers (URIs).

You can drag a server shortcut from the Horizon Client Home window into another app, such as Notes. The server shortcut appears as a URI in the other app, for example, `vmware-view://server-address`. You can also drag a server address or URI from another app into the Home window.

After you connect to a server, you can drag a remote desktop or published application shortcut from the Horizon Client desktop and application selection window into another app, such as Notes. The shortcut appears as a URI in the other app, for example, `vmware-view://server-name/item-name`.

If you drag a server, remote desktop, or published application shortcut from Horizon Client into a folder on the Mac, Horizon Client creates a shortcut file in the folder. You can double-click this shortcut file to start Horizon Client and connect to the server, remote desktop, or published application.

Select a Favorite Remote Desktop or Published Application

You can select favorite remote desktops and published applications. Shortcuts for favorite items are identified by a star and appear on the **Favorites** tab. Favorite items are saved after you log off from the server.

Prerequisites

Obtain the credentials for connecting to the server, such as a user name and password or RSA SecurID and passcode.

Procedure

- 1 On the Horizon Client Home window, double-click the server icon.
- 2 If prompted, supply your RSA user name and passcode, your Active Directory user name and password, or both.
- 3 To select or deselect a favorite remote desktop or published application, perform these steps.

Option	Action
Select a favorite	Select the remote desktop or published application shortcut, press Control-click, and select Mark as Favorite from the context menu. A star appears in the upper-right corner of the remote desktop or published application shortcut.
Deselect a favorite	Select the remote desktop or published application shortcut, press Control-click, and deselect Mark as Favorite from the context menu. A star no longer appears in the upper-right corner of the remote desktop or published application shortcut.

- 4 (Optional) To display only favorite remote desktops or published applications, click the **Favorites** button (star icon) in the upper-right corner of the desktop and application selection window.

You can click the **Favorites** button again to display all the available remote desktops and published applications.

Removing a Server Shortcut from the Home Window

After you connect to a server, Horizon Client saves a server shortcut to the Home window.

You can remove a server shortcut by selecting the shortcut and pressing the **Delete** key. Alternatively, you can Control-click or right-click the shortcut on the Horizon Client Home window and select **Delete**.

You cannot remove remote desktop or published application shortcuts that appear after you connect to a server.

Using External Devices

You can use keyboards, displays, microphones, and other external devices with remote desktops and published applications.

This chapter includes the following topics:

- [Printing From a Remote Desktop or Published Application](#)
- [Use USB Redirection to Connect USB Devices](#)
- [Create Keyboard Shortcut Mappings](#)
- [Modify the Horizon Client Mouse Shortcut Mappings](#)
- [Monitors and Screen Resolution](#)
- [Using the Real-Time Audio-Video Feature for Webcams and Microphones](#)

Printing From a Remote Desktop or Published Application

You can print to a network printer or a locally attached printer from a remote desktop or published application.

You can use the Virtual Printing feature or the VMware Integrated Printing feature, depending on which feature is enabled in Horizon Agent.

Enabling Virtual Printing in Horizon Client

When you use the VMware Blast display protocol or the PCoIP display protocol, you can use printers configured for the Mac client from a remote desktop or published application. You do not need to install printer drivers on a remote desktop to use the virtual printing feature.

Note You do not need to enable the VMware Integrated Printing feature. This feature is enabled by default.

You typically enable Virtual Printing the first time you start Horizon Client. Click **Continue** when Horizon Client prompts you to start remote desktop USB and printing services and type your system credentials.

If you do not enable Virtual Printing the first time you start Horizon Client, you can use the **Connection** menu to enable Virtual Printing.

- To enable Virtual Printing before you connect to a remote desktop or published application, select **VMware Horizon Client > Connection > Start Printing Services**. Click **Continue** and type your system credentials.
- To enable Virtual Printing after you connect to a remote desktop or published application, select **VMware Horizon Client > Connection > Start Printing Services**. Click **Continue**, type your system credentials, and reconnect to the remote desktop or published application. If you cancel the reconnection, you can select **Connection > Enable Printing** and Horizon Client prompts you to reconnect again.

When the Virtual Printing feature is enabled, the **Connection** menu displays **Printing Enabled**.

Note If you install Horizon Client on a Mac on which VMware Fusion was previously started, printing services are already enabled when you start Horizon Client. This behavior occurs because VMware Fusion and Horizon Client use some of the same files to implement Virtual Printing.

Set Printing Preferences for the Virtual Printing Feature

You can set printing preferences in a remote desktop for the Virtual Printing feature. With the Virtual Printing feature, you can use network or locally attached printers from a remote desktop without having to install additional printer drivers in the remote desktop. For each printer available through this feature, you can set preferences for data compression, print quality, double-sided printing, color, and other settings.

After a printer is added on the local client computer, Horizon Client adds that printer to the list of available printers in the remote desktop. No further configuration is required. If you have administrator privileges, you can install printer drivers on the remote desktop without creating a conflict with the Virtual Printing component.

Changes to printing preferences are not persistent. Printing preferences revert to the default settings the next time a user connects to a remote desktop.

Important This feature is not available for the following types of printers.

- USB printers that use the USB redirection feature to connect to a virtual USB port in the remote desktop.

You must disconnect the USB printer from the remote desktop to use the Virtual Printing feature with it.
 - The Windows feature for printing to a file.

Selecting the **Print to file** check box in a Print dialog box does not work. Using a printer driver that creates a file does work. For example, you can use a PDF writer to print to a PDF file.
-

Prerequisites

To use Virtual Printing, a Horizon administrator must enable the Virtual Printing feature for the remote desktop.

To determine whether the Virtual Printing feature is installed in a remote desktop, verify that the C:\Program Files\Common Files\ThinPrint folder exists in the remote desktop file system.

Procedure

- 1 In the Windows remote desktop, go to **Control Panel > Hardware and Sound > Devices and Printers**.
- 2 In the **Devices and Printers** window, right-click the virtual printer and select **Printer properties** from the context menu.

In a remote desktop, each virtual printer might appear as *<printer_name>*, *<printer_name>(s<session_ID>)*, or *<printer_name>#.<number>*.
- 3 On the **General** tab, click **Preferences**.
- 4 In the Printing Preferences dialog box, select the different tabs and specify which settings to use.
- 5 To save your changes, click **OK**.

Using USB Printers

A USB printer is a printer that is attached to a USB port on the local client system. You can send print jobs to a USB printer attached to the local client system from a remote desktop.

- You can use the USB redirection feature to attach a USB printer to a virtual USB port in the remote desktop, but only if the required drivers are also installed on the remote desktop.

If you use the USB redirection feature, the printer is no longer logically attached to the physical USB port on the client, and it does not appear in the list of local printers on the local client machine. You can print to the USB printer from the remote desktop, but you cannot print to the USB printer from the local client machine. In the remote desktop, redirected USB printers appear as *<printer_name>*.

For information about how to connect a USB printer, see [Use USB Redirection to Connect USB Devices](#).

- You can alternatively use the Virtual Printing feature or the VMware Integrated Printing feature to send print jobs to a USB printer. You can print to the USB printer from both the remote desktop and the client system, and you do not need to install printer drivers in the remote desktop.

Virtual printers and redirected USB printers can work together without conflict.

Use USB Redirection to Connect USB Devices

With the USB redirection feature, you can use locally attached USB devices, such as thumb flash drives, in a remote desktop or published application.

When you use the USB redirection feature, most USB devices that are attached to the local client system become available from menus in Horizon Client. You use these menus to connect and disconnect the devices.

The types of USB devices that you can redirect depend on how a Horizon administrator has configured the remote desktop or published application.

If you use the client drive redirection feature to share a USB storage device or a folder on a USB storage device, you cannot use the USB redirection feature to redirect the device to a remote desktop or published application because the device is already shared.

You can connect USB devices to a remote desktop or published application either manually or automatically.

Prerequisites

- To use USB devices with a remote desktop or published application, a Horizon administrator must enable the USB redirection feature.
- The first time you attempt to connect a USB device, you must provide the Administrator password. Horizon Client prompts you for the password.

Some components required for USB redirection that Horizon Client installs must be configured, and configuration of these components requires Administrator privileges.

- Become familiar with [USB Redirection Limitations](#).

Procedure

- ◆ Manually connect the USB device to a remote desktop.
 - a The first time you use the USB feature, from the VMware Horizon Client menu bar, click **Connection > USB > Start remote USB services** and provide the Administrator password when prompted.
 - b Connect the USB device to the local client system.
 - c From the VMware Horizon Client menu bar in the remote desktop, click **Connection > USB > Connect to a desktop to list USB devices**.
 - d Connect to a remote desktop to list the connected USB devices and select a USB device.

The device is manually redirected from the local system to the remote desktop.
- ◆ Connect the USB device to a published application.
 - a The first time you use the USB feature, from the VMware Horizon Client menu bar, click **Connection > USB > Start remote USB services** and provide the Administrator password when prompted.
 - b Plug in the USB device.
 - c Open the published application.
 - d Click the **Settings** button (gear icon) in the upper-right corner of the desktop and application selection window.
 - e Select **Applications** in the left pane of the Settings dialog box.
 - f Click **USB** at the top of the right pane of the Settings dialog box.

The available USB devices appear in the left pane.

- g Select a USB device and click **Connect Device**.

If a USB device is already connected to a remote desktop or application, you must disconnect the device from the desktop or application before you can select it.

- h Select a published application and click **Continue**.

You can select any running published application. After you select a published application, you can use the USB device with the published application.

- i After you finish using the published application, open the Settings dialog box again, select **USB**, and select **Disconnect** to release the USB device from the published application.

You can now use the USB device with your local client system, a remote desktop, or another published application.

- ◆ Configure Horizon Client to connect USB devices automatically to a remote desktop when you plug them in to the local system.

Use the autoconnect feature if you plan to connect devices that use MTP drivers, such as Android-based Samsung smart phones and tablets.

- a Before you plug in the USB device, start Horizon Client and connect to the remote desktop.
- b The first time you use the USB feature, from the VMware Horizon Client menu bar, click **Connection > USB > Start remote USB services** and provide the Administrator password when prompted.
- c From the VMware Horizon Client menu bar in the remote desktop, click **Connection > USB > Automatically connect when inserted**.
- d Plug in the USB device.

USB devices that you connect to your local system after you start Horizon Client are redirected to the remote desktop.

- ◆ Configure Horizon Client to connect USB devices automatically to a remote desktop when Horizon Client starts.

- a The first time you use the USB feature, from the VMware Horizon Client menu bar in the remote desktop, click **Connection > USB > Start remote USB services** and provide the Administrator password when prompted.
- b From the VMware Horizon Client menu bar in the remote desktop, click **Connection > USB > Automatically connect at startup**.
- c Plug in the USB device and restart Horizon Client.

USB devices that are connected to the local client system when you start Horizon Client are redirected to the remote desktop.

The USB device appears in the remote desktop or published application. A USB device might take up to 20 seconds to appear in the remote desktop or published application. The first time you connect the device to a remote desktop you might be prompted to install drivers.

If the USB device does not appear in the remote desktop or published application after several minutes, disconnect and reconnect the device to the client computer.

What to do next

If you have problems with USB redirection, see the topic about troubleshooting USB redirection problems in the *Configuring Remote Desktop Features in Horizon 7* document.

USB Redirection Limitations

The USB redirection feature has certain limitations.

- When you access a USB device from a menu in Horizon Client and use the device in a remote desktop, you cannot access the device on the local computer.
- USB devices that do not appear in the menu, but are available in a remote desktop, include human interface devices such as keyboards and pointing devices. The remote desktop and the local computer use these devices at the same time. Interaction with these devices can sometimes be slow because of network latency.
- Large USB disk drives can take several minutes to appear in the remote desktop.
- Some USB devices require specific drivers. If a required driver is not already installed on a remote desktop, you might be prompted to install it when you connect the USB device to the remote desktop.
- If you plan to attach USB devices that use MTP drivers, such as Android-based Samsung smart phones and tablets, configure Horizon Client so that it automatically connects USB devices to the remote desktop. Otherwise, if you try to manually redirect the USB device by using a menu item, the device is not redirected unless you unplug the device and then plug it in again.
- Webcams are not supported for USB redirection.
- The redirection of USB audio devices depends on the state of the network and is not reliable. Some devices require a high data throughput even when they are idle. Audio input and output devices work well with the Real-Time Audio-Video feature. You do not need to use USB redirection for those devices.
- You cannot format a redirected USB drive in a published desktop unless you connect as an administrator user.

Note Do not redirect USB Ethernet devices to a remote desktop. If the local system is connected, the remote desktop can connect to the network. If you set the remote desktop to autoconnect USB devices, you can add an exception to exclude the Ethernet connection. For information about configuring USB redirection, see the *VMware Horizon Client for Mac Installation and Setup Guide* document.

Create Keyboard Shortcut Mappings

You can customize how remote desktops and published applications interpret Apple keyboard shortcuts by creating keyboard shortcut mappings.

When you create a keyboard shortcut mapping, you map an Apple keyboard shortcut to a Windows keyboard shortcut. A keyboard shortcut consists of one or more key modifiers, such as Control and Shift, and a key code. A key code can be any key on your keyboard, except for a modifier key. When you press a mapped keyboard shortcut on your Apple keyboard, the corresponding Windows keyboard shortcut or action occurs in the remote desktop or application.

If you attempt to map an operating system keyboard shortcut, the results can be unpredictable. For more information, see [Considerations for Mapping Operating System Keyboard Shortcuts](#).

Procedure

- 1 Select **VMware Horizon Client > Preferences** and click **Keyboard & Mouse**.
- 2 Select the **Key Mappings** tab.
- 3 Configure the keyboard shortcut mappings.

Option	Action
Delete a keyboard shortcut mapping	Select the mapping to delete and click the minus (-) button.
Add a keyboard shortcut mapping	<ol style="list-style-type: none"> a Click the plus (+) button. b Specify the Apple keyboard shortcut sequence by clicking one or more keyboard modifiers and typing a key code in the text box. You can also select a key from the drop-down menu. The From: field shows the keyboard shortcut that you created. c Specify the corresponding Windows keyboard shortcut sequence by clicking one or more keyboard modifiers and typing a key code in the text box. You can also select a key from the drop-down menu. The To: field shows the keyboard shortcut that you created. d To save your changes, click OK. <p>The keyboard shortcut mapping is enabled by default (the On check box next to the keyboard shortcut mapping is selected).</p>
Modify a keyboard shortcut mapping	<p>Double-click the mapping and make your changes.</p> <ul style="list-style-type: none"> ■ To modify the Apple keyboard shortcut sequence, click one or more keyboard modifiers and type a key code in the text box. You can also select a key from the drop-down menu. ■ To modify the corresponding Windows keyboard shortcut sequence, click one or more keyboard modifiers and type a key code in the text box. You can also select a key from the drop-down menu. <p>To save your changes, click OK.</p>
Disable a keyboard shortcut mapping	Deselect the On check box next to the keyboard shortcut mapping. When you disable a keyboard shortcut mapping, Horizon Client does not send the Apple keyboard shortcut to the remote desktop or application.
Enable or disable language-specific key mappings	Select or deselect the Enable Language Specific Key Mappings check box. The check box is selected by default.
Restore the default mappings	Click Restore Defaults . Any changes that you made to the default keyboard shortcut mappings are deleted and the default mappings are restored.

4 Close the Preferences dialog box.

Your keyboard shortcut mapping changes take effect immediately. You do not need to restart open remote desktops or published applications to make the changes take effect.

Considerations for Mapping Operating System Keyboard Shortcuts

Mac and Windows both include default keyboard shortcuts. For example, Command-Tab and Command-Space bar are common keyboard shortcuts on Mac systems and Ctrl+Esc and Alt+Enter are common keyboard shortcuts on Windows systems. If you attempt to map one of these operating system keyboard shortcuts in Horizon Client, the behavior of the shortcut on the Mac client system and in the remote desktop or published application can be unpredictable.

- If you map a keyboard shortcut, how the shortcut behaves on the Mac client system depends on how the operating system manages the shortcut. For example, the keyboard shortcut might trigger an action in the operating system and Horizon Client might not respond to the shortcut. Alternatively, the keyboard shortcut might trigger an action in both the operating system and Horizon Client.
- Before you map a Mac keyboard shortcut in Horizon Client, you must disable the shortcut in System Preferences on the Mac client system. Not all Mac keyboard shortcuts can be disabled.
- If you map a Windows keyboard shortcut in Horizon Client, the mapped action occurs when you use the shortcut in the remote desktop or published application.
- For published applications, Windows shortcuts that include the Windows key are disabled by default and do not appear on the Horizon Client Keyboard Preferences dialog box. If you create a mapping for one of these disabled keyboard shortcuts, the shortcut appears in the Keyboard Preferences dialog box.

For a list of the default Mac keyboard shortcuts, go to the Apple support website (<http://support.apple.com>). For a list of the default Windows shortcuts, go to the Microsoft Windows website (<http://windows.microsoft.com>).

Modify the Horizon Client Mouse Shortcut Mappings

You can configure a single-button Apple mouse to send a right-click and a middle-click to remote desktops and published applications. You can modify, enable, or disable the default mouse shortcut mappings. You cannot create mouse shortcut mappings, or delete the default mouse shortcut mappings.

Procedure

- 1 Select **VMware Horizon Client > Preferences** and click **Keyboard & Mouse**.
- 2 Select the **Mouse Shortcuts** tab.

3 Modify the mouse shortcut mappings.

Option	Action
Modify a mouse shortcut mapping	Double-click the mapping and make your changes. To save your changes, click OK .
Disable a mouse shortcut mapping	Deselect the On check box next to the mouse shortcut mapping. When you disable a mouse shortcut mapping, Horizon Client does not send the mouse shortcut to the remote desktop or published application.
Enable a mouse shortcut mapping	Select the On check box next to the mouse shortcut mapping. When you enable a mouse shortcut mapping, Horizon Client sends the mouse shortcut to the remote desktop or published application.
Restore the default settings	Click Restore Defaults . Any changes that you made to the default mouse shortcut mappings are deleted and the default mappings are restored.

4 Close the Preferences dialog box.

Your mouse shortcut mapping changes take effect immediately. You do not need to restart open remote desktops or published applications to make the changes take effect.

Monitors and Screen Resolution

When you use the VMware Blast display protocol or the PCoIP display protocol, you can extend a remote desktop to multiple monitors. If you have a Mac with Retina Display, you can see the remote desktop in full resolution.

With the VMware Blast display protocol or the PCoIP display protocol, a remote desktop screen resolution of 4K (3840 x 2160) is supported. The number of 4K displays that are supported depends on the hardware version of the desktop virtual machine and the Windows version.

Hardware Version	Windows Version	Number of 4K Displays Supported
10 (ESXi 5.5.x compatible)	7, 8, 8.x, 10	1
11 (ESXi 6.0 compatible)	7 (3D rendering feature disabled and Windows Aero disabled)	3
11	7 (3D rendering feature enabled)	1
11	8, 8.x, 10	1
13 or 14	7, 8, 8.x, 10 (3D rendering feature enabled)	1
13 or 14	7, 8, 8.x, 10	4

Using Full-Screen Mode with Multiple Monitors

When a remote desktop window is open, you can use the **Window > Enter Full Screen** menu item or the expander arrows in the upper-right corner of the remote desktop window to extend the remote desktop

across multiple monitors. You can select the **Window > Use Single Display in Full Screen** menu item to make the remote desktop fill only one monitor.

The monitors do not have to be in the same mode. For example, if you are using a laptop that is connected to an external monitor, the external monitor can be in portrait mode or landscape mode.

You can select a full-screen option from the Settings dialog box after you connect to a server and before you open a remote desktop. Click the **Settings** button (gear icon) in the upper-right corner of the desktop and application selection window, select the remote desktop, and select a full-screen option from the **Full Screen** drop-down menu.

You can use the selective multiple-monitor feature to display a remote desktop window on a subset of your monitors. For more information, see [Select Specific Monitors to Display a Remote Desktop](#).

Using Remote Desktops with Split View

With Split View, which is supported in El Capitan (10.11) and later, you can fill your Mac screen with two applications without manually moving and resizing windows. You can use Split View with remote desktops in full-screen mode (**Full Screen** or **Use Single Display in Full Screen** option).

Using a High-Resolution Mac with Retina Display

If you use the VMware Blast display protocol or the PCoIP display protocol, Horizon Client supports high resolutions for client systems that support Retina Display. After you connect to a remote desktop, you can select the **Connection > Resolution > Full Resolution** menu item to enable high-resolution mode. This menu item appears only if the client system supports Retina Display.

In high-resolution mode, the DPI Synchronization feature ensures that the remote desktop's DPI setting matches the client system's DPI setting. For more information, see [Using DPI Synchronization](#).

Using DPI Synchronization

The DPI Synchronization feature ensures that the DPI setting in a remote desktop matches the client system's DPI setting.

The DPI Synchronization feature has the following requirements.

- The client system must support Retina Display.
- Full-resolution mode (**Connection > Resolution > Full Resolution**) must be selected in the remote desktop.
- If you use multiple monitors, the Retina Display must be the primary window in system preferences. You cannot have more than one display in full-screen mode.

A Horizon administrator can disable the DPI synchronization feature.

If DPI synchronization is disabled, display scaling is used. The Display Scaling feature scales the remote desktop appropriately.

Following are tips for using the DPI Synchronization feature.

- If you change the DPI setting on the client system, but the DPI setting does not change in the remote desktop, you might need to log out and log in again to make Horizon Client aware of the new DPI setting on the client system.
- If you start a remote session on a client system that has a DPI setting of more than 100 percent, and then use the same session on another client system that has a different DPI setting of more than 100 percent, you might need to log out and log back in to the remote session on the second client system to make DPI synchronization work on the second client system.
- If you connect to an active remote session in full-resolution mode, Horizon Client scales the resolution to be similar to when DPI Synchronization is enabled, but icons are not as clear. If you switch from normal to full-resolution mode in an active remote session, Horizon Client prompts you to log off from the remote session for the resolution change to take effect.
- If you use a non-Retina Display computer when you start a remote session, and then use a Retina Display computer to connect to the same session, the remote session cannot change to the new DPI setting until after you log off.

Select Specific Monitors to Display a Remote Desktop

If you have multiple monitors, you can select the monitors on which to display a remote desktop window. For example, if you have three monitors, you can specify that the remote desktop window appears on only two of those monitors.

You can select up to four adjacent monitors.

Prerequisites

You must have two or more monitors.

Procedure

- 1 Start Horizon Client and connect to a server.
- 2 In the desktop and application selector window, right-click the remote desktop and select **Settings**.
- 3 From the **Connect Via** drop-down menu, select **PCoIP** or **VMware Blast**.
- 4 Select **Use Selective Displays** from the **Full Screen** drop-down menu.

Thumbnails of the monitors that are currently connected to the client system appear under Display Arrangement. The display topology matches the display settings on the client system.

- 5 To select or deselect a monitor on which to display the remote desktop window, click a thumbnail.

When you select a monitor, its thumbnail changes color. If you violate a display selection rule, a warning message appears.

- 6 Connect to the remote desktop.

Your changes are applied immediately when you connect to the remote desktop. The remote desktop enters full-screen mode on the displays that you selected.

Select Specific Monitors to Display Published Applications

You can select the monitors on which to display published application windows. For example, if you have three monitors, you can specify that published application windows appear on only two of those monitors.

You can select up to four adjacent monitors. The monitors can be side by side, or stacked vertically. For example, you might configure two rows of two monitors each.

Procedure

- 1 Start Horizon Client and connect to a server.
- 2 Click the **Settings** button (gear icon) in the upper-right corner of the desktop and application selection window.
- 3 Select **Applications** in the left pane of the Settings dialog box.
- 4 Click the **Display** tab.

Thumbnails of the monitors that are currently connected to the client system appear under Display Arrangement. The display topology matches the display settings on the client system.

- 5 To select or deselect a monitor on which to display published applications, click a thumbnail.

When you select a monitor, its thumbnail changes color. If you violate a display selection rule, a warning message appears.

Using Exclusive Mode

Exclusive mode is similar to full-screen mode in that the remote desktop fills the screen. With exclusive mode, unlike full-screen mode, the VMware Horizon Client menu bar and Dock do not appear when you move your pointer to the edges of the screen.

To enter exclusive mode, open a remote desktop in windowed mode, press and hold down the Option key, and select **Window > Enter Exclusive Mode**.

When a remote desktop is in windowed mode, you can also press Command-Control-Option-F to enter exclusive mode. To exit exclusive mode, press Command-Control-Option-F again.

Note If you do not press and hold down the Option key, the **Enter Full Screen** menu item appears instead of the **Enter Exclusive Mode** menu item. If the remote desktop is in full-screen mode, you cannot select the **Enter Exclusive Mode** menu item.

To use exclusive mode with two monitors, before you open the remote desktop, select **Use All Displays** from the Settings dialog box, and then open the desktop and enter exclusive mode. To use exclusive mode with a single monitor, before you open the remote desktop, select **Use Single Display** from the Settings dialog box, and then connect to the remote desktop and enter exclusive mode.

To open the Settings dialog box, click the **Settings** button (gear icon) in the upper-right corner of the desktop and application selection window, select the remote desktop, and select an option from the **Full Screen** drop-down menu.

Customize the Display Resolution and Display Scaling for a Remote Desktop

You can use Horizon Client to customize the display resolution and display scaling for a remote desktop. The display resolution determines the clarity of the text and images. At higher resolutions, such as 1600 x 1200 pixels, items appear sharper. Display scaling, which is represented as a percentage, increases or decreases the size of text, icons, and navigation elements.

This feature has the following limitations and considerations.

- Customizing the display resolution for a remote desktop is not supported in multiple-monitor mode.
- If you select a custom resolution that is higher than the client resolution, Horizon Client resizes the remote desktop window to fit the client window. If you select a custom resolution that is lower than the client resolution, black bars appear in the remote desktop window.
- If you customize the display resolution during a remote desktop session, your changes take effect immediately. If you customize display scaling during a remote desktop session, you must log out and log back in to make your changes take effect.
- The Horizon Client **Connection > Resolution** menu is available only if you select automatic resolution. For more information, see [Using a High-Resolution Mac with Retina Display](#).

Procedure

- 1 Start Horizon Client and connect to a server.
- 2 In the desktop and application selector window, right-click the remote desktop and select **Settings**.
- 3 Click the **Display** tab.
- 4 To customize the display resolution, select a resolution from the **Resolution** drop-down menu.

If you select **Automatic** (the default setting), Horizon Client fits the remote desktop to the client window size. If the remote desktop does not support the display resolution that you select, it uses the default setting.
- 5 To customize display scaling, select a scaling size from the **Scaling** drop-down menu.

If you select **Automatic** (the default setting), Horizon Client sets the display scaling percentage based on the display resolution that you select.

Using the Real-Time Audio-Video Feature for Webcams and Microphones

With the Real-Time Audio-Video feature, you can use the local client system's webcam or microphone in a remote desktop or published application. Real-Time Audio-Video is compatible with standard conferencing applications and browser-based video applications. It supports standard webcams, audio USB devices, and analog audio input.

When You Can Use a Webcam with the Real-Time Audio-Video Feature

If a Horizon administrator has configured the Real-Time Audio-Video feature, you can use a webcam that is built in or connected to the client computer in a remote desktop or published application. You can use the webcam in conferencing applications such as Skype, Webex, or Google Hangouts.

During the setup of an application such as Skype, Webex, or Google Hangouts on a remote desktop, you can select input and output devices from menus in the application.

For remote desktops and published applications, a redirected webcam is named VMware Virtual Webcam in the application.

For many applications, you do not need to select an input device.

When the client computer uses the webcam, the remote session can use it at the same time. Also, if the remote session uses the webcam, the client computer can use it at the same time.

Note If you use a USB webcam, do not connect it from the **Connection > USB** menu in Horizon Client. Doing so routes the device through USB redirection and the performance is not usable for video chat.

If more than one webcam is connected to the local client computer, you can configure a preferred webcam to use in remote sessions.

Select a Default Microphone on the Mac Client

If you have multiple microphones on the Mac client, the remote desktop uses only one microphone. You can use the System Preferences on the Mac client to specify the default microphone in the remote desktop.

With the Real-Time Audio-Video feature, audio input devices and audio output devices work without using USB redirection and the required network bandwidth is greatly reduced. Analog audio input devices are also supported.

This procedure describes how to select a microphone from the user interface of the Mac client. You can also configure a preferred microphone by using the Mac defaults system. For more information, see the *VMware Horizon Client for Mac Installation and Setup Guide* document.

Important When you use a USB microphone, do not connect it from the **Connection > USB** menu in Horizon Client. Doing so routes the device through USB redirection and the device cannot use the Real-Time Audio-Video feature.

Prerequisites

- Verify that you have a USB microphone, or another type of microphone, installed and operational on the Mac client.
- Use the VMware Blast display protocol or the PCoIP display protocol for the remote desktop.

Procedure

- 1 On the Mac client, select **Apple menu > System Preferences** and click **Sound**.

- 2 Open the Input pane of Sound preferences.
- 3 Select the microphone that you prefer to use.

The next time that you connect to a remote desktop and start a call, the remote desktop uses the default microphone that you selected on the Mac client.

Allowing Access to Webcams and Microphones

When you first use a webcam or microphone in a remote session on a macOS Mojave (10.14) client system, you are prompted to grant access to the system's camera and microphone features.

If you do not grant access at that time, you can grant access later by going to System Preferences, selecting **Security & Privacy**, clicking the **Privacy** tab, and selecting **Camera** or **Microphone**.

Upgrade Horizon Client Online

You can configure Horizon Client to look for and install updates each time it starts. You can also look for and install updates manually.

If Horizon Client detects a new version, you can download and install the new version, have Horizon Client remind you to install the new version the next time it starts, or skip the new version. If you skip a new version when looking for updates manually, the automatic update process also skips that version.

Procedure

- ◆ To configure Horizon Client to look for and install updates each time it starts, select **VMware Horizon Client > Preferences** and select the **Automatically check for updates** check box.

The **Automatically check for updates** check box is selected by default.

- ◆ To look manually for and install an update, select **VMware Horizon Client > Check for Updates**.

Troubleshooting Horizon Client

You can solve most problems with Horizon Client by restarting or resetting remote desktops or published applications, or by reinstalling Horizon Client.

This chapter includes the following topics:

- [Restart a Remote Desktop](#)
- [Reset Remote Desktops or Published Applications](#)
- [Uninstalling Horizon Client](#)
- [Connecting to a Server in Workspace ONE Mode](#)

Restart a Remote Desktop

If the remote desktop operating system stops responding, you might need to restart a remote desktop. Restarting a remote desktop is similar to using the Windows operating system restart command. The remote desktop operating system usually prompts you to save any unsaved data before it restarts.

You can restart a remote desktop only if a Horizon administrator has enabled the restart feature for the remote desktop.

Procedure

- ◆ In the desktop and application selection window, select the remote desktop shortcut, press Control-click, and select **Restart** from the context menu.

The operating system in the remote desktop restarts and Horizon Client disconnects and logs off from the remote desktop.

What to do next

Wait an appropriate amount of time for the system to restart before you attempt to reconnect to the remote desktop.

If restarting the remote desktop does not solve the problem, you might need to reset the remote desktop. See [Reset Remote Desktops or Published Applications](#).

Reset Remote Desktops or Published Applications

You might need to reset a remote desktop if the desktop operating system stops responding and restarting the remote desktop does not solve the problem.

Resetting a remote desktop is the same as pressing the **Reset** button on a physical PC to force the PC to restart. Any files that are open on the remote desktop are closed and are not saved.

Resetting published applications quits all open applications.

Resetting published applications quits the applications without saving any unsaved data. All open published applications are closed.

You can reset a remote desktop only if a Horizon administrator has enabled the reset feature for the remote desktop.

Procedure

- ◆ Use the **Reset** command.

Option	Action
Reset a remote desktop from the desktop and application selection window	Select the remote desktop name, press Control-click, and select Reset from the context menu.
Reset published applications from the desktop and application selection window	Click the Settings button (gear icon) in the upper-right corner of the window, select Applications in the left pane, click Reset , and click Continue .

When you reset a remote desktop, the operating system in the remote desktop restarts and Horizon Client disconnects and logs off from the remote desktop. When you reset published applications, the published applications quit.

What to do next

Wait an appropriate amount of time for system to restart before attempting to reconnect to the remote desktop or published application.

Uninstalling Horizon Client

Sometimes you can resolve problems with Horizon Client by uninstalling and reinstalling Horizon Client.

To uninstall Horizon Client, use the same method that you use to uninstall any application.

Drag the **VMware Horizon Client** application from the **Applications** folder to the **Trash** and empty the trash.

After Horizon Client is uninstalled, you can reinstall it.

Connecting to a Server in Workspace ONE Mode

You cannot connect to a server directly through Horizon Client, or your remote desktop and published application entitlements are not visible in Horizon Client.

Problem

- When you try to connect to the server directly through Horizon Client, Horizon Client redirects you to the Workspace ONE portal.
- When you open a remote desktop or published application through a URI or shortcut, or when you open a local file through file association, the request redirects you to the Workspace ONE portal for authentication.
- After you open a remote desktop or published application through Workspace ONE and Horizon Client starts, you cannot see or open other entitled remote desktops or published applications in Horizon Client.

Cause

Beginning with Horizon 7 version 7.2, a Horizon administrator can enable Workspace ONE mode on a Connection Server instance. This behavior is normal when Workspace ONE mode is enabled on a Connection Server instance.

Solution

Use Workspace ONE to connect to a Workspace ONE enabled server and access your remote desktops and published applications.