

VMware Horizon Client for Android Installation and Setup Guide

Modified on 21 SEP 2017

VMware Horizon Client for Android 4.6

vmware[®]

You can find the most up-to-date technical documentation on the VMware Web site at:

<https://docs.vmware.com/>

The VMware Web site also provides the latest product updates.

If you have comments about this documentation, submit your feedback to:

docfeedback@vmware.com

Copyright © 2011–2017 VMware, Inc. All rights reserved. [Copyright and trademark information.](#)

VMware, Inc.
3401 Hillview Ave.
Palo Alto, CA 94304
www.vmware.com

Contents

VMware Horizon Client for Android Installation and Setup Guide	5
1 Setup and Installation	7
System Requirements	7
System Requirements for Android Clients	7
System Requirements for Thin Clients	8
System Requirements for Chromebooks	8
System Requirements for Real-Time Audio-Video	9
Smart Card Authentication Requirements	9
Configure Smart Card Authentication	10
Fingerprint Authentication Requirements	11
Supported Desktop Operating Systems	12
Preparing Connection Server for Horizon Client	12
Installing Horizon Client	13
Install or Upgrade Horizon Client	13
Configure AirWatch to Deliver Horizon Client to Android Devices	14
Configure AirWatch to Deliver Horizon Client to Android for Work Devices	16
Configuring a List of Servers and a Default Server for Chromebooks	19
Configure Horizon Client in Thin Client Mode	20
Using Horizon Client on a Thin Client	20
Using Embedded RSA SecurID Software Tokens	21
Configure Advanced TLS/SSL Options	22
Configure VMware Blast Options	22
Configure the Horizon Client Default View	23
Horizon Client Data Collected by VMware	24
2 Using URIs to Configure Horizon Client	27
Syntax for Creating vmware-view URIs	27
Examples of vmware-view URIs	30
3 Managing Remote Desktop and Application Connections	33
Setting the Certificate Checking Mode in Horizon Client	33
Connect to a Remote Desktop or Application	34
Use Unauthenticated Access to Connect to Remote Applications	36
Share Access to Local Storage with Client Drive Redirection	37
Add a Remote Desktop or Application Shortcut to the Android Home Screen	38
Manage Server Shortcuts	39
Select a Favorite Remote Desktop or Application	39
Disconnecting From a Remote Desktop or Application	40
Log Off From a Remote Desktop	40
Manage Desktop and Application Shortcuts	41

- Using Android 7.0 Nougat Multi-Window Modes with Horizon Client 41
- Using Horizon Client with Samsung DeX 41
 - Enable the DeX Mode Auto Launch Feature 41

- 4 Using a Microsoft Windows Desktop or Application 43**
 - Feature Support Matrix for Android 44
 - Input Devices, Keyboards, and Keyboard Settings 46
 - Enable the Japanese 106/109 Keyboard Layout 46
 - Using the Real-Time Audio-Video Feature 47
 - Using Native Operating System Gestures with Touch Redirection 47
 - Using the Unity Touch Sidebar with a Remote Desktop 48
 - Using the Unity Touch Sidebar with a Remote Application 50
 - Horizon Client Tools on a Mobile Device 52
 - Gestures 54
 - Multitasking 55
 - Copying and Pasting Text and Images 55
 - Saving Documents in a Remote Application 56
 - Screen Resolutions and Using External Displays 56
 - PCoIP Client-Side Image Cache 57
 - Internationalization and International Keyboards 58

- 5 Troubleshooting Horizon Client 59**
 - Restart a Remote Desktop 59
 - Reset a Remote Desktop or Remote Applications 60
 - Uninstall Horizon Client 61
 - Collecting and Sending Logging Information to VMware 61
 - Enable Horizon Client Log Collection 61
 - Manually Retrieve and Send Horizon Client Log Files 62
 - Disable Horizon Client Log Collection 62
 - Report Horizon Client Crash Data to VMware 62
 - Horizon Client Stops Responding or the Remote Desktop Freezes 63
 - Problem Establishing a Connection When Using a Proxy 63
 - Connecting to a Server in Workspace ONE Mode 64

- Index 65

VMware Horizon Client for Android Installation and Setup Guide

This document, *VMware Horizon Client for Android Installation and Setup Guide*, provides information about installing, configuring, and using VMware Horizon® Client™ software on an Android device.

This information is intended for administrators who must set up a Horizon deployment that includes Android client devices. The information is written for experienced system administrators who are familiar with virtual machine technology and datacenter operations.

Setup and Installation

Setting up a Horizon deployment for Android clients involves using certain Connection Server configuration settings, meeting the system requirements for Horizon servers and client devices, and installing the Horizon Client app.

This chapter includes the following topics:

- [“System Requirements,”](#) on page 7
- [“Preparing Connection Server for Horizon Client,”](#) on page 12
- [“Installing Horizon Client,”](#) on page 13
- [“Configuring a List of Servers and a Default Server for Chromebooks,”](#) on page 19
- [“Configure Horizon Client in Thin Client Mode,”](#) on page 20
- [“Using Embedded RSA SecurID Software Tokens,”](#) on page 21
- [“Configure Advanced TLS/SSL Options,”](#) on page 22
- [“Configure VMware Blast Options,”](#) on page 22
- [“Configure the Horizon Client Default View,”](#) on page 23
- [“Horizon Client Data Collected by VMware,”](#) on page 24

System Requirements

Android, thin client, and Chromebook devices that run Horizon Client must meet certain hardware and software requirements.

System Requirements for Android Clients

The Android device on which you install Horizon Client, and the peripherals it uses, must meet certain system requirements.

Android operating systems

- Android 4.0 (Ice Cream Sandwich)
- Android 4.1, 4.2, and 4.3 (Jelly Bean)
- Android 4.4 (KitKat)
- Android 5.0 (Lollipop)
- Android 6.0 (Marshmallow)
- Android 7.0 and 7.1 (Nougat)

	<ul style="list-style-type: none"> ■ Android 8.0
CPU architecture	<ul style="list-style-type: none"> ■ ARM ■ x86
<hr/>	
	NOTE Non-NEON devices are not supported.
<hr/>	
External keyboards	(Optional) Bluetooth and docked keyboard devices. For information about the external devices that your specific device supports, see the documentation from the device manufacturer.
Smart cards	See “Smart Card Authentication Requirements,” on page 9.
Connection Server, security server, and View Agent or Horizon Agent	Latest maintenance release of Horizon 6 version 6.x and later releases. VMware recommends that you use a security server or Unified Access Gateway appliance so that client devices do not require a VPN connection. If your company has an internal wireless network to provide routable access to remote desktops that devices can use, you do not have to set up a security server, Unified Access Gateway, or VPN connection.
Display protocols	<ul style="list-style-type: none"> ■ PCoIP ■ VMware Blast (requires Horizon Agent 7.0 or later)

You can also install Horizon Client for Android on certain thin clients and Chromebooks. See [“System Requirements for Thin Clients,”](#) on page 8 and [“System Requirements for Chromebooks,”](#) on page 8.

System Requirements for Thin Clients

You can install Horizon Client for Android on certain thin clients.

The thin client on which you install Horizon Client for Android, and the external input devices it uses, must meet certain system requirements.

Thin client models and Android operating systems	<ul style="list-style-type: none"> ■ Remix Mini with Android 5.1 (RemixOS 2.0.205 or later) ■ NVIDIA SHIELD Android TV with Android 6.0 ■ Amazon Fire TV (1st Generation) with Android 5.1
External input devices	Horizon Client generally works with any external input device, including keyboards and controllers, that works with the thin client. For information about the devices that a specific thin client supports, see the documentation from the device manufacturer.
Horizon Client requirements	Enable the Thin Client mode setting in Horizon Client. See “Configure Horizon Client in Thin Client Mode,” on page 20.

System Requirements for Chromebooks

You can install Horizon Client for Android on certain Chromebook models. You can install Horizon Client for Android on a Chromebook from Google Play. Not all features are supported on a Chromebook.

Chromebook models that support Android apps	<ul style="list-style-type: none"> ■ ASUS Chromebook Flip ■ Acer Chromebook R11 C738T ■ Google Chromebook Pixel (2015)
--	---

Google is continuing to evaluate more devices. For the latest information, go to https://sites.google.com/a/chromium.org/dev/chromium-os/chrome-os-systems-supporting-android-apps?visit_id=0-636124384717258228-2661029306&rd=1.

Feature limitations

The following features are not supported when you install Horizon Client for Android on a Chromebook.

- AirWatch integration
- Fingerprint authentication
- Smart card authentication
- Rich text copy and paste
- Multiple monitors

System Requirements for Real-Time Audio-Video

Real-Time Audio-Video works with standard audio and video devices and with standard conferencing applications such as Skype, WebEx, and Google Hangouts. To support Real-Time Audio-Video, your Horizon environment must meet certain software and hardware requirements.

Remote desktops and applications

To use Real-Time Audio-Video with published desktops and remote applications, you must have Horizon Agent 7.0.2 or later.

Client access device

Real-Time Audio Video is supported on all Android devices that run Horizon Client for Android. For more information, see “[System Requirements for Android Clients](#),” on page 7.

Smart Card Authentication Requirements

Client systems that use a smart card for user authentication must meet certain requirements.

Client Hardware and Software Requirements

VMware recommends that you use an Android 4.0 or later operating system. The CPU architecture may be ARM or x86.

Each client system that uses a smart card for user authentication must have the following hardware and software:

- Horizon Client
- A compatible smart card reader

VMware tested the baiMobile 3000MP Bluetooth Smart Card, baiMobile 301MP USB Smart Card, and baiMobile 301MP_LT Smart Card readers.

- Smart card middleware

The Android device app must support your baiMobile smart card reader. For example, one such app is baiMobile PCSC-Lite (Android device tile name baiMobile PC/SC). Horizon Client for Android contains support for both the baiMobile 3000MP Bluetooth and baiMobile 301MP USB smart card readers.

Without such an app, you can pair the Bluetooth card reader with the Android device, but you cannot connect it. The app sends a connection request to the reader and you tap the **OK** button on the reader to establish the Bluetooth connection.

- Product-specific application drivers

Users that authenticate with smart cards must have a smart card and each smart card must contain a user certificate.

Remote Desktop and Application Software Requirements

A Horizon administrator must install product-specific application drivers on the remote desktops or RDS host. VMware tested the ActiveClient6.2.0.50, ActivClient_7.0.1, Gemalto.MiniDriver.NET.inf, and Charismathics CSTC PIV 5.2.2 drivers.

Enabling the Username Hint Field in Horizon Client

In some environments, smart card users can use a single smart card certificate to authenticate to multiple user accounts. Users enter their user name in the **Username hint** field during smart card sign-in.

To make the **Username hint** field appear on the Horizon Client login dialog box, you must enable the smart card user name hints feature for the Connection Server instance in Horizon Administrator. The smart card user name hints feature is supported only with Horizon 7 version 7.0.2 and later servers and agents. For information about enabling the smart card user name hints feature, see the *View Administration* document.

If your environment uses an Unified Access Gateway appliance rather than a security server for secure external access, you must configure the Unified Access Gateway appliance to support the smart card user name hints feature. The smart card user name hints feature is supported only with Unified Access Gateway 2.7.2 and later. For information about enabling the smart card user name hints feature in Unified Access Gateway, see the *Deploying and Configuring Unified Access Gateway* document.

NOTE Horizon Client still supports single-account smart card certificates when the smart card user name hints feature is enabled.

Additional Smart Card Authentication Requirements

In addition to meeting the smart card requirements for Horizon Client systems, other Horizon components must meet certain configuration requirements to support smart cards.

Connection Server and security server hosts

An administrator must add all applicable Certificate Authority (CA) certificates for all trusted user certificates to a server truststore file on the Connection Server host or security server host. These certificates include root certificates and must include intermediate certificates if the user's smart card certificate was issued by an intermediate certificate authority.

For information about configuring Connection Server to support smart card use, see the *View Administration* document.

Active Directory

For information about tasks that an administrator might need to perform in Active Directory to implement smart card authentication, see the *View Administration* document.

Configure Smart Card Authentication

Smart card configuration tasks include connecting and pairing the card reader with the device and setting the smart card removal policy.

Prerequisites

Verify that the client device, remote desktops, RDS hosts, Connection Server host, and other Horizon components meet the smart card authentication requirements. See "[Smart Card Authentication Requirements](#)," on page 9.

Procedure

- 1 Install the smart card middleware app on the device.
- 2 Pair the device with the smart card reader, according to the documentation provided by the manufacturer of the reader.

If you are using a Bluetooth smart card reader, a randomly generated number is displayed on both devices during this process. When you confirm that the numbers match, you establish secure Bluetooth communication.

- 3 Configure the smart card removal policy.

Option	Description
Set the policy on the Connection Server instance	<p>When you set the policy on the Connection Server instance, you can disconnect users from the Connection Server instance when they remove their smart cards, or keep users connected to Connection Server when they remove their smart cards and let them start new desktop or application sessions without reauthenticating.</p> <ol style="list-style-type: none"> a In Horizon Administrator, select View Configuration > Servers. b On the Connection Servers tab, select the Connection Server instance and click Edit. c On the Authentication tab, select or deselect the Disconnect user sessions on smart card removal check box to configure the smart card removal policy. d Click OK to save your changes. e Restart the Connection Server service to make your changes take effect. <p>If you select the Disconnect user sessions on smart card removal check box, Horizon Client returns to the Recent tab when users remove their smart cards.</p>
Set the policy on the remote desktop	<p>When you set the policy on the remote desktop, you can use the Group Policy Editor (<code>gpedit.msc</code>) to configure one of the following settings: no action, lock workstation, force log off, or Disconnect if a Remote Desktop Services session.</p> <ol style="list-style-type: none"> a Open <code>gpedit.msc</code> in the desktop operating system. b Navigate to Windows settings > Security settings > Local policies > Security options > Interactive logon: smart card removal behavior. c Run the <code>gpupdate /force</code> command after you change the configuration to force a group policy refresh.

Fingerprint Authentication Requirements

To use fingerprint authentication in Horizon Client, the Android device on which you install Horizon Client must meet certain requirements.

Android device models	Any Android device model that has a fingerprint sensor and native fingerprint reader functionality.
Operating system requirements	<ul style="list-style-type: none"> ■ Android 6 (Marshmallow) and later ■ The Fingerprint Authentication option must be enabled and at least one fingerprint must be enrolled.
Connection Server requirements	<ul style="list-style-type: none"> ■ Horizon 6 version 6.2 or a later release. ■ Enable biometric authentication in Connection Server. For information, see "Configure Biometric Authentication" in the <i>View Administration</i> document.

Horizon Client requirements

- The Connection Server instance must present a valid root-signed certificate to Horizon Client.
- Set the certificate checking mode to **Never connect to untrusted servers** or **Warn before connecting to untrusted servers**. For information about setting the certificate checking mode, see [“Setting the Certificate Checking Mode in Horizon Client,”](#) on page 33.
- Enable fingerprint authentication by tapping **Enable Fingerprint** on the server login window. After you successfully log in, your Active Directory credentials are stored securely in your Android device. The **Enable Fingerprint** option is shown the first time you log in and does not appear after fingerprint authentication is enabled.

You can use fingerprint authentication with smart card authentication and as part of two-factor authentication with RSA SecurID and RADIUS authentication. If you use fingerprint authentication with smart card authentication, Horizon Client connects to the server after you enter your PIN and the fingerprint authentication window does not appear.

Supported Desktop Operating Systems

A Horizon administrator creates virtual machines that have a guest operating system and installs agent software in the guest operating system. End users can log in to these virtual machines from a client device.

For a list of the supported Windows guest operating systems, see the *View Installation* document.

Some Linux guest operating systems are also supported if you have View Agent 6.1.1 or later, or Horizon Agent 7.0 or later. For information about system requirements, configuring Linux virtual machines for use in Horizon, and a list of supported features, see *Setting Up Horizon 6 for Linux Desktops* or *Setting Up Horizon 7 for Linux Desktops*.

Preparing Connection Server for Horizon Client

A Horizon administrator must perform specific tasks to enable end users to connect to remote desktops and applications.

Before end users can connect to a Connection Server instance or a security server and access a remote desktop or application, a Horizon administrator must configure certain pool settings and security settings:

- If you plan to use Unified Access Gateway, configure Connection Server to work with Unified Access Gateway. See the *Deploying and Configuring Unified Access Gateway* document. Unified Access Gateway appliances fulfill the same role that was previously played by only security servers.
- If you are using a security server, verify that you are using the latest maintenance releases of Connection Server 6.x and Security Server 6.x or later releases. For more information, see the *View Installation* document.
- If you plan to use a secure tunnel connection for client devices and if the secure connection is configured with a DNS host name for Connection Server or a security server, verify that the client device can resolve this DNS name.

To enable or disable the secure tunnel, in Horizon Administrator, go to the Edit Horizon Connection Server Settings dialog box and use the check box called **Use secure tunnel connection to desktop**.

- Verify that a desktop or application pool has been created and that the user account that you plan to use is entitled to access the pool. For information, see the *Setting Up Virtual Desktops in Horizon 7* or *Setting Up Published Desktops and Applications in Horizon 7* document.

- To use two-factor authentication with Horizon Client, such as RSA SecurID or RADIUS authentication, you must enable this feature on Connection Server. For more information, see the topics about two-factor authentication in the *View Administration* document.
- To hide security information in Horizon Client, including server URL information and the **Domain** drop-down menu, enable the **Hide server information in client user interface** and **Hide domain list in client user interface** settings in Horizon Administrator. These global settings are available in Horizon 7 version 7.1 and later. For information about configuring global settings, see the *View Administration* document.

To authenticate when the **Domain** drop-down menu is hidden, users must provide domain information by entering their user name in the format `domain\username` or `username@domain` in the **User name** text box.

IMPORTANT If you enable the **Hide server information in client user interface** and **Hide domain list in client user interface** settings and select two-factor authentication (RSA SecureID or RADIUS) for the Connection Server instance, do not enforce Windows user name matching. Enforcing Windows user name matching will prevent users from being able to enter domain information in the user name text box and login will always fail. For more information, see the topics about two-factor authentication in the *View Administration* document.

- To enable end users to save their passwords with Horizon Client, so that they do not always need to supply credentials when connecting to a Connection Server instance, configure Horizon LDAP for this feature on the Connection Server host.

Users can save their passwords if Horizon LDAP is configured to allow it, if the Horizon Client certificate verification mode is set to **Warn before connecting to untrusted servers** or **Never connect to untrusted servers**, and if Horizon Client can fully verify the server certificate that Connection Server presents. For instructions, see the *View Administration* document.

- Verify that the desktop or application pool is set to use the VMware Blast display protocol or the PCoIP display protocol. For information, see the *Setting Up Virtual Desktops in Horizon 7* and *Setting Up Published Desktops and Applications in Horizon 7* documents.
- To provide end users unauthenticated access to published applications in Horizon Client, you must enable this feature in Connection Server. For more information, see the topics about unauthenticated access in the *View Administration* document.

Installing Horizon Client

You can install Horizon Client the same way that you install other Android apps. You can also use AirWatch to deliver Horizon Client to Android device users.

Install or Upgrade Horizon Client

Horizon Client for Android is an Android app, and you install it just as you do other Android apps.

Prerequisites

- If you have not already set up the device, do so. See the manufacturer's user's guide for the device.
- Verify that you have the URL for a download page that contains the Horizon Client installer. This URL might be the VMware Downloads page at <http://www.vmware.com/go/viewclients>.
- Become familiar with the device's procedure for installing apps.

Devices from different manufacturers use different methods for installing Android apps. See the manufacturer's user's guide for the device. Depending on the device, you might have to perform the following tasks before you can install an app:

- Install a particular driver.

- Install a file browser.

Procedure

- 1 Browse to the URL for downloading the Horizon Client app, or search for the Horizon Client app in the Google Play Store or Amazon Appstore for Android.

For some devices, you download the file to the device. For others, you download the file to a PC or a USB device.

- 2 If necessary, copy the app (.apk file) to your device.
- 3 Install the app according to the device's customary procedure for installing apps.

For example, on some devices, you must tap the file to install it.

What to do next

To determine whether the installation succeeded, verify that the **Horizon** app icon appears on the **Apps** tab on the Android device.

The first time you launch Horizon Client on Android 6.0 Marshmallow, the app prompts you to allow Horizon Client to make and manage phone calls, access photos, media, and files, and record audio on your device.

If you installed Horizon Client on a thin client, see “[Configure Horizon Client in Thin Client Mode](#),” on page 20.

Configure AirWatch to Deliver Horizon Client to Android Devices

You can configure AirWatch to deliver Horizon Client to Android device users.

You can optionally specify a list of Connection Server instances or a default Connection Server instance. If you specify a list of servers, the servers appear as shortcuts in Horizon Client. If you specify a default server, Horizon Client automatically connects to that server.

If your environment is set up for Android for Work, do not follow this procedure. Instead, see “[Configure AirWatch to Deliver Horizon Client to Android for Work Devices](#),” on page 16.

Prerequisites

- Install and deploy AirWatch. See <http://www.air-watch.com>.
- Download the Horizon Client app from the VMware Downloads page at <http://www.vmware.com/go/viewclients> or from the Google Play Store or Amazon Appstore for Android.
- Become familiar with the AirWatch console. This procedure assumes you know how to use the AirWatch console. For more information, see the AirWatch documentation or online help.
- Decide which version of Horizon Client to deploy with the AirWatch console. The AirWatch console cannot deploy both the ARM and the x86 version at the same time.

Procedure

- 1 Log in to the AirWatch console as an administrator.
- 2 Select **Accounts > Users > List View**, click **Add**, select **Add User**, and add user accounts for the users who will run Horizon Client on their Android devices.
- 3 Select **Accounts > Users > User Groups > List View**, click **Add**, select **Add User Group**, and create a user group for the user accounts that you created.

- 4 Create an application profile for Horizon Client in AirWatch.
 - a Select **Apps & Books > Applications > Application Settings > Profiles** and click **Add Profile**.
 - b Select the **SDK Profile** configuration type.
 - c Select the **Android** profile type.
 - d (Optional) Click **Custom Settings** to configure a list of servers or a default server.

Use the server property to specify the IP address or host name of the server, the username and domain properties to specify the name and domain of a user that is entitled to use the server, and the description property to specify a description of the server. The username, domain, and description properties are optional. For example:

```
{
  "settings": {
    "server-list":
      [

{"server":"123.456.1.1","username":"User1","domain":"TestDomain1","description":"View
server 1"},

{"server":"123.456.1.2","username":"User2","domain":"TestDomain2","description":"View
server 2"},

{"server":"123.456.1.3","username":"User3","domain":"TestDomain3","description":"View
server 3"},

{"server":"viewserver4.mydomain.com","username":"User4","domain":"TestDomain4","descripti
on":"View server 4"}
      ]
    }
  }
```

You can use the `default` property to specify a default server. Valid values are `true` and `false`. For example:

```
{
  "settings": {
    "server-list":
      [

{"server":"123.456.1.1","username":"User1","domain":"TestDomain1","description":"View
server 1","default":true},
      ]
    }
  }
```

- 5 Upload and add the Horizon Client application to AirWatch.
 - a Select **Apps & Books > Applications > List View** and click **Add Application** on the **Internal** tab.
 - b Browse to the Horizon Client app that you downloaded and click **Save** to upload the application to AirWatch.
 - c On the **Info** tab, type an application name and specify the supported mobile device models.
 - d On the **Assignment** tab, assign the Horizon Client application to the user group that you created.

- e On the **Deployment** tab, set **Application uses AirWatch SDK** to **Yes** and select the SDK profile that you created from the **SDK Profile** drop-down menu.
 - f Publish the Horizon Client application.
- 6 Install and set up the AirWatch Agent on each device.
- You can download the AirWatch Agent from the Google Play Store or Amazon Appstore for Android.
- 7 Use the AirWatch console to install the Horizon Client application on the devices.
- You cannot install the Horizon Client application before the effective date on the **Deployment** tab.

AirWatch delivers Horizon Client to the devices in the user group that you associated with the Horizon Client application.

When a user launches Horizon Client, Horizon Client communicates with the AirWatch Agent on the device. If you configured a list of Connection Server instances, AirWatch pushes the server information to the AirWatch Agent on the device and shortcuts for those servers appear in Horizon Client.

What to do next

You can use the AirWatch console to edit the Horizon Client application and push those changes to devices.

Configure AirWatch to Deliver Horizon Client to Android for Work Devices

You can configure AirWatch to deliver Horizon Client to Android for Work device users.

You can optionally specify a list of Connection Server instances or a default Connection Server instance. If you specify a list of servers, the servers appear as shortcuts in Horizon Client. If you specify a default server, Horizon Client automatically connects to that server.

Use this procedure only if your environment is set up for Android for Work. If your environment is not set up for Android for Work, see [“Configure AirWatch to Deliver Horizon Client to Android Devices,”](#) on page 14.

Prerequisites

- Verify that your AirWatch environment is integrated with Android for Work. See the AirWatch documentation or online help.
- Install and deploy AirWatch. You must install AirWatch Server v8.0 FP02 or later and AirWatch Agent v4.2 or later. See <http://www.air-watch.com>. You can download AirWatch Agent from Google Play Store or Amazon Appstore for Android.
- Become familiar with the AirWatch console. This procedure assumes that you know how to use the AirWatch console. See the AirWatch documentation or online help.
- Verify that you have a corporate Google account. You must have a corporate Google account to enroll Android for Work devices. For information about the enrollment process, see the AirWatch documentation or online help.

Procedure

- 1 Log in to the AirWatch Console as an administrator.
- 2 Create and configure a smart group for your Horizon Client users in AirWatch.
 - a Select **Groups and Settings > Groups > Assignment Groups**.
 - b Click **Add Smart Group**.

- c Enter the smart group name, select the smart group type, and configure the smart group properties.
 - d Click **Save**.
- 3 Add the Horizon Client application to AirWatch.
 - a Select **Apps & Books > Applications > List View**.
 - b On the **Public** tab, click **Add Application**.
 - c Select **Android** from the **Platform** drop-down menu, click **Search App Store**, enter **com.vmware.view.client.android** in the **Name** text box, and click **Next**.
 - d Click **Select** next to the Horizon Client application.
 - e Click **Save & Publish**.
- 4 Assign the Horizon Client application to users and configure the deployment details.
 - a Select **Apps & Books > Applications > List View**.
 - b On the **Public** tab, click the **Edit** icon next to the Horizon Client application.
 - c On the **Assignment** tab, assign the Horizon Client application to the smart group that you created.

- d (Optional) On the **Deployment** tab, select a push mode, select the **Send Application Configuration** check box, enter **broker_list** in the **Configuration Key** text box, select **String** from the **Value Type** drop-down menu, and enter a list of servers in the **Configuration Value** text box in JSON format.

Use the **server** property to specify the IP address or host name of the server, the **username** and **domain** properties to specify the name and domain of a user that is entitled to the server, and the **description** property to specify a description of the server. The **username**, **domain**, and **description** properties are optional. For example:

```
{
  "settings":{
    "server-list":
      [

{"server":"123.456.1.1","username":"User1","domain":"TestDomain1","description":"View
server 1"},

{"server":"123.456.1.2","username":"User2","domain":"TestDomain2","description":"View
server 2"},

{"server":"123.456.1.3","username":"User3","domain":"TestDomain3","description":"View
server 3"},

{"server":"viewserver4.mydomain.com","username":"User4","domain":"TestDomain4","descripti
on":"View server 4"}
      ]
    }
  }
```

You can use the **default** property to specify a default server. Valid values are **true** and **false**. For example:

```
{
  "settings":{
    "server-list":
      [

{"server":"123.456.1.1","username":"User1","domain":"TestDomain1","description":"View
server 1","default":true},
      ]
    }
  }
```

- e Click **Save & Publish** to make the Horizon Client application available to end users.
- 5 Enroll Android for Work devices.
- You use your corporate Google account to enroll the devices.
- 6 In the AirWatch Console, install the Horizon Client application on each device.

AirWatch delivers Horizon Client to the Android devices in the smart group that you created.

When a user starts Horizon Client, Horizon Client communicates with the AirWatch Agent on the Android device.

If you configured a list of Connection Server instances or a default Connection Server instance, AirWatch pushes the server information to the AirWatch Agent on the Android devices.

What to do next

You can use the AirWatch console to edit the Horizon Client application and push those changes to mobile devices. For example, you can add a default Connection Server instance to the server list for the Horizon Client application.

Configuring a List of Servers and a Default Server for Chromebooks

You can configure a list of Connection Server instances and a default Connection Server instance for Horizon Client for Android on enrolled Chromebooks.

When you configure a list of servers, the servers appear as shortcuts in Horizon Client. If you configure a default server, Horizon Client automatically connects to that server.

To configure a list of servers or a default server, you must create a JSON configuration file. A Chrome administrator must use the Google Admin console to upload the JSON configuration file for the Horizon Client for Android app. For detailed information about using the Google Admin console, see the G Suite Administrator Help.

For example, the following JSON configuration file specifies a list of servers. The `server` property specifies the IP address or host name of the server, the `username` and `domain` properties specify the name and domain of a user that is entitled to use the server, and the `description` property specifies a description of the server. The `username`, `domain`, and `description` properties are optional.

```
{
  "broker_list": "
    {
      \"settings\": {
        \"server-list\": [{
          \"server\": \"123.456.1.1\",
          \"description\": \"View Server 1\",
          \"username\": \"User1\",
          \"domain\": \"TestDomain1\"
        }, {
          \"server\": \"123.456.1.2\",
          \"description\": \"View Server 2\",
          \"username\": \"User2\",
          \"domain\": \"TestDomain2\"
        }, {
          \"server\": \"123.456.1.3\",
          \"description\": \"View Server 3\",
          \"username\": \"User3\",
          \"domain\": \"TestDomain3\"
        }, {
          \"server\": \"viewserver4.mydomain.com\",
          \"description\": \"View Server 4\",
          \"username\": \"User4\",
          \"domain\": \"TestDomain4\"
        }
      ]
    }
  }
}
```

The following example shows how to use the `default` property to specify a default server. Valid values are `true` and `false`.

```
{
  "broker_list": "
    {
      \"settings\": {
```

```

    \"server-list\": [{
      \"server\": \"123.456.1.1\",
      \"description\": \"View Server 1\",
      \"default\": true,
      \"username\": \"User1\",
      \"domain\": \"TestDomain1\"
    }]
  }
}

```

You can install Horizon Client for Android only on certain Chromebook models. For information, see [“System Requirements for Chromebooks,”](#) on page 8.

Configure Horizon Client in Thin Client Mode

You can configure Horizon Client to work on a thin client by enabling the **Thin Client mode** setting.

Prerequisites

Install Horizon Client on the thin client. For thin client requirements, see [“System Requirements for Thin Clients,”](#) on page 8.

Procedure

- 1 Start Horizon Client on the thin client.
- 2 Tap the **Settings** (gear) icon in the upper-right corner of the Horizon Client window.
- 3 Tap **Thin Client mode** and select the **Thin Client mode** check box.

What to do next

See [“Using Horizon Client on a Thin Client,”](#) on page 20.

Using Horizon Client on a Thin Client

Some features are different or unavailable when you use Horizon Client in thin client mode.

- The Horizon Client window resolution is set to **Auto-fit** by default. The auto-fit resolution is the same as the thin client's HDMI output. For example, if the thin client supports HDMI 4K output, the auto-fit resolution is 4K. If the thin client supports HDMI 1080p output, the auto-fit resolution is 1920x1080. You can downscale the resolution by modifying the Horizon Client **Resolution** setting.
- The Horizon Client **Presentation Mode** and **Stay Awake** display settings are not available.
- You cannot modify the Horizon Client **Keyboard** settings.
- The Horizon Client Tools radial menu is not available in remote desktops and applications.
- In general, the gestures you use in Horizon Client depend on the thin client model and the type of external input device that you use with the thin client. For example, you might have a keyboard, mouse, remote control, or game controller. See the documentation for the external input device for more information.
- The Unity Touch sidebar contains **Keyboard**, **Settings**, and **Disconnect** icons. For more information, see [“Using the Unity Touch Sidebar with a Remote Desktop,”](#) on page 48 and [“Using the Unity Touch Sidebar with a Remote Application,”](#) on page 50.
- The Unity Touch sidebar is supported on Remix Mini and NVIDIA SHIELD Android TV devices. The Unity Touch sidebar is not supported on Amazon Fire TV.

- If you are connected to a remote desktop or application from an Amazon Fire TV device, you must use a pop-up menu to display Horizon Client Settings and to disconnect from the remote desktop or application. On a remote control or external keyboard, press the **Menu** button to display the pop-up menu.

Using Embedded RSA SecurID Software Tokens

If you create and distribute RSA SecurID software tokens to end users, they need enter only their PIN, rather than their PIN and a token code, to authenticate.

Setup Requirements

You can use Compressed Token Format (CTF) or dynamic seed provisioning, which is also called CT-KIP (Cryptographic Token Key Initialization Protocol), to set up an easy-to-use RSA authentication system. With this system, you generate a URL to send to end users. To install the token, end users paste this URL directly into Horizon Client on their client devices. The dialog box for pasting this URL appears when end users connect to a Connection Server instance with Horizon Client.

Horizon Client also supports file-based provisioning. When a file-based software token is issued to a user, the authentication server generates an XML-format token file called an SDTID file. Horizon Client can import the SDTID file directly. Users can also launch Horizon Client by tapping the SDTID file in a file browser.

After the software token is installed, end users enter a PIN to authenticate. With external RSA tokens, end users must enter a PIN and the token code generated by a hardware or software authentication token.

The following URL prefixes are supported for end users that copy and paste the URL into Horizon Client when Horizon Client is connected to an RSA-enabled Connection Server instance:

- `viewclient-secrid://`
- `http://127.0.0.1/secrid/`

End users can install the token by tapping the URL. Both the `viewclient-secrid://` and `http://127.0.0.1/secrid/` prefixes are supported. Not all browsers support hyperlinks that begin with `http://127.0.0.1`. Some file browsers, such as the File Manager app on the ASUS Transformer Pad, cannot link the SDTID file with Horizon Client.

For information about using dynamic seed provisioning or file-based (CTF) provisioning, see the Web page *RSA SecurID Software Token for iPhone Devices* at <http://www.rsa.com/node.aspx?id=3652> or *RSA SecurID Software Token for Android* at <http://www.rsa.com/node.aspx?id=3832>.

Instructions to End Users

When you create a CTFString URL or CT-KIP URL to send to end users, you can generate a URL with or without a password or activation code. You send this URL to end users in an email that must include the following information:

- Instructions for navigating to the Install Software Token dialog box.
 - Tell end users to tap **External Token** in the Horizon Client dialog box that prompts them for RSA SecurID credentials when they connect to a Connection Server instance.
- CTFString URL or CT-KIP URL in plain text.
 - If the URL has formatting on it, end users will get an error message when they try to use it in Horizon Client.
- Activation code, if the CT-KIP URL that you create does not already include the activation code.
 - End users must enter this activation code in a text field of the dialog box.

- If the CT-KIP URL includes an activation code, tell end users that they need not enter anything in the **Password or Activation Code** text box in the Install Software Token dialog box.

Configure Advanced TLS/SSL Options

You can select the security protocols and cryptographic algorithms that are used to encrypt communications between Horizon Client and Horizon servers and between Horizon Client and the agent in the remote desktop.

By default, TLSv1.0, TLSv1.1, and TLSv1.2 are enabled. SSL v2.0 and 3.0 are not supported. The default cipher control string is "!aNULL:kECDH+AESGCM:ECDH+AESGCM:RSA+AESGCM:kECDH+AES:EC DH+AES:RSA+AES".

If you configure a security protocol for Horizon Client that is not enabled on the Horizon server to which the client connects, a TLS/SSL error occurs and the connection fails.

For information about configuring the security protocols that are accepted by Connection Server instances, see the *View Security* document.

Procedure

- 1 Open **Settings** and tap **Security options**.

If you are connected to a remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon and tap the gear icon to access **Settings**. If you are not using full-screen mode, **Settings** is in the menu in the upper right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

- 2 Tap **Advanced SSL Options**.
- 3 Make sure that **Use Default Settings** is unchecked.
- 4 To enable or disable a security protocol, tap the check box next to the security protocol name.
- 5 To change the cipher control string, replace the default string.
- 6 (Optional) If you need to revert to the default settings, tap to select the **Use Default Settings** option.
- 7 Tap **OK** to save your changes.

Your changes take effect the next time you connect to the server.

Configure VMware Blast Options

You can configure H.264 decoding and network condition options for remote desktop and application sessions that use the VMware Blast display protocol.

You cannot configure VMware Blast settings after you connect to a server.

JPG/PNG encoding is always used in multi-monitor mode, even when H.264 decoding is enabled.

Prerequisites

To use this feature, Horizon Agent 7.0 or later must be installed.

Procedure

- 1 Before you log in to a server, tap the **Settings** (gear) icon in the upper-right corner of the Horizon Client window and tap **VMware Blast**.

You cannot configure VMware Blast settings after you log in to a server.

- 2 Configure the decoding and network condition options.

Option	Action
H.264	<p>Configure this option to allow H.264 decoding in Horizon Client.</p> <p>When this option is selected (the default setting), Horizon Client uses H.264 decoding if the agent supports H.264 software or hardware encoding. If the agent does not support H.264 software or hardware encoding, Horizon Client uses JPG/PNG decoding.</p> <p>Deselect this option to use JPG/PNG decoding.</p>
Network Condition	<p>Select one of the following network condition options:</p> <ul style="list-style-type: none"> ■ Excellent - Horizon Client uses only TCP networking. This option is ideal for a LAN environment. ■ Typical (default) - Horizon Client works in mixed mode. In mixed mode, Horizon Client uses TCP networking when connecting to the server and uses Blast Extreme Adaptive Transport (BEAT) if the agent and Blast Security Gateway (if enabled) support BEAT connectivity. This option is the default setting. ■ Poor - Horizon Client uses only BEAT networking if the BEAT Tunnel Server is enabled on the server, otherwise it switches to mixed mode. <p>NOTE In Horizon 7 version 7.1 and earlier, Connection Server and Security Server instances do not support the BEAT Tunnel Server. Unified Access Gateway 2.9 and later supports the BEAT Tunnel Server. Blast Security Gateway for Connection Server and Security Server instances do not support BEAT networking.</p>

Changes for H.264 take effect the next time a user connects to a remote desktop or application and selects the VMware Blast display protocol. Your changes do not affect existing VMware Blast sessions.

Configure the Horizon Client Default View

You can configure whether recently used desktops and applications or server shortcuts appear when you launch Horizon Client.

Procedure

- 1 Open **Settings** and tap **Display**.

If you are connected to a remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon and tap the gear icon to access **Settings**. If you are not using full-screen mode, **Settings** is in the menu in the upper right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

- 2 Tap **Default launch view**.
- 3 Tap an option to select the default view.

Option	Description
Recent	The Recent tab appears when you launch Horizon Client. The Recent tab contains shortcuts to recently used desktops and applications. This is the default setting.
Servers	The Servers tab appears when you launch Horizon Client. The Servers tab contains shortcuts to the servers that you added to Horizon Client.

The default view you selected takes effect immediately.

Horizon Client Data Collected by VMware

If your company participates in the customer experience improvement program, VMware collects data from certain Horizon Client fields. Fields that contain sensitive information are anonymous.

VMware collects data on client systems to prioritize hardware and software compatibility. If your company's administrator has opted to participate in the customer experience improvement program, VMware collects anonymous data about your deployment to respond better to customer requirements. VMware does not collect data that identifies your organization. Horizon Client information is sent first to the Connection Server instance and then to VMware, with data from Connection Server, desktop pools, and remote desktops.

Although the information is encrypted while in transit to the Connection Server instance, the information on the client system is logged unencrypted in a user-specific directory. The logs do not contain any personally identifiable information.

The administrator who installs Connection Server can select whether to participate in the VMware customer experience improvement program while running the Connection Server installation wizard, or an administrator can set an option in Horizon Administrator after the installation.

Table 1-1. Data Collected from Horizon Clients for the Customer Experience Improvement Program

Description	Is This Field Made Anonymous ?	Example Value
Company that produced the Horizon Client application	No	VMware
Product name	No	VMware Horizon Client
Client product version	No	(The format is <i>x.x.x-yyyyyy</i> , where <i>x.x.x</i> is the client version number and <i>yyyyyy</i> is the build number.)
Client binary architecture	No	Examples include the following: <ul style="list-style-type: none"> ■ i386 ■ x86_64 ■ arm
Client build name	No	Examples include the following: <ul style="list-style-type: none"> ■ VMware-Horizon-Client-Win32-Windows ■ VMware-Horizon-Client-Linux ■ VMware-Horizon-Client-iOS ■ VMware-Horizon-Client-Mac ■ VMware-Horizon-Client-Android ■ VMware-Horizon-Client-WinStore
Host operating system	No	Examples include the following: <ul style="list-style-type: none"> ■ Windows 8.1 ■ Windows 7, 64-bit Service Pack 1 (Build 7601) ■ iPhone OS 5.1.1 (9B206) ■ Ubuntu 12.04.4 LTS ■ Mac OS X 10.8.5 (12F45)

Table 1-1. Data Collected from Horizon Clients for the Customer Experience Improvement Program (Continued)

Description	Is This Field Made Anonymous ?	Example Value
Host operating system kernel	No	Examples include the following: <ul style="list-style-type: none"> ■ Windows 6.1.7601 SP1 ■ Darwin Kernel Version 11.0.0: Sun Apr 8 21:52:26 PDT 2012; root:xnu-1878.11.10~1/RELEASE_ARM_S5L8945X ■ Darwin 11.4.2 ■ Linux 2.6.32-44-generic #98-Ubuntu SMP Mon Sep 24 17:27:10 UTC 2012 ■ unknown (for Windows Store)
Host operating system architecture	No	Examples include the following: <ul style="list-style-type: none"> ■ x86_64 ■ i386 ■ armv7l ■ ARM
Host system model	No	Examples include the following: <ul style="list-style-type: none"> ■ Dell Inc. OptiPlex 960 ■ iPad3,3 ■ MacBookPro8,2 ■ Dell Inc. Precision WorkStation T3400 (A04 03/21/2008)
Host system CPU	No	Examples include the following: <ul style="list-style-type: none"> ■ Intel(R) Core(TM)2 Duo CPU E8400 @ 3.00GH ■ Intel(R) Core(TM)2 Quad CPU Q6600 @ 2.40GH ■ unknown (for iPad)
Number of cores in the host system's processor	No	For example: 4
MB of memory on the host system	No	Examples include the following: <ul style="list-style-type: none"> ■ 4096 ■ unknown (for Windows Store)
Number of USB devices connected	No	2 (USB device redirection is supported only for Linux, Windows, and Mac clients.)
Maximum concurrent USB device connections	No	2
USB device vendor ID	No	Examples include the following: <ul style="list-style-type: none"> ■ Kingston ■ NEC ■ Nokia ■ Wacom
USB device product ID	No	Examples include the following: <ul style="list-style-type: none"> ■ DataTraveler ■ Gamepad ■ Storage Drive ■ Wireless Mouse

Table 1-1. Data Collected from Horizon Clients for the Customer Experience Improvement Program (Continued)

Description	Is This Field Made Anonymous ?	Example Value
USB device family	No	Examples include the following: <ul style="list-style-type: none">■ Security■ Human Interface Device■ Imaging
USB device usage count	No	(Number of times the device was shared)

Using URIs to Configure Horizon Client

2

Using uniform resource identifiers (URIs), you can create a Web page or an email with links that end users click to start Horizon Client, connect to a server, and open a specific desktop or application with specific configuration options.

You can simplify the process of connecting to a remote desktop or application by creating Web or email links for end users. You create these links by constructing URIs that provide some or all the following information, so that your end users do not need to supply it:

- Connection Server address
- Port number for Connection Server
- Active Directory user name
- RADIUS or RSA SecurID user name, if different from the Active Directory user name
- Domain name
- Desktop or application display name
- Actions including reset, log out, and start session

To construct a URI, you use the `vmware-view` URI scheme with Horizon Client specific path and query parts.

NOTE You can use URIs to start Horizon Client only if the client software is already installed on client computers.

This chapter includes the following topics:

- [“Syntax for Creating vmware-view URIs,”](#) on page 27
- [“Examples of vmware-view URIs,”](#) on page 30

Syntax for Creating vmware-view URIs

Syntax includes the `vmware-view` URI scheme, a path part to specify the desktop or application, and, optionally, a query to specify desktop or application actions or configuration options.

URI Specification

Use the following syntax to create URIs to start Horizon Client:

```
vmware-view://[authority-part]/[path-part][?query-part]
```

The only required element is the URI scheme, `vmware-view`. For some versions of some client operating systems, the scheme name is case-sensitive. Therefore, use `vmware-view`.

IMPORTANT In all parts, non-ASCII characters must first be encoded according to UTF-8 [STD63], and then each octet of the corresponding UTF-8 sequence must be percent-encoded to be represented as URI characters.

For information about encoding for ASCII characters, see the URL encoding reference at <http://www.utf8-chartable.de/>.

authority-part Specifies the server address and, optionally, a user name, a non-default port number, or both. Underscores (`_`) are not supported in server names. Server names must conform to DNS syntax.

To specify a user name, use the following syntax:

`user1@server-address`

You cannot specify a UPN address, which includes the domain. To specify the domain, you can use the `domainName` query part in the URI.

To specify a port number, use the following syntax:

`server-address:port-number`

path-part Specifies the desktop or application. Use the desktop display name or application display name. This name is the one specified in Horizon Administrator when the desktop or application pool was created. If the display name has a space in it, use the `%20` encoding mechanism to represent the space.

query-part Specifies the configuration options to use or the desktop or application actions to perform. Queries are not case-sensitive. To use multiple queries, use an ampersand (`&`) between the queries. If queries conflict with each other, the last query in the list is used. Use the following syntax:

`query1=value1[&query2=value2...]`

Supported Queries

This topic lists the queries that are supported for this type of Horizon Client. If you are creating URIs for multiple types of clients, such as desktop clients and mobile clients, see the *Using VMware Horizon Client* guide for each type of client system.

action

Table 2-1. Values That Can Be Used With the action Query

Value	Description
<code>browse</code>	Displays a list of available desktops and applications hosted on the specified server. You are not required to specify a desktop or application when using this action. If you use the <code>browse</code> action and specify a desktop or application, the desktop or application is highlighted in the list of available items.
<code>start-session</code>	Opens the specified desktop or application. If no action query is provided and the desktop or application name is provided, <code>start-session</code> is the default action.

Table 2-1. Values That Can Be Used With the action Query (Continued)

Value	Description
reset	Shuts down and restarts the specified desktop. Unsaved data is lost. Resetting a remote desktop is the equivalent of pressing the Reset button on a physical PC. Specifying an application is not supported. If you specify an application, an error message appears. If you do not specify a desktop or application, Horizon Client quits all remote applications.
restart	Shuts down and restarts the specified desktop. Restarting a remote desktop is the equivalent of the Windows operating system restart command. The operating system usually prompts the user to save any unsaved data before it restarts.
logoff	Logs the user out of the guest operating system in the remote desktop. If you specify an application, the action is ignored or the end user sees the warning message "Invalid URI action."

args	Specifies command-line arguments to add to remote application launch. Use the syntax <code>args=value</code> , where <i>value</i> is a string. Use percent encoding for the following characters: <ul style="list-style-type: none"> ■ For a colon (:), use <code>%3A</code> ■ For a back slash (\), use <code>%5C</code> ■ For a space (), use <code>%20</code> ■ For a double quotation mark ("), use <code>%22</code> For example, to specify the filename "My new file.txt" for the Notepad++ application, use <code>%22My%20new%20file.txt%22</code> .
appProtocol	For remote applications, valid values are PCOIP and BLAST . For example, to specify PCoIP, use the syntax <code>appProtocol=PCOIP</code> .
defaultLaunchView	Sets the default launch view for Horizon Client. Valid values are recent and servers .
desktopProtocol	For remote desktops, valid values are PCOIP and BLAST . For example, to specify PCoIP, use the syntax <code>desktopProtocol=PCOIP</code> .
domainName	The NETBIOS domain name associated with the user who is connecting to the remote desktop or application. For example, you might use <code>mycompany</code> rather than <code>mycompany.com</code> .
tokenUserName	Specifies the RSA or RADIUS user name. Use this query only if the RSA or RADIUS user name is different from the Active Directory user name. If you do not specify this query and RSA or RADIUS authentication is required, the Windows user name is used. The syntax is <code>tokenUserName=name</code> .

unauthenticatedAccess Enabled	If this option is set to true , the Unauthenticated Access feature is enabled by default. If this option is set to false , the Unauthenticated Access feature is disabled. When this option is set to "", the Unauthenticated Access feature is disabled. The Log in anonymously using Unauthenticated Access option is available in the Horizon Client settings. An example of the syntax is unauthenticatedAccessEnabled=true .
unauthenticatedAccess Account	Sets the account to use if the Unauthenticated Access feature is enabled. If Unauthenticated Access is disabled, then this query is ignored. An example of the syntax using the anonymous1 user account is unauthenticatedAccessAccount=anonymous1 .

Examples of vmware-view URIs

You can create hypertext links or buttons with the `vmware-view` URI scheme and include these links in email or on a Web page. Your end users can click these links to, for example, open a particular remote desktop with the startup options you specify.

URI Syntax Examples

Each URI example is followed by a description of what the end user sees after clicking the URI link.

1 `vmware-view://view.mycompany.com/Primary%20Desktop?action=start-session`

Horizon Client starts and connects to the `view.mycompany.com` server. The login box prompts the user for a user name, domain name, and password. After a successful login, the client connects to the desktop whose display name is displayed as **Primary Desktop**, and the user is logged in to the guest operating system.

NOTE The default display protocol and window size are used. The default display protocol is PCoIP. The default window size is full screen.

2 `vmware-view://view.mycompany.com:7555/Primary%20Desktop`

This URI has the same effect as the previous example, except that it uses the nondefault port of 7555 for Connection Server. (The default port is 443.) Because a desktop identifier is provided, the desktop opens even though the `start-session` action is not included in the URI.

3 `vmware-view://fred@view.mycompany.com/Finance%20Desktop?desktopProtocol=PCoIP`

Horizon Client starts and connects to the `view.mycompany.com` server. In the login box, the **User name** text box is populated with the name **fred**. The user must supply the domain name and password. After a successful login, the client connects to the desktop whose display name is displayed as **Finance Desktop**, and the user is logged in to the guest operating system. The connection uses the PCoIP display protocol.

4 `vmware-view://view.mycompany.com/Calculator?action=start-session&appProtocol=BLAST`

Horizon Client starts and connects to the `view.mycompany.com` server. In the login box, the user must supply the user name, domain name, and password. After a successful login, the client connects to the application whose display name is displayed as **Calculator**. The connection uses the VMware Blast display protocol.

5 `vmware-view://fred@view.mycompany.com/Finance%20Desktop?domainName=mycompany`

Horizon Client starts and connects to the `view.mycompany.com` server. In the login box, the **User name** text box is populated with the name **fred**, and the **Domain** text box is populated with **mycompany**. The user must supply only a password. After a successful login, the client connects to the desktop whose display name is displayed as **Finance Desktop**, and the user is logged in to the guest operating system.

6 `vmware-view://view.mycompany.com/`

Horizon Client starts and the user is taken to the login prompt for connecting to the `view.mycompany.com` server.

7 `vmware-view://view.mycompany.com/Primary%20Desktop?action=reset`

Horizon Client starts and connects to the `view.mycompany.com` server. The login box prompts the user for a user name, domain name, and password. After a successful login, Horizon Client displays a dialog box that prompts the user to confirm the reset operation for Primary Desktop.

NOTE This action is available only if a Horizon administrator has enabled the desktop reset feature for the desktop.

8 `vmware-view://view.mycompany.com/Primary%20Desktop?action=restart`

Horizon Client starts and connects to the `view.mycompany.com` server. The login box prompts the user for a user name, domain name, and password. After a successful login, Horizon Client displays a dialog box that prompts the user to confirm the restart operation for Primary Desktop.

NOTE This action is available only if a Horizon administrator has enabled the desktop restart feature for the desktop.

9 `vmware-view://view.mycompany.com?action=reset`

Horizon Client starts and connects to the `view.mycompany.com` server. The login box prompts the user for a user name, domain name, and password. After a successful login, Horizon Client displays a dialog box that prompts the user to confirm the reset operation for all remote applications.

10 `vmware-view://`

If the client is already running, the Horizon Client application comes to the foreground. If the client is not already running, Horizon Client starts.

11 `vmware-view://?defaultlaunchview=recent`

Horizon Client starts and the user sees the **Recent** tab.

12 `vmware-view://10.10.10.10/My%20Notepad++?args=%22My%20new%20file.txt%22`

Launches My Notepad++ on server 10.10.10.10 and passes the argument `My new file.txt` in the application launch command. The filename is enclosed in double quotes because it contains spaces.

13 `vmware-view://10.10.10.10/Notepad++%2012?args=a.txt%20b.txt`

Launches Notepad++ 12 on server 10.10.10.10 and passes the argument `a.txt b.txt` in the application launch command. Because the argument is not enclosed in quotes, a space separates the filenames and the two files are opened separately in Notepad++.

NOTE Applications can differ in the way they use command line arguments. For example, if you pass the argument `a.txt b.txt` to Wordpad, Wordpad will open only one file, `a.txt`.

14 `vmware-view://view.mycompany.com/Notepad?unauthenticatedAccessEnabled=true&unauthenticatedAccessAccount=anonymous1`

Horizon Client starts and connects to the `view.mycompany.com` server using the **anonymous1** user account. The Notepad application is launched without prompting the user to provide login credentials.

HTML Code Examples

You can use URIs to make hypertext links and buttons to include in emails or on Web pages. The following examples show how to use the URI from the first URI example to code a hypertext link that says, **Test Link**, and a button that says, **TestButton**.

```
<html>
<body>

<a href="vmware-view://view.mycompany.com/Primary%20Desktop?action=start-session">Test
Link</a><br>

<form><input type="button" value="TestButton" onClick="window.location.href=
'vmware-view://view.mycompany.com/Primary%20Desktop?action=start-session'"></form> <br>

</body>
</html>
```

Managing Remote Desktop and Application Connections

3

End users can use Horizon Client to connect to a server, edit the list of servers they connect to, log in to or off of remote desktops, and use remote applications. For troubleshooting purposes, end users can also reset remote desktops and applications.

Depending on how you configure policies for remote desktops, end users might be able to perform many operations on their desktops.

This chapter includes the following topics:

- [“Setting the Certificate Checking Mode in Horizon Client,”](#) on page 33
- [“Connect to a Remote Desktop or Application,”](#) on page 34
- [“Use Unauthenticated Access to Connect to Remote Applications,”](#) on page 36
- [“Share Access to Local Storage with Client Drive Redirection,”](#) on page 37
- [“Add a Remote Desktop or Application Shortcut to the Android Home Screen,”](#) on page 38
- [“Manage Server Shortcuts,”](#) on page 39
- [“Select a Favorite Remote Desktop or Application,”](#) on page 39
- [“Disconnecting From a Remote Desktop or Application,”](#) on page 40
- [“Log Off From a Remote Desktop,”](#) on page 40
- [“Manage Desktop and Application Shortcuts,”](#) on page 41
- [“Using Android 7.0 Nougat Multi-Window Modes with Horizon Client,”](#) on page 41
- [“Using Horizon Client with Samsung DeX,”](#) on page 41

Setting the Certificate Checking Mode in Horizon Client

You can determine whether client connections are rejected if any or some server certificate checks fail by configuring a setting in Horizon Client.

Certificate checking occurs for SSL connections between the server and Horizon Client. Certificate verification includes the following checks:

- Is the certificate intended for a purpose other than verifying the identity of the sender and encrypting server communications? That is, is it the correct type of certificate?
- Has the certificate expired, or is it valid only in the future? That is, is the certificate valid according to the computer clock?

- Does the common name on the certificate match the host name of the server that sends it? A mismatch can occur if a load balancer redirects Horizon Client to a server that has a certificate that does not match the host name entered in Horizon Client. Another reason a mismatch can occur is if you enter an IP address rather than a host name in the client.
- Is the certificate signed by an unknown or untrusted certificate authority (CA)? Self-signed certificates are one type of untrusted CA.

To pass this check, the certificate's chain of trust must be rooted in the device's local certificate store.

IMPORTANT For information about distributing a self-signed root certificate that users can install on their Android devices, as well as instructions for installing a certificate on an Android device, see the documentation on the Google Web site, such as the *Android 3.0 User's Guide*.

To set the certificate checking mode, start Horizon Client and open **Settings**. In **Settings**, tap **Security options** and tap **Security mode**. You have three choices:

- **Never connect to untrusted servers.** If any of the certificate checks fails, the client cannot connect to the server. An error message lists the checks that failed.
- **Warn before connecting to untrusted servers.** If a certificate check fails because the server uses a self-signed certificate, you can click **Continue** to ignore the warning. For self-signed certificates, the certificate name is not required to match the server name you entered in Horizon Client.
- **Do not verify server identity certificates.** This setting means that no certificate checking occurs.

If the certificate checking mode is set to **Warn**, you can still connect to a server that uses a self-signed certificate.

If an administrator later installs a security certificate from a trusted certificate authority, so that all certificate checks pass when you connect, this trusted connection is remembered for that specific server. In the future, if that server ever presents a self-signed certificate again, the connection fails. After a particular server presents a fully verifiable certificate, it must always do so.

Connect to a Remote Desktop or Application

To connect to a remote desktop or application, you must provide the name of a server and supply credentials for your user account.

Before you have end users access their remote desktops and applications, test that you can connect to a remote desktop or application from a client device. You might need to specify a server and supply credentials for your user account.

Prerequisites

- Obtain login credentials, such as a user name and password, RSA SecurID user name and passcode, RADIUS authentication user name and passcode, or smart card personal identification number (PIN).
- Obtain the NETBIOS domain name for logging in. For example, you might use *mycompany* rather than *mycompany.com*.
- Perform the administrative tasks described in [“Preparing Connection Server for Horizon Client,”](#) on page 12.
- If you are outside the corporate network and require a VPN connection to access remote desktops and applications, verify that the client device is set up to use a VPN connection and turn on that connection.
- Verify that you have the fully qualified domain name (FQDN) of the server that provides access to the remote desktop or application. Underscores (_) are not supported in server names. If the port is not 443, you also need the port number.

- If you plan to use embedded RSA SecurID software, verify that you have the correct CT-KIP URL and activation code. See [“Using Embedded RSA SecurID Software Tokens,”](#) on page 21.
- Configure the certificate checking mode for the SSL certificate presented by the server. See [“Setting the Certificate Checking Mode in Horizon Client,”](#) on page 33.
- If you plan to use fingerprint authentication, verify that the Fingerprint Authentication option is enabled and at least one fingerprint is enrolled on the Android device. For complete fingerprint authentication requirements, see [“Fingerprint Authentication Requirements,”](#) on page 11.

Procedure

- 1 If a VPN connection is required, turn on the VPN.
- 2 On the Android device, tap the **Horizon** app icon.
- 3 Connect to a server.

Option	Action
Connect to a new server	Enter the name of a server, enter a description (optional), and tap Connect .
Connect to an existing server	Tap the server shortcut on the Servers tab.

Connections between Horizon Client and servers always use SSL. The default port for SSL connections is 443. If the server is not configured to use the default port, use the format shown in this example: **view.company.com:1443**.

- 4 If a smart card is required or optional, select the smart card certificate to use and enter your PIN.
If your smart card has only one certificate, that certificate is already selected. If there are many certificates, you can scroll through the certificates.
- 5 If you are prompted for RSA SecurID credentials or RADIUS authentication credentials, either type your credentials or, if you plan to use an embedded RSA SecurID token, install an embedded token.

Option	Action
Existing token	If you use a hardware authentication token or software authentication token on a smart phone, enter your user name and passcode. The passcode might include both a PIN and the generated number on the token.
Install software token	Tap External Token . In the Install Software Token dialog box, paste the CT-KIP URL or CTFString URL that your administrator sent to you in email. If the URL contains an activation code, you do not need to enter anything in the Password or Activation Code text box.

- 6 If you are prompted a second time for RSA SecurID credentials or RADIUS authentication credentials, enter the next generated number on the token.
Do not enter your PIN, and do not enter the same generated number that you entered before. If necessary, wait until a new number is generated.
If this step is required, it is required only when you mistype the first passcode or when configuration settings in the RSA server change.
- 7 If you are prompted for a user name and password, supply your Active Directory credentials.
 - a Type the user name and password of a user who is entitled to use at least one desktop or application pool.
 - b Select a domain.
If the **Domain** drop-down menu is hidden, type the user name as **username@domain** or **domain\username**.

- c (Optional) If the **Enable Fingerprint** check box is available, select it to use fingerprint authentication.
The **Enable Fingerprint** check box is available only if biometric authentication is enabled on the server and you have not previously authenticated with fingerprint authentication.
- d (Optional) Select the **Save Password** check box if your administrator has enabled this feature and if the server certificate can be fully verified.

If this is the first time you are saving a password, you are prompted to activate the device administrator, which is required to save a password on Android devices.

- e Tap **Connect**.

If fingerprint authentication is enabled and you are logging in for the first time, your Active Directory credentials are stored securely in the Android device's database for future use.

- 8 If you are prompted for fingerprint authentication, place your finger on the fingerprint sensor.
If you do not want to use fingerprint authentication, tap **Cancel**. You can connect to the server again and tap **Use password** to enter a user name and password.
- 9 (Optional) Tap the display protocol settings icon in the upper-right corner of the window to select the display protocol to use.
VMware Blast provides better battery life and is the best protocol for high-end 3D and mobile device users.
- 10 Tap a desktop or application to connect to it.
If you are connecting to a published desktop, and if the desktop is already set to use the Microsoft RDP display protocol, you cannot connect immediately. You are prompted to have the system log you off the remote operating system so that a connection can be made with the PCoIP display protocol or the VMware Blast display protocol.

After you connect to a desktop or application for the first time, a shortcut for the desktop or application is saved to the **Recent** tab. The next time you want to connect to the remote desktop or application, you can tap the shortcut instead of tapping the server icon.

Use Unauthenticated Access to Connect to Remote Applications

A Horizon administrator can use the Unauthenticated Access feature to create Unauthenticated Access users and entitle those users to remote applications on a Connection Server instance. Unauthenticated Access users can log in to the server anonymously to connect to their remote applications.

Before you have end users access a remote application with the Unauthenticated User feature, test that you can connect to the remote application from a client device. You might need to specify a server and supply credentials for your user account.

Prerequisites

- Perform the administrative tasks described in [“Preparing Connection Server for Horizon Client,”](#) on page 12.
- Set up Unauthenticated Access users on the Connection Server instance. For information, see [“Providing Unauthenticated Access for Published Applications”](#) in the *View Administration* document.
- Configure the certificate checking mode for the SSL certificate presented by the server. See [“Setting the Certificate Checking Mode in Horizon Client,”](#) on page 33.
- If you are accessing remote applications outside of the corporate network, verify that your client device is set up to use a VPN connection and turn on that connection.

Procedure

- 1 If a VPN connection is required, turn on the VPN.
- 2 On the Android device, tap the **Horizon** app icon.
- 3 Tap the **Settings** (gear) icon in the upper-right corner of the Horizon Client window, tap **Unauthenticated access**, and select the **Unauthenticated access** check box.
- 4 Connect to the server on which you have unauthenticated access to remote applications.

Option	Description
Connect to a new server	Enter the name of a server, enter a description (optional), and tap Connect .
Connect to an existing server	Tap the server shortcut on the Servers tab.

Connections between Horizon Client and servers always use SSL. The default port for SSL connections is 443. If the server is not configured to use the default port, use the format shown in this example: `view.company.com:1443`.

- 5 When the login window appears, select a user account from the **User account** drop-down menu, if required.
If only one user account is available, the user account is automatically selected.
- 6 (Optional) Select the **Always use this account** check box to bypass the login window the next time you connect to the server.
To deselect this setting before you connect to the server the next time, touch and hold the server shortcut until the context menu appears, tap **Edit**, tap **Forget the saved Unauthenticated Access account (name)**, and tap **Done**.
- 7 Tap **Connect** to log in to the server.
The application selection window appears.
- 8 Tap an application icon to start the application.

After you connect to a remote application for the first time, a shortcut for the application is saved to the **Recent** tab. The next time you want to connect to the application, you can tap the shortcut instead of tapping the server icon.

Share Access to Local Storage with Client Drive Redirection

You can configure Horizon Client to share local storage with a remote desktop or application. This feature is called client drive redirection.

In a Windows remote desktop or remote application, local storage appears in the **Devices and drives** section in the **This PC** folder, or in the **Other** section in the **Computer** folder. The folders and storage devices that you select for sharing use the naming format *name on HorizonClient*.

Prerequisites

- Enable the client drive redirection feature. This task includes installing View Agent 6.1.1 or later, or Horizon Agent 7.0 or later, and enabling the agent **Client Drive Redirection** option. It can also include setting policies or registry settings to control client drive redirection behavior. For more information, see the *Configuring Remote Desktop Features in Horizon 7* document.
- Connect to the remote desktop or application with which you want to share local storage. If you have not logged in at least once, become familiar with the procedure [“Connect to a Remote Desktop or Application,”](#) on page 34.

Procedure

- 1 Open **Settings** and tap **Local storage redirection**.

If you are connected to the remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon and tap the gear icon. If you are not using full-screen mode, **Settings** is in the menu in the upper-right corner of the Horizon Client toolbar.

- 2 Tap **Local Storage Redirection** and configure the local storage redirection options.

Option	Action
Automatically share all removable storage devices	Select the Enable auto direct for mounted storage check box. All removable storage devices mounted to your device are automatically shared with the remote desktop or application. This option is selected by default.
Do not automatically share all removable storage devices	Deselect the Enable auto direct for mounted storage check box. The next time you connect to the remote desktop or application, removable storage devices mounted to your device are not automatically shared with the remote desktop or application. NOTE Deselecting the Enable auto direct for mounted storage check box does not stop sharing a removable storage device that is already shared with the remote desktop or application.
Share a specific folder or removable storage device	Select the check box next to the name of the local folder or removable storage device in the list. The device becomes available in the remote desktop or application. When you connect a removable storage device, its name appears in the list. When you disconnect a removable storage device, its name is removed from the list.
Stop sharing a specific folder or removable storage device	Deselect the check box next to the name of the local folder or removable storage device in the list. The device is no longer available in the remote desktop or application.

- 3 Tap **OK** to save your settings.

What to do next

Verify your changes from within the remote desktop or application.

- From within a Windows remote desktop, open the **This PC** folder and look in the **Devices and drives** section, or open the **Computer** folder and look in the **Other** section. If you shared a folder or storage device, you should see the folder or device. Shared folders and storage devices use the naming format *name on HorizonClient*.
- From a remote application, select **File > Open** or **File > Save As**, if applicable. If you shared a folder or storage device, you should be able to navigate to the folder or device. Shared folders and storage devices use the naming format *name on HorizonClient*.

Add a Remote Desktop or Application Shortcut to the Android Home Screen

You can add a shortcut for a remote desktop or application to the Android home screen and then tap the shortcut to open the remote desktop or application.

On Android 4 through 7 devices, Horizon Client adds the remote desktop or application shortcut to the Android home screen.

On Android 8 devices, remote desktop and application shortcuts appear as entries above the **Horizon** app icon when you touch and hold the app icon. You can drag an entry from the app icon to the Android home screen to create a shortcut directly on the Android home screen.

When Horizon Client for Android is installed on a Chromebook, Horizon Client adds the remote desktop or application shortcut to the Chrome App Launcher.

This feature is not available on Amazon devices, on Android devices that are managed by AirWatch, or when you connect to the server anonymously by using the Unauthenticated Access feature.

Procedure

- 1 You can add a desktop or application shortcut before or after you connect to a server.

If you are not connected to a server, you must have connected to the remote desktop or application at least once from the device so that a shortcut for the desktop or application appears on the **Recent** tab.

Option	Action
If you have not connected to a server	On the Recent tab, touch and hold the shortcut until Add To Home appears at the bottom of the window and then drag the shortcut to Add To Home .
If you are connected to a server	On the All or Favorites tab, touch and hold the desktop or application shortcut until the context menu appears and tap Add To Home .

- 2 Type a name for the shortcut and tap **OK**.

If the name is longer than 12 characters, the extra characters do not appear on the Android home screen.

Manage Server Shortcuts

After you connect to a server, Horizon Client creates a server shortcut. You can edit and remove server shortcuts.

Horizon Client saves the server name or IP address in a shortcut, even if you mistype the server name or type the wrong IP address. You can delete or change this information by editing the server name or IP address. If you do not type a server description, the server name or IP address becomes the server description.

Server shortcuts can appear on multiple pages and you can swipe across pages to see more shortcuts. Horizon Client creates new pages, as needed, to accommodate all of your server shortcuts.

Procedure

- 1 On the **Servers** tab, touch and hold the server shortcut until the context menu appears.
- 2 Use the context menu to delete the server or edit the server name, server description, or user name.

You can also remove a credential that was saved for fingerprint authentication by tapping **Remove Credential**.

Select a Favorite Remote Desktop or Application

You can select remote desktops and applications as favorites. Favorites are identified by a star. The star helps you quickly find your favorite desktops and applications. Your favorite selections are saved, even after you log off from the server.

Prerequisites

Obtain the credentials you need to connect to the server, such as a user name and password or RSA SecurID and passcode.

Procedure

- 1 On the **Servers** tab, tap the server shortcut to connect to the server.

- 2 If prompted, supply your RSA user name and passcode, your Active Directory user name and password, or both.
- 3 Perform these steps to select or deselect a desktop or application as a favorite.

Option	Action
Select a favorite	Touch and hold the desktop or application name until the context menu appears and tap Mark as Favorite . A star appears in the upper right corner of the name and the name appears on the Favorites tab.
Deselect a favorite	On the All or Favorites tab, touch and hold the desktop or application name until the context menu appears and tap Unmark Favorite . A star no longer appears in the upper right corner of the name and the name disappears from the Favorites tab.

- 4 (Optional) Tap the **Favorites** tab to display only favorite desktops or applications.
You can tap the **All** tab to display all the available desktops and applications.

Disconnecting From a Remote Desktop or Application

You can disconnect from a remote desktop without logging off, so that applications remain open on the remote desktop. You can also disconnect from a remote application so that the remote application remains open.

On a mobile device, when you are using a remote desktop or application in full-screen mode, you can disconnect by tapping the Horizon Client Tools radial menu icon and tapping the **Disconnect** icon. If you are not using full-screen mode, **Disconnect** is in the menu in the upper-right corner of the Horizon Client toolbar.

On a thin client, when you are connected to a remote desktop or application, you disconnect by clicking the **Disconnect** icon in the Unity Touch sidebar or in a pop-up menu, depending on your thin client model. For more information, see [“Using Horizon Client on a Thin Client,”](#) on page 20.

NOTE A Horizon administrator can configure a remote desktop to automatically log off when it is disconnected. In that case, any open programs in the remote desktop are stopped.

Log Off From a Remote Desktop

You can log off from a remote desktop operating system, even if you do not have a desktop open in Horizon Client. If you are currently connected to and logged in to a remote desktop, you can use the Windows **Start** menu to log off. After Windows logs you off, the desktop is disconnected.

Prerequisites

Obtain the credentials that you use to log in, such as your Active Directory user name and password, RSA SecurID user name and passcode, or RADIUS authentication user name and passcode.

Procedure

- 1 On the **Servers** tab, tap the server shortcut.
- 2 If prompted, supply your RSA user name and passcode, your Active Directory user name and password, or both.
- 3 Touch and hold the desktop name until the context menu appears.
You can perform this step from either the **All** or **Favorites** tab.
- 4 Tap **Log Off** in the context menu.

Any unsaved files that are open on the remote desktop are closed during the logoff operation.

What to do next

Tap the Android Back button or the **Disconnect** icon in the upper-right corner of the window and tap **Log Out** to disconnect from the server.

Manage Desktop and Application Shortcuts

After you connect to a remote desktop or application, Horizon Client saves a shortcut for the recently used desktop or application. You can rearrange and remove these shortcuts.

Desktop and application shortcuts can appear on multiple pages and you can swipe across pages to see more shortcuts. Horizon Client creates new pages, as needed, to accommodate all of your shortcuts.

Procedure

- Perform these steps to remove a desktop or application shortcut from the **Recent** tab.
 - a Touch and hold the shortcut until **Remove Shortcut** appears at the bottom of the window.
 - b Drag the shortcut to **Remove Shortcut**.
- To move a desktop or application shortcut, touch and hold the shortcut and drag it to the new location. You cannot drag a shortcut to another page unless that page already exists.

Using Android 7.0 Nougat Multi-Window Modes with Horizon Client

Android 7.0 Nougat allows several apps to share the screen at the same time. You can use split-screen mode with Horizon Client on an Android 7.0 Nougat device. Horizon Client does not support picture-in-picture mode.

With split-screen mode, you can run Horizon Client and another app side-by-side, or one-above-the other. A dividing line separates the two apps, and you can make one app larger and the other app smaller.

Using Horizon Client with Samsung DeX

If the Android device supports Samsung DeX, you can use Horizon Client in DeX desktop mode.

When the device is in DeX desktop mode, Horizon Client treats the device as a thin client and **Thin Client mode** is enabled. For more information, see [“Using Horizon Client on a Thin Client,”](#) on page 20.

The following features are supported when you use Horizon Client in Horizon DeX desktop mode:

- You can configure Horizon Client to start automatically when you switch to DeX desktop mode. See [“Enable the DeX Mode Auto Launch Feature,”](#) on page 41.
- Desktop and application sessions continue to run after you enter or exit from DeX desktop mode.
- If Horizon Client is maximized, remote desktops enter full-screen mode after you switch to DeX desktop mode..
- You can use the language switch key on a Samsung physical keyboard to switch the language input method in a remote desktop.

Enable the DeX Mode Auto Launch Feature

You can configure Horizon Client to start automatically when you switch the Android device to DeX desktop mode.

If you added a desktop or application shortcut to the Android home screen, Horizon Client connects to the most recent shortcut after Horizon Client starts. For information about adding shortcuts to the Android home screen, see [“Add a Remote Desktop or Application Shortcut to the Android Home Screen,”](#) on page 38.

The DeX mode auto launch feature is disabled by default.

You cannot enable the DeX mode auto launch feature if a default Connection Server instance is configured for Horizon Client.

Prerequisites

Verify that the Android device supports Samsung DeX.

Procedure

- 1 Before you log in to a server, tap the **Settings** (gear) icon in the upper-right corner of the Horizon Client window.
- 2 Tap **Display**, tap **Dex Mode Auto Launch**, and select the **Dex Mode Auto Launch** check box.

Using a Microsoft Windows Desktop or Application

4

Horizon Client for Android includes additional features to aid in navigation on Android devices and thin clients. Users can use external devices with remote desktops and applications, copy text and images from client devices to remote desktops and applications, and save documents in remote applications.

This chapter includes the following topics:

- [“Feature Support Matrix for Android,”](#) on page 44
- [“Input Devices, Keyboards, and Keyboard Settings,”](#) on page 46
- [“Enable the Japanese 106/109 Keyboard Layout,”](#) on page 46
- [“Using the Real-Time Audio-Video Feature,”](#) on page 47
- [“Using Native Operating System Gestures with Touch Redirection,”](#) on page 47
- [“Using the Unity Touch Sidebar with a Remote Desktop,”](#) on page 48
- [“Using the Unity Touch Sidebar with a Remote Application,”](#) on page 50
- [“Horizon Client Tools on a Mobile Device,”](#) on page 52
- [“Gestures,”](#) on page 54
- [“Multitasking,”](#) on page 55
- [“Copying and Pasting Text and Images,”](#) on page 55
- [“Saving Documents in a Remote Application,”](#) on page 56
- [“Screen Resolutions and Using External Displays,”](#) on page 56
- [“PCoIP Client-Side Image Cache,”](#) on page 57
- [“Internationalization and International Keyboards,”](#) on page 58

Feature Support Matrix for Android

Some features are supported on one type of Horizon Client but not on another.

Table 4-1. Features Supported on Windows Desktops for Android Horizon Clients

Feature	Windows 10 Desktop	Windows 8.x Desktop	Windows 7 Desktop	Windows Vista Desktop	Windows XP Desktop	Windows Server 2008/2012 R2 or Windows Server 2016 Desktop
RSA SecurID or RADIUS	X	X	X	Limited	Limited	X
Single sign-on	X	X	X	Limited	Limited	X
RDP display protocol						
PCoIP display protocol	X	X	X	Limited	Limited	X
VMware Blast display protocol	X	X	X			X
USB redirection						
Client drive redirection	X	X	X			X
Real-Time Audio-Video	X	X	X			X
Wyse MMR						
Windows 7 MMR						
Virtual printing						
Location-based printing	X	X	X	Limited	Limited	X
Smart cards	X	X	X	Limited	Limited	X
Multiple monitors						

Windows 10 desktops require View Agent 6.2 or later or Horizon Agent 7.0 or later. Windows Server 2012 R2 desktops require View Agent 6.1 or later or Horizon Agent 7.0 or later. Windows Server 2016 desktops require Horizon Agent 7.0.2 or later.

IMPORTANT View Agent 6.1 and later and Horizon Agent 7.0 and later releases do not support Windows XP and Windows Vista desktops. View Agent 6.0.2 is the last View release that supports these guest operating systems. Customers who have an extended support agreement with Microsoft for Windows XP and Vista, and an extended support agreement with VMware for these guest operating systems, can deploy the View Agent 6.0.2 version of their Windows XP and Vista desktops with Connection Server 6.1.

For descriptions of these features, see the *View Planning* document.

Feature Support for Published Desktops on RDS Hosts

RDS hosts are server computers that have Windows Remote Desktop Services and View Agent or Horizon Agent installed. Multiple users can have desktop sessions on an RDS host simultaneously. An RDS host can be either a physical machine or a virtual machine.

NOTE The following table contains rows only for the features that are supported. Where the text specifies a minimum version of View Agent, the text "and later" is meant to include Horizon Agent 7.0.x and later.

Table 4-2. Features Supported for RDS Hosts with View Agent 6.0.x or Later, or Horizon Agent 7.0.x or Later, Installed

Feature	Windows Server 2008 R2 RDS Host	Windows Server 2012 RDS Host	Windows Server 2016 RDS Host
RSA SecurID or RADIUS	X	X	Horizon Agent 7.0.2 and later
Smart card	View Agent 6.1 and later	View Agent 6.1 and later	Horizon Agent 7.0.2 and later
Single sign-on	X	X	Horizon Agent 7.0.2 and later
RDP display protocol (for desktop clients)	X	X	Horizon Agent 7.0.2 and later
PCoIP display protocol	X	X	Horizon Agent 7.0.2 and later
VMware Blast display protocol	Horizon Agent 7.0 and later	Horizon Agent 7.0 and later	Horizon Agent 7.0.2 and later
HTML Access	View Agent 6.0.2 and later (virtual machine only)	View Agent 6.0.2 and later (virtual machine only)	Horizon Agent 7.0.2 and later
Client drive redirection	View Agent 6.1.1 and later	View Agent 6.1.1 and later	Horizon Agent 7.0.2 and later
Virtual printing (for desktop clients)	View Agent 6.0.1 and later (virtual machine only)	View Agent 6.0.1 and later (virtual machine only)	Horizon Agent 7.0.2 and later (virtual machine only)
Location-based printing	View Agent 6.0.1 and later (virtual machine only)	View Agent 6.0.1 and later (virtual machine only)	Horizon Agent 7.0.2 and later (virtual machine only)
Multiple monitors (for desktop clients)	X	X	Horizon Agent 7.0.2 and later
Unity Touch (for mobile and Chrome OS clients)	X	X	Horizon Agent 7.0.2 and later
Real-Time Audio-Video (RTAV)	Horizon Agent 7.0.2 and later	Horizon Agent 7.0.2 and later	Horizon Agent 7.0.3 and later

For information about which editions of each guest operating system are supported, see the *View Installation* document.

Limitations for Specific Features

Specific features that are supported on Windows desktops for Horizon Client for Android have certain restrictions.

Table 4-3. Requirements for Specific Features

Feature	Requirements
Location-based printing for Windows Server 2008 R2 desktops, published desktops (on virtual machine RDS hosts), and remote applications	Horizon 6.0.1 with View and later servers.
Smart cards for published desktops	View Agent 6.1 and later or Horizon Agent 7.0 and later.
Real-Time Audio-Video	See “System Requirements for Real-Time Audio-Video,” on page 9.
Client drive redirection	View Agent 6.1.1 and later or Horizon Agent 7.0 and later.

Feature Support for Linux Desktops

Some Linux guest operating systems are supported if you have View Agent 6.1.1 or later or Horizon Agent 7.0 or later. For a list of supported Linux operating systems and information about supported features, see the *Setting Up Horizon 6 for Linux Desktops* or *Setting Up Horizon 7 for Linux Desktops* document.

Input Devices, Keyboards, and Keyboard Settings

Horizon Client supports Bluetooth and docked keyboard devices and keyboards. You can also set preferences for settings such as auto-capitalization and text correction.

External Keyboards and Input Devices

For information about the devices that a specific tablet supports, see the documentation from the tablet manufacturer.

External keyboards are sometimes automatically detected by Horizon Client. For some external keyboards, you must either tap the tablet screen with three fingers at the same time, or you must tap the **Keyboard** icon. If you are using a remote desktop or application in full-screen mode, the **Keyboard** icon is in the Horizon Client Tools radial menu. If you are not using full-screen mode, the **Keyboard** icon is on the Horizon Client toolbar.

NOTE On Kindle Fire tablets, tapping with three fingers does not display the onscreen keyboard. You can instead use the **Keyboard** icon to display the onscreen keyboard.

After the external keyboard is detected, you might not be able to use the Horizon Client Tools or three-finger tap to display the onscreen keyboard. You might first have to deactivate the external keyboard by pressing its **Eject** key.

International Onscreen Keyboards

With the correct input methods installed, you can input characters for the following languages: English-United States, Japanese, French, German, Simplified Chinese, Traditional Chinese, Korean, and Spanish.

To choose a language for the keyboard or voice, tap the **Keyboard Settings** key on the onscreen keyboard. The **Keyboard Settings** key is the left-most key on the bottom row of the onscreen keyboard. When you finish selecting settings, tap the Android **Back** button to dismiss the dialog box.

Enable the Japanese 106/109 Keyboard Layout

If you are connected to a Windows XP desktop, you can configure Horizon Client to use the Japanese 106/109 keyboard layout.

Prerequisites

Use Horizon Client to connect to a Windows XP desktop that has the Japanese keyboard layout enabled.

Procedure

- 1 Open **Settings** and tap **Keyboard**.

If you are using the remote desktop in full-screen mode, tap the Horizon Client Tools radial menu icon and tap the gear icon. If you are not using full-screen mode, **Settings** is in the menu in the upper-right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

- 2 Tap **Use Japanese 106/109 Keyboard Layout** to select the check box.

This setting is disabled if the keyboard layout on the Windows XP desktop is not set to Japanese or if the desktop is not running Windows XP.

Using the Real-Time Audio-Video Feature

With the Real-Time Audio-Video feature, you can use the client device's built-in cameras and microphones in a remote desktop. Real-Time Audio-Video is compatible with standard conferencing applications such as Skype, WebEx, and Google Hangouts.

Real-Time Audio-Video is enabled by default when you install Horizon Client on the client device.

For information about setting up the Real-Time Audio-Video feature on a remote desktop, see the *Configuring Remote Desktop Features in Horizon 7* document.

When you install Horizon Client on an Android 6 or later device, Horizon Client prompts you for permission to access the camera and microphone. You must grant permission for the camera and microphone to work with the remote desktop. You can enable or disable access to the camera or microphone in the Android Settings app. For Android devices earlier than Android 6, permission to the camera and microphone is opened by default.

If the camera is currently being used by another app, it cannot be used by the remote desktop simultaneously. Also, if the camera is being used by the remote desktop, it cannot be used by the client device at the same time.

If the client device has both a front and a back camera, you can select which camera to use in the remote desktop. If you are using a remote desktop in full-screen mode, tap the Horizon Client Tools radial menu icon, tap the gear icon, tap **Camera**, tap **Select a camera**, and tap the camera to use. If you are not using full-screen mode, **Settings** is in the menu in the upper-right corner of the Horizon Client toolbar. The **Camera** setting is available only when the camera is started.

Using Native Operating System Gestures with Touch Redirection

You can use native operating system gestures from a touch-based mobile device when you are connected to a Windows 8, Windows 10, or Windows Server 2012 remote desktop, or to a remote application that is hosted on Windows Server 2012. For example, you can touch, hold, and release an item on a Windows 8 desktop to display the item's context menu.

When touch redirection is enabled, you can use only native operating system touch gestures. Horizon Client local gestures, such as double-click and pinch, no longer work. You must drag the Unity Touch tab button to display the Unity Touch sidebar.

Touch redirection is enabled by default when you connect to a Windows 8, Windows 10, or Windows Server 2012 remote desktop, or to a remote application that is hosted on Windows Server 2012.

To disable touch redirection, open **Settings**, tap **Touch**, and deselect the **Windows native touch gestures** check box. If you are connected to a remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon and tap the gear icon. If you are not using full-screen mode, **Settings** is in the menu in the upper-right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

Using the Unity Touch Sidebar with a Remote Desktop

You can quickly navigate to a remote desktop application or file from a Unity Touch sidebar. From this sidebar, you can open files and applications, switch between running applications, and minimize, maximize, restore, or close windows and applications in a remote desktop.

The Unity Touch feature is available only if a Horizon administrator has enabled it. If users have a floating desktop, users' favorite applications and files can be saved only if Windows roaming user profiles are configured for the remote desktop. A Horizon administrator can also create a default **Favorite Applications** list that end users see the first time the sidebar appears. For more information, see "Configuring Unity Touch" in the *Configuring Remote Desktop Features in Horizon 7* document.

If the Unity Touch feature is enabled, the sidebar appears on the left side of the window when you first access a remote desktop.

Figure 4-1. Unity Touch Sidebar for a Remote Desktop on a Mobile Device





Figure 4-2. Unity Touch Sidebar for a Remote Desktop on a Thin Client



If you access a desktop that has Unity Touch enabled but the sidebar is not displayed, you can see a tab on the left side of the window. Besides swiping this tab to the right to open the sidebar, you can slide the tab up or down.

From this sidebar, you can perform many actions on a file or application.

Table 4-4. Unity Touch Sidebar Actions for a Remote Desktop

Action	Procedure
Show or hide the onscreen keyboard	(Thin client only) Select the Keyboard icon.
Change the Horizon Client settings	(Thin client only) Select the Settings icon.
Disconnect from the desktop	(Thin client only) Select the Disconnect icon.
Show the sidebar	Swipe the tab to the right. When the sidebar is open, you cannot perform actions on the desktop window or the Horizon Client Tools radial menu.
Hide the sidebar	Swipe the tab to the left to close the sidebar. When the sidebar is open, you cannot perform actions on the desktop window or the Horizon Client Tools radial menu.
Navigate to an application	Tap All Programs and navigate to the application just as you would from the Windows Start menu.
Navigate to a file	Tap My Files to access the User folder, and navigate to the file. My Files includes folders such as My Pictures, My Documents, and Downloads. My Files includes the folders in the user profile (%USERPROFILE% directory). If you relocate the system folder in the %USERPROFILE% directory, the My Files menu can also display content from the relocated folder, whether it is a local relocated folder or a network share folder.
Search for an application or file	<ul style="list-style-type: none"> ■ Tap in the Search box and type the name of the application or file. ■ To use voice dictation, tap the microphone on the keyboard. ■ To launch an application or file, tap the name of the application or file in the search results. ■ To return to the home view of the sidebar, tap the X to close the Search box.
Open an application or file	Tap the name of the file or application in the sidebar. The application starts and the sidebar closes.
Switch between running applications or open windows	Tap the application name under Running Applications . If more than one file is open for one application, tap the chevron (>) next to the application to expand the list.
Minimize a running application or window	Touch and hold the application name under Running Applications until the context menu appears. Tap Minimize .
Maximize a running application or window	Touch and hold the application name under Running Applications until the context menu appears. Tap Maximize .
Close a running application or window	Touch and hold the application name under Running Applications until the context menu appears. Tap Close .
Restore a running application or window to its previous size and position	Touch and hold the application name under Running Applications until the context menu appears. Tap Restore .
Create a list of favorite applications or files	<ol style="list-style-type: none"> 1 Search for the application or file, or tap Manage under the Favorite Applications or Favorite Documents list. If the Manage bar is not visible, tap the chevron (>) next to Favorite Applications or Favorite Files. 2 Tap the check box next to the names of your favorites in the search results or in the list of available applications or files. The favorite that you add last appears at the top of your favorites list. Your favorites are remembered across all of your mobile devices so that, for example, you have the same list whether using your smart phone or your tablet.

Table 4-4. Unity Touch Sidebar Actions for a Remote Desktop (Continued)

Action	Procedure
Remove an application or file from the favorites list	<ol style="list-style-type: none"> 1 Search for the application or file, or tap Manage under the Favorite Applications or Favorite Documents list. If the Manage bar is not visible, tap the chevron (>) next to Favorite Applications or Favorite Documents. 2 Tap to remove the check mark next to the name of the application or file in the favorites list.
Reorder an application or file in the favorites list	<ol style="list-style-type: none"> 1 Tap Manage under the Favorite Applications or Favorite Documents list. If the Manage bar is not visible, tap the chevron (>) next to Favorite Applications or Favorite Documents. 2 In the favorites list, touch and hold the handle on the left side of the application or file name and drag the favorite up or down the list.


Using the Unity Touch Sidebar with a Remote Application

You can quickly navigate to a remote application from a Unity Touch sidebar. From this sidebar, you can launch applications, switch between running applications, and minimize, maximize, restore, or close remote applications. You can also switch to a remote desktop.

The Unity Touch feature is available only if a Horizon administrator has enabled it.

When you access a remote application, the Unity Touch sidebar appears on the left side of the window. If the Unity Touch sidebar is closed, a tab appears on the left side of the window. You can swipe this tab to the right to reopen the sidebar. You can also slide the tab up or down.

Figure 4-3. Unity Touch Sidebar for a Remote Application on a Mobile Device

Figure 4-4. Unity Touch Sidebar for a Remote Application on a Thin Client

From the Unity Touch sidebar, you can perform many actions on a remote application.

Table 4-5. Unity Touch Sidebar Actions for a Remote Application

Action	Procedure
Show or hide the onscreen keyboard	(Thin client only) Select the Keyboard icon.
Modify Horizon Client settings	(Thin client only) Select the Settings icon.
Disconnect from the application	(Thin client only) Select the Disconnect icon.
Show the sidebar	Swipe the tab to the right to open the sidebar. When the sidebar is open, you cannot perform actions on the application window.
Hide the sidebar	Swipe the tab to the left to close the sidebar. When the sidebar is open, you cannot perform actions on the application window.
Switch between running applications	Tap the application under Current Connection .
Open an application	Tap the name of the application under Applications in the sidebar. The application starts and the sidebar closes.
Close a running application	<ol style="list-style-type: none"> 1 Touch and hold the application name under Current Connection until the context menu appears. 2 Tap Close.
Minimize a running application	<ol style="list-style-type: none"> 1 Touch and hold the application name under Current Connection until the context menu appears. 2 Tap Minimize.
Maximize a running application	<ol style="list-style-type: none"> 1 Touch and hold the application name under Current Connection until the context menu appears. 2 Tap Maximize.
Restore a running application	<ol style="list-style-type: none"> 1 Touch and hold the application name under Current Connection until the context menu appears. 2 Tap Restore.
Switch to a remote desktop	Tap the desktop name under Desktops .

Horizon Client Tools on a Mobile Device

On a mobile device, the Horizon Client Tools include buttons for displaying the onscreen keyboard, virtual touchpad, configuration settings, and a virtual keypad for arrow keys and function keys.

When you use a remote desktop or application in full-screen mode, the Horizon Client Tools radial menu icon appears at the right edge of the window. You can drag the radial menu icon to relocate it. Tap to expand the radial menu and display icons for each tool, which you can tap to select. Tap outside the tool icons to collapse the icons back into the radial menu icon.

If the remote desktop or application is not in full-screen mode, a toolbar appears on the right side of the menu bar at the top of the window. You can tap the **Full Screen** icon on the toolbar to enter full-screen mode. When you are in full-screen mode, you can tap a similar icon in the radial menu to exit full-screen mode.

The radial menu includes several tools.

Table 4-6. Radial Menu Icons

Icon	Description
	Horizon Client Tools radial menu
	Disconnect
	Onscreen keyboard (toggles to show or hide)
	Settings
	Navigation keys
	Virtual touchpad
	Gesture help

Onscreen Keyboard

The onscreen keyboard has more keys than the standard onscreen keyboard, for example, Control keys and function keys are available. To display the onscreen keyboard, tap the screen with three fingers at the same time or tap the **Keyboard** icon.

If you are using a remote desktop or application in full-screen mode, the **Keyboard** icon is in the Horizon Client Tools radial menu. If you are not using full-screen mode, the **Keyboard** icon is on the Horizon Client toolbar.

You can also use the feature that displays the onscreen keyboard whenever you tap a text field, such as in a note or new contact. If you then tap in an area that is not a text field, the keyboard is dismissed.

To turn this feature on or off, use the **Keyboard popup** and **Keyboard dismiss** options. To display these options when you are using a remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon, tap the gear icon, and tap **Keyboard**. If you are not using full-screen mode, **Settings** is in the menu in the upper-right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

NOTE On Kindle Fire tablets, tapping with three fingers does not display the onscreen keyboard. You can instead tap the **Keyboard** icon on the Horizon Client toolbar to display the onscreen keyboard.

Even if you use an external keyboard, a one-row onscreen keyboard might still appear, which contains function keys, and the Ctrl, Alt, Win, and arrow keys. Some external keyboards do not have all these keys.

Sending a String of Characters

From the onscreen keyboard, tap the pen icon on the left side of the Ctrl key to display the local input buffer. Text that you type into this text box is not sent to an application until you tap **Send**. For example, if you open an application such as Notepad and tap the pen icon, the text that you type does not appear in the Notepad application until you tap **Send**.

Use this feature if you have a poor network connection. That is, use this feature if, when you type a character, the character does not immediately appear in the application. With this feature, you can quickly type up to 1,000 characters and then either tap **Send** or tap **Return** to have all 1,000 characters appear at once in the application.

Navigation Keys

Tap the **Ctrl/Page** icon in the Horizon Client Tools or onscreen keyboard to display the navigation keys. These keys include Page Up, Page Down, arrow keys, function keys, and other keys that you often use in Windows environments, such as Alt, Del, Shift, Ctrl, Win, and Esc. You can press and hold arrow keys for continuous key strokes. For a picture of the Ctrl/Page icon, see the table at the beginning of this topic.

Use the Shift key on this keypad when you need to use key combinations that include the Shift key, such as Ctrl+Shift. To tap a combination of these keys, such as Ctrl+Alt+Shift, first tap the onscreen Ctrl key. After the Ctrl key turns blue, tap the onscreen Alt key. After the Alt key turns blue, tap the onscreen Shift key. A single onscreen key is provided for the key combination Ctrl+Alt+Del.

Onscreen Touchpad and Full-Screen Touchpad

The virtual touchpad can be either regular-size, to resemble a touchpad on a laptop computer, or full screen, so that the entire device screen is a touchpad.

By default, when you tap the touchpad icon, you can touch anywhere on the screen to move the mouse pointer. The screen becomes a full-screen touchpad.

- Moving your finger around the touchpad creates a mouse pointer that moves around the remote desktop or application.
- You can use the regular-size and full-screen virtual touchpad for single-clicking and double-clicking.
- The regular touchpad also contains left-click and right-click buttons.
- You can tap with two fingers and then drag to scroll vertically.

You can drag the regular-size virtual touchpad to the side of the device so that you can use your thumb to operate the touchpad while you are holding the device.

You can make the virtual touchpad resemble the touchpad on a laptop, including right-click and left-click buttons, by setting the **Full screen touchpad** setting to off. If you are using the remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon, tap the gear icon, tap **Touch**, and deselect the **Full screen touchpad** setting.

To adjust how quickly the pointer moves when you use the touchpad, adjust the **Touchpad sensitivity** option. If you are using the remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon, tap the gear icon, tap **Touch**, tap **Touchpad sensitivity**, and drag the slider.

If you are not using full-screen mode, **Settings** is in the menu in the upper-right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

Gestures

VMware has created user interaction aids to help you navigate conventional Windows user interface elements on a non-Windows device.

Clicking

As in other applications, you tap to click a user interface element.

Right-Clicking

The following options are available for right-clicking:

- Use the Horizon Client Tools to display the regular virtual touchpad and use the touchpad's right-click button.
- On a touch screen, tap with two fingers at nearly the same time. The right-click occurs where the first finger tapped.
- On some devices, you can use an external mouse, such as a USB or Bluetooth mouse, to right-click.

Scrolling and Scrollbars

The following options are available for vertical scrolling.

- On a touch screen, tap with one or two fingers and then drag to scroll. The text under your fingers moves in the same direction as your fingers.

IMPORTANT Scrolling with one finger has the following limitations: It does not work if you have zoomed in, or when the onscreen keyboard is displayed, or when you are using the full-screen touchpad.

- Use the Horizon Client Tools to display the touchpad, tap the touchpad with two fingers, and then drag to scroll.
- Use the onscreen touchpad to move the mouse pointer and click scroll bars.

Zooming In and Out

As in other applications, pinch your fingers together or apart to zoom on a touch screen.

Window Resizing

If you use the full-screen touchpad to resize a window, touch and hold one finger at the corner or side of the window and drag to resize.

If you use the regular-size virtual touchpad, touch and hold the left-click button while dragging the corner or side of a window.

Sound, Music, and Video

If sound is turned on for your device, you can play audio in a remote desktop.

Using a Thin Client

How you interact with Windows user interface elements when Horizon Client is installed on a thin client depends on the thin client model and the external input device you are using with the thin client. For more information, see [“Using Horizon Client on a Thin Client,”](#) on page 20.

Multitasking

You can switch between Horizon Client and other apps without losing a remote desktop or application connection.

In a WiFi network, by default Horizon Client runs in the background indefinitely. In a 3G network, Horizon Client suspends data transmission when you switch to another app. Data transmission resumes when you switch back to Horizon Client.

The Horizon Client icon appears in the status bar when the app is running in the background and there is a connection to a remote desktop. To switch back to Horizon Client, tap the icon in the status bar.

You can copy and paste plain text between an Android device application and a remote desktop or between two remote desktops. Formatting information is not copied.

- Text that you copy to the Android device's clipboard is automatically copied to the remote desktop's clipboard when you log in to the remote desktop.
- If you are logged in to a remote desktop, text that you copy to the remote desktop's clipboard is copied to the Android device's clipboard when you press the **Home** button or switch to the background.

By default, you can copy and paste plain text between an Android device application and a remote application. The clipboard can accommodate up to 64K characters for copy and paste operations.

To enable users to copy plain text between a remote application and an Android device application, you must modify the PCoIP or VMware Blast group policy setting called **Configure clipboard redirection** on the RDS host that hosts the remote application pool.

For information about configuring PCoIP and VMware Blast group policy settings, see the *Configuring Remote Desktop Features in Horizon 7* document.

Copying and Pasting Text and Images

By default, you can copy and paste plain text from an Android device to a remote desktop or application. If a Horizon administrator enables the feature, you can also copy and paste plain text from a remote desktop or application to the Android device, or between two remote desktops or applications.

A Horizon administrator can configure this feature so that copy and paste operations are allowed only from the Android device to a remote desktop or application, or only from a remote desktop or application to the Android device, or both, or neither.

You can also copy and paste images and Rich Text Format (RTF) text, but the following restrictions apply:

- You can copy and paste images and RTF text from the Android device to a remote desktop or application. You cannot copy and paste images and RTF text from a remote desktop or application to the Android device.
- Only Google apps are supported. For example, you can copy and paste images and RTF text from Google Docs, Gmail, Chrome, Google+, Google Hangouts, Google Calendar, Google Sheets, and Google Slides.
- You can copy and paste images only when the Android device can access the Google website.
- If you select an image and RTF text (or plain text) together, the image is discarded and only the text is copied and pasted. To copy and paste an image, you must select only the image.

- A Horizon administrator can use group policies to restrict clipboard formats during copy and paste operations. The clipboard format filter policies for Microsoft Office Chart and Smart Art data and Microsoft Text Effects data are not supported. For information about clipboard format filter policies, see the *Configuring Remote Desktop Features in Horizon 7* document. Using Smart Policies to control copy and paste behavior in remote desktops is not supported.

The clipboard can accommodate a maximum of 1 MB of data for copy and paste operations. If the text and RTF data together use less than maximum clipboard size, the formatted text is pasted. Often the RTF data cannot be truncated, so that if the text and formatting use more than the maximum clipboard size amount, the RTF data is discarded, and plain text is pasted. If you are unable to paste all of the formatted text you selected in one operation, you might need to copy and paste smaller amounts in each operation.

Saving Documents in a Remote Application

With certain remote applications, such as Microsoft Word or WordPad, you can create and save documents. Where these documents are saved depends on your company's network environment. For example, your documents might be saved to a home share mounted on your local computer.

A Horizon administrator can use the RDS Profiles group policy setting called **Set Remote Desktop Services User Home Directory** to specify where documents are saved. For more information, see the *Configuring Remote Desktop Features in Horizon 7* document.

Screen Resolutions and Using External Displays

You can use Horizon Client with external displays and you can change screen resolutions.

When you connect a client device to an external display or projector, Horizon Client supports certain maximum display resolutions. You can change the screen resolution used on the client device to allow scrolling a larger screen resolution.

Enlarging the Screen Resolution for a Remote Desktop

By default, the display resolution is set so that the entire Windows desktop fits inside the client device, and the desktop icons and task bar icons are a certain size. If you change the default to a higher resolution, the desktop still fits inside the client device, but the desktop and taskbar icons become smaller.

You can pinch your fingers apart to zoom in and make the desktop larger than the device screen. You can then tap and drag to access the edges of the desktop.

Changing the Display Resolution Setting

You can use the **Resolution** setting to set the display resolution to a larger value. If you are using a remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon, tap the gear icon, tap **Display**, and tap **Resolution**. If you are not using full-screen mode, **Settings** is in the menu in the upper-right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

Using High Quality Mode

You can use the High Quality Mode feature to obtain the best display quality in remote desktops and applications.

To enable High Quality Mode, before you connect to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window, tap **Display**, and then tap **High Quality Mode**. You cannot enable the **High Quality Mode** setting after you connect to a remote desktop or application.

The High Quality Mode feature has the following requirements and limitations:

- You cannot use the High Quality Mode feature for existing sessions. You must log out and log in to a new session for the feature to take effect.
- The **High Quality Mode** setting is not available if the Android device has less than an extra-high density (xhdpi) screen.
- The High Quality Mode feature requires Horizon Agent 7.0.3 or later.

High Quality Mode is disabled by default.

Using External Displays

You can use the **Enable External display** setting to configure settings for external displays, such as projectors and attached monitors.

When the **Enable External display** setting is selected, you can select the **Presentation mode**, **Multi-Monitor mode**, **Keep screen on when external display is connected**, and **Zoom** settings. When the **Enable External display** setting is not selected, all of the external display settings are disabled.

In **Presentation mode**, a keyboard and expanded onscreen touchpad appear on the device when you display a remote desktop on an external display. The expanded touchpad and keyboard appear when you plug the device into the external display. The device detects the maximum resolution provided by the external display. The presentation mode feature is supported only if you have an Android 4.2 or later device.

You can use the **Multi-Monitor mode** setting to extend a secondary desktop on an external display. The Unity Touch sidebar is supported only on the device monitor. You cannot change the orientation and full-screen mode. You can interact with remote desktops and applications on the external display with the onscreen touchpad and full-screen touchpad. You cannot use the physical mouse on the external display. The multi-monitor mode feature is supported only if you have an Android 4.2 or later device.

You can use the **Keep screen on when external display is connected** setting to keep the display from turning off after a period of inactivity. You can drag the **Zoom** slider to set the resolution for the external display.

If you are connected to a remote desktop or application, pressing the Android Back button quits presentation mode or multi-monitor mode and the **Enable External display** setting is deselected.

To configure external display settings if you are using a remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon, tap the gear icon, tap **Display**, and then tap **External Display Options**. If you are not using full-screen mode, **Settings** is in the menu in the upper-right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

Do not use an external mouse, such as a Bluetooth mouse, when using the **Presentation mode** setting. Instead, use the large onscreen touchpad on the Android device. If you attempt to use a mouse, the mouse pointer might not be able to move to the bottom or right side of the screen, and when moved to the top of the screen, might conflict with some of the function keys shown on the large onscreen touchpad, rather than the top of the remote desktop.

PCoIP Client-Side Image Cache

PCoIP client-side image caching stores image content on the client to avoid retransmission. This feature reduces bandwidth usage.

The PCoIP image cache captures spatial, as well as temporal, redundancy. For example, when you scroll down through a PDF document, new content appears from the bottom of the window and the oldest content disappears from the top of the window. All the other content remains constant and moves upward. The PCoIP image cache is capable of detecting this spatial and temporal redundancy.

Because during scrolling, the display information sent to the client device is primarily a sequence of cache indices, using the image cache saves a significant amount of bandwidth. This efficient scrolling has benefits both on the LAN and over the WAN.

- On the LAN, where bandwidth is relatively unconstrained, using client-side image caching delivers significant bandwidth savings.
- Over the WAN, to stay within the available bandwidth constraints, scrolling performance would be degraded without client-side caching. Over the WAN, client-side caching saves bandwidth and ensure a smooth, highly responsive scrolling experience.

With client-side caching, the client stores portions of the display that were previously transmitted. The cache size is 250 MB.

Internationalization and International Keyboards

Both the Horizon Client user interface and the documentation are available in English, Japanese, French, German, Simplified Chinese, Traditional Chinese, Korean, and Spanish. International keyboards of English-United States, Japanese, French, German, Simplified Chinese, Traditional Chinese, Korean, and Spanish are supported.

To choose a language for the keyboard or voice, tap the Keyboard Settings key on the onscreen keyboard. The Keyboard Settings key is the left-most key on the bottom row of the onscreen keyboard.

Troubleshooting Horizon Client

You can solve most Horizon Client problems by resetting the desktop or reinstalling the app.

You can also enable log collection and send log files to VMware for troubleshooting.

This chapter includes the following topics:

- [“Restart a Remote Desktop,”](#) on page 59
- [“Reset a Remote Desktop or Remote Applications,”](#) on page 60
- [“Uninstall Horizon Client,”](#) on page 61
- [“Collecting and Sending Logging Information to VMware,”](#) on page 61
- [“Report Horizon Client Crash Data to VMware,”](#) on page 62
- [“Horizon Client Stops Responding or the Remote Desktop Freezes,”](#) on page 63
- [“Problem Establishing a Connection When Using a Proxy,”](#) on page 63
- [“Connecting to a Server in Workspace ONE Mode,”](#) on page 64

Restart a Remote Desktop

You might need to restart a remote desktop if the desktop operating system stops responding. Restarting a remote desktop is the equivalent of the Windows operating system restart command. The desktop operating system usually prompts you to save any unsaved data before it restarts.

You can restart a remote desktop only if a Horizon administrator has enabled the desktop restart feature for the desktop.

For information about enabling the desktop restart feature, see the *Setting Up Virtual Desktops in Horizon 7* or *Setting Up Published Desktops and Applications in Horizon 7* document.

Prerequisites

- Obtain login credentials, such as a user name and password, RSA SecurID user name and passcode, RADIUS authentication user name and passcode, or smart card personal identification number (PIN).
- If you have not logged in at least once, become familiar with the procedure [“Connect to a Remote Desktop or Application,”](#) on page 34.

Procedure

- 1 On the **Servers** tab, tap the server shortcut to connect to the server.
- 2 If prompted, supply your RSA user name and passcode, your Active Directory user name and password, or both.

- 3 Touch and hold the desktop name until the context menu appears.

You can perform this step from either the **All** or **Favorites** tab.

- 4 Tap **Restart** in the context menu.

Restart is available only if the status of the desktop is such that the action can be taken.

The operating system in the remote desktop reboots and Horizon Client disconnects and logs off from the desktop.

What to do next

Wait an appropriate amount of time for system startup before you attempt to reconnect to the remote desktop.

If restarting the remote desktop does not solve the problem, you might need to reset the remote desktop. See [“Reset a Remote Desktop or Remote Applications,”](#) on page 60.

Reset a Remote Desktop or Remote Applications

You might need to reset a remote desktop if the desktop operating system stops responding and restarting the remote desktop does not solve the problem. Resetting remote applications quits all open applications.

Resetting a remote desktop is the equivalent of pressing the Reset button on a physical PC to force the PC to restart. Any files that are open on the remote desktop are closed and are not saved.

Resetting remote applications is the equivalent of quitting the applications without saving any unsaved data. All open remote applications are closed, even applications that come from different RDS server farms.

You can reset a remote desktop only if a Horizon administrator has enabled the desktop reset feature for the desktop.

For information about enabling the desktop reset feature, see the *Setting Up Virtual Desktops in Horizon 7* or *Setting Up Published Desktops and Applications in Horizon 7* document.

Prerequisites

- Obtain login credentials, such as a user name and password, RSA SecurID user name and passcode, RADIUS authentication user name and passcode, or smart card personal identification number (PIN).
- If you have not logged in at least once, become familiar with the procedure [“Connect to a Remote Desktop or Application,”](#) on page 34.

Procedure

- 1 On the **Servers** tab, tap the server shortcut to connect to the server.
- 2 If prompted, supply your RSA user name and passcode, your Active Directory user name and password, or both.
- 3 Touch and hold the desktop or application name until the context menu appears.
You can perform this step from either the **All** or **Favorites** tab.
- 4 Tap **Reset** in the context menu.

Reset is available only if the status of the desktop or application is such that the action can be taken.

When you reset a remote desktop, the operating system in the remote desktop reboots and Horizon Client disconnects and logs off from the desktop. When you reset remote applications, the applications quit.

What to do next

Wait an appropriate amount of time for system startup before attempting to reconnect to the remote desktop or application.

Uninstall Horizon Client

You can sometimes resolve problems with Horizon Client by uninstalling and reinstalling Horizon Client. You uninstall Horizon Client just as you would any Android app.

Procedure

- 1 On your device, go to the **Horizon** app.
- 2 Touch and hold the app icon until the **Uninstall** (trash can) icon appears on your device.
- 3 Drag the app to the **Uninstall** (trash can) icon.

Alternatively, you can go to **Apps > Settings** and select **Applications > Manage Applications** to uninstall Horizon Client.

What to do next

Reinstall Horizon Client.

See [“Install or Upgrade Horizon Client,”](#) on page 13.

Collecting and Sending Logging Information to VMware

You can configure Horizon Client to collect log information and send log files to VMware for troubleshooting.

If Horizon Client quits unexpectedly, Horizon Client immediately prompts you to send log files to VMware. If log collection is enabled, the crash log file contains detailed debug information. If log collection is disabled, only certain exception information is included in the crash log file.

Horizon Client generates three types of log files (*Horizon_View_Client_logs_timestamp.txt*, *libcdk_timestamp.txt*, and *pcoip_client_timestamp.txt*) and keeps the last five log files of each type.

If you choose to send log files to VMware, Horizon Client uses the available email client on the client device to create a message. If the email client can send multiple attachments, Horizon Client attaches the last five log files of each type to the message. If the email client cannot send multiple attachments, Horizon Client compresses the last five log files of each type and attaches a ZIP file to the message. The ZIP file name contains a time stamp, for example, *Horizon_View_Client_logs_timestamp.zip*.

You can also manually retrieve and send log files at any time.

Enable Horizon Client Log Collection

When you enable log collection, Horizon Client creates log files that contain information that can help VMware troubleshoot problems with Horizon Client.

Because log collection affects the performance of Horizon Client, enable log collection only if you are experiencing a problem.

Prerequisites

Verify that an email client is available on the device. Horizon Client requires an email client to send log files.

Procedure

- 1 Open **Settings** and tap **Log collection**.

If you are connected to a remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon and tap the gear icon. If you are not using full-screen mode, **Settings** is in the menu in the upper right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

- 2 Tap **Enable log** to select the check box and tap **OK** to confirm your choice.

After log collection is enabled, Horizon Client generates a log file it quits unexpectedly or when it is exited and relaunched.

Manually Retrieve and Send Horizon Client Log Files

When Horizon Client log collection is enabled on your device, you can manually retrieve and send log files at any time.

This procedure shows you how retrieve and send log files through Horizon Client. You can also retrieve log files by using tools that can access app storage space. Horizon Client saves log files in the `Android/data/com.vmware.view.client.android/files` directory.

Prerequisites

- Verify that an email client is available on the device. Horizon Client requires an email client to send log files.
- Enable Horizon Client log collection. See [“Enable Horizon Client Log Collection,”](#) on page 61.

Procedure

- 1 Open **Settings** and tap **Log collection**.

If you are connected to a remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon and tap the gear icon. If you are not using full-screen mode, **Settings** is in the menu in the upper right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

- 2 Tap **Send the log**.

Horizon Client uses the email client on the device to create a message. The body of the message contains information about your device. If your email client can send multiple attachments, Horizon Client attaches the last five log files of each type to the message. If your email client cannot send multiple attachments, Horizon Client compresses the last five log files of each type and attaches a ZIP file to the message.

Disable Horizon Client Log Collection

Because log collection affects the performance of Horizon Client, disable log collection if you are not troubleshooting a problem.

Procedure

- 1 Open **Settings** and tap **Log collection**.

If you are connected to a remote desktop or application in full-screen mode, tap the Horizon Client Tools radial menu icon and tap the gear icon. If you are not using full-screen mode, **Settings** is in the menu in the upper right corner of the Horizon Client toolbar. If you are not connected to a remote desktop or application, tap the gear icon in the upper right corner of the Horizon Client window.

- 2 Tap **Enable log** to clear the check box.

Report Horizon Client Crash Data to VMware

You can configure Horizon Client to report crash data to VMware.

Procedure

- 1 Tap the **Settings** (gear) icon in the upper right corner of the Horizon Client window.

- 2 Tap **Crash Reporting**.
- 3 Tap **Crash Reporting** to enable or disable the check box.

The setting is enabled by default.

If Horizon Client stops responding, a crash log file is uploaded to the VMware server the next time Horizon Client starts.

Horizon Client Stops Responding or the Remote Desktop Freezes

When the window freezes, first, try resetting the remote desktop operating system.

Problem

Horizon Client does not work or repeatedly exits unexpectedly or the remote desktop freezes.

Cause

Assuming that Horizon servers are configured properly and that firewalls surrounding them have the correct ports open, other issues usually relate to Horizon Client on the device or to the guest operating system on the remote desktop.

Solution

- If the operating system in the remote desktop freezes, use Horizon Client on the device to reset the desktop.
This option is available only if the Horizon administrator has enabled this feature.
- Uninstall and reinstall the app on the device.
- If resetting the remote desktop and reinstalling Horizon Client do not help, you can reset the Android device, as described in the user guide for your Android device.
- If you get a connection error when you attempt to connect to the server, you might need to change your proxy settings.

Problem Establishing a Connection When Using a Proxy

Sometimes if you attempt to connect to Connection Server using a proxy while on the LAN, an error occurs.

Problem

If the Horizon environment is set up to use a secure connection from the remote desktop to Connection Server, and if the client device is configured to use an HTTP proxy, you might not be able to connect.

Cause

Unlike Windows Internet Explorer, the client device does not have an Internet option to bypass the proxy for local addresses. When an HTTP proxy is used for browsing external addresses, and you try to connect to Connection Server using an internal address, you might see the error message `Could not establish connection`.

Solution

- ◆ Remove the proxy settings so that the device no longer uses a proxy.

Connecting to a Server in Workspace ONE Mode

If you cannot connect to a server directly through Horizon Client, or if your desktop and application entitlements are not visible in Horizon Client, Workspace ONE mode might be enabled on the server.

Problem

- When you try to connect to the server directly through Horizon Client, Horizon Client redirects you to the Workspace ONE portal.
- When you open a desktop or application through a URI or shortcut, or when you open a local file through file association, the request redirects you to the Workspace ONE portal for authentication.
- After you open a desktop or application through Workspace ONE and Horizon Client starts, you cannot see or open other entitled remote desktops or applications in Horizon Client.

Cause

Beginning with Horizon 7 version 7.2, a Horizon administrator can enable Workspace ONE mode on a Connection Server instance. This behavior is normal when Workspace ONE mode is enabled on a Connection Server instance.

Solution

Use Workspace ONE to connect to a Workspace ONE enabled server and access your remote desktops and applications.

Index

A

- agent, installation requirements **12**
- AirWatch integration **14, 16**
- Android, installing Horizon Client on **7**
- Android Horizon Client, uninstalling **61**
- Aptelligent **62**

B

- background multitasking **55**

C

- caching, client-side image **57**
- certificates, ignoring problems **33**
- Chromebook **19**
- Chromebooks **8**
- client image cache **57**
- Connection Server **12**
- connection problems **63**
- copying and pasting **55**
- customer experience program, desktop pool data **24**

D

- default view **23**
- DeX Mode **41**
- disconnecting from a remote desktop **40**
- display requirements **56**
- displays, external **56**

E

- external displays **56**

F

- favorites **39**
- favorites list in Unity Touch sidebar **48**
- feature support matrix **44**
- fingerprint authentication **11**

G

- Google Play Store **13, 61**

H

- hardware requirements
 - Android devices **7**
 - smart card authentication **9**
- Horizon Client
 - disconnect from a desktop **40**
 - logging in **34**
 - setup for Android devices **7**
 - system requirements for Android devices **7**
 - troubleshooting **63**
- Horizon Client for Android
 - installing **13**
 - uninstalling **61**

I

- image cache, client **57**
- input devices for the Android **46**
- installing Horizon Client **13**

J

- Japanese keyboard layout **46**

K

- keyboard
 - navigation keys **52**
 - onscreen **52, 54**
- keyboard support **46, 58**
- keys, navigation **52**

L

- local storage redirection **37**
- log collection **62**
- log off **40**
- logging **61**
- logging in
 - to a desktop **34**
 - to a server **34**

M

- manage desktop shortcuts **41**
- managing desktops **33**
- multitasking **55**

N

- navigation keys **52**

O

operating systems, supported on the agent **12**
options, configuration **52**

P

PCoIP client image cache **57**
picture in picture mode **41**
prerequisites for client devices **12**
projectors **56**
proxy connections **63**

R

Real-Time Audio-Video feature **9**
reset a desktop **60**
resizing windows **54**
resolution, screen **56**
restart desktop **59**
RSA SecurID tokens **21**
RTAV **47**
running in the background **55**

S

Samsung DeX Mode **41**
saving documents in a remote application **56**
screen resolution **56**
scrolling **54**
security servers **12**
server connections, managing **33**
shortcut
 desktops **41**
 Home screen **38**
sidebar, Unity Touch **48**
smart card authentication
 on devices **10**
 requirements **9**
software tokens **21**
split screen mode **41**
SSL options **22**
system requirements, for Android devices **7**

T

tablet gestures **54**
thin client **20**
thin client requirements **8**
Thin Client mode **20**
tokens, RSA SecurID **21**
toolbar, Horizon Client **52**
touchpad, virtual **52**
troubleshooting, connection problems **63**

U

Unauthenticated Access **36**
Unity Touch feature **48**

Unity Touch sidebar **50**
URI examples **30**
URI syntax for Horizon Clients **27**
URIs (uniform resource identifiers) **27**

V

VMware Blast **22**

W

Windows 8 gestures **47**
Workspace ONE **64**