

# Using VMware Cloud Director Object Storage Extension as a Tenant User

16 APR 2020

VMware Cloud Director Object Storage Extension 1.5

You can find the most up-to-date technical documentation on the VMware website at:

<https://docs.vmware.com/>

**VMware, Inc.**  
3401 Hillview Ave.  
Palo Alto, CA 94304  
[www.vmware.com](http://www.vmware.com)

Copyright © 2020 VMware, Inc. All rights reserved. [Copyright and trademark information.](#)

# Contents

<b>1</b>	<b>What is VMware Cloud Director Object Storage Extension</b>	<b>5</b>
<b>2</b>	<b>Getting Started With VMware Cloud Director Object Storage Extension</b>	<b>7</b>
	Access the VMware Cloud Director Object Storage Extension Tenant Portal	9
	Roles and Rights in VMware Cloud Director Object Storage Extension	10
	Edit the Server-Side Encryption Configuration	11
<b>3</b>	<b>Working with Buckets</b>	<b>12</b>
	Create a Bucket	12
	Enable or Disable Versioning	13
	Working with Bucket Logs	14
	Enable Bucket Logging	14
	Edit Bucket Logging Configuration	15
	Working with Cross-Origin Resource Sharing Rules	16
	Create a Cross-Origin Resource Sharing Rule	16
	Edit a Cross-Origin Resource Sharing Rule	17
	Add Tags to a Bucket	17
	Sharing Buckets	18
	Share a Bucket Using a Canned Access Control List	18
	Share a Bucket Using a Custom Access Control List	19
	Review Shared Buckets	20
	Synchronize a Bucket	20
	Empty a Bucket	21
	Delete a Bucket	21
<b>4</b>	<b>Working with Objects</b>	<b>23</b>
	Working with Folders	23
	Create a Folder	24
	Delete a Folder	25
	Upload Files to VMware Cloud Director Object Storage Extension	26
	Add Tags and Metadata to an Object	26
	Sharing Objects	28
	Share an Object by Using a Canned Access Control List	28
	Share an Object by Using a Custom Access Control List	29
	Copy an Object	30
	Preview an Object	31
	Download an Object	32
	Delete an Object	32

## 5 Working with Multiple Sites 34

- Preview an Object in a Remote Site 34
- Download an Object from a Remote Site 35
- Switch to a Remote Site 36

## 6 Working with VMware Cloud Director Objects 37

- Working with vApps in VMware Cloud Director Object Storage Extension 37
  - Capture vApps 37
  - Share a vApp 38
  - Review Shared vApps 39
  - Download a vApp 39
  - Upload a vApp 40
  - Restore a vApp 40
  - Delete vApps 41
- Working with Catalogs 42
  - Create a Catalog 42
  - Create a Template in a Catalog 42
  - Upload Files to a Catalog 43
  - Import a Catalog to VMware Cloud Director 44
  - Publish a Catalog 45
  - Share a Catalog 45
  - Review Shared Catalogs 46
  - Unpublish a Catalog 46
  - Empty a Catalog 47
  - Delete a Catalog 47

## 7 Working with Security Credentials 49

- Working with User Credentials 49
  - Create a User Credential 49
  - Activate or Deactivate a User Credential 50
  - Delete a User Credential 50
- Working with Application Credentials 50
  - Create an Application Credential 51
  - Activate or Deactivate an Application Credential 51
  - Delete an Application Credential 51

## 8 Working with VMware Cloud Director Object Storage Extension S3 API 53

# What is VMware Cloud Director Object Storage Extension

# 1


VMware Cloud Director Object Storage Extension is a standalone middleware service that provides object storage capabilities to VMware Cloud Director users. During the installation and configuration, the user interface of VMware Cloud Director Object Storage Extension registers as a plug-in to VMware Cloud Director. As a result, you can access VMware Cloud Director Object Storage Extension from the VMware Cloud Director service provider admin portal and the VMware Cloud Director tenant portal.

By integrating with VMware Cloud Director, VMware Cloud Director Object Storage Extension provides you the capability to store and share unstructured data within your VMware Cloud Director organization. You can also use VMware Cloud Director Object Storage Extension for backup and archiving purposes.

You can use VMware Cloud Director Object Storage Extension to store the following data types:

- Media files (images, audio, and video)
- Static Web content (HTML, CSS, JS, and ICO)
- Read-only documents (PDF)
- Backup and archives

The following diagram illustrates a high-level architecture of VMware Cloud Director Object Storage Extension.



# Getting Started With VMware Cloud Director Object Storage Extension

## 2

When you log in to VMware Cloud Director Object Storage Extension for the first time, your inventory in VMware Cloud Director Object Storage Extension is empty and the **Getting Started** pages guide you through the first steps for working with buckets, vApps, and catalogs.

## Understanding Buckets

Before you start uploading files to VMware Cloud Director Object Storage Extension, you must create a bucket. You can then upload any number of files to the bucket. A bucket is a logical unit of storage. Buckets are the fundamental containers in VMware Cloud Director Object Storage Extension.

You can access and manage buckets from the VMware Cloud Director Object Storage Extension user interface. See [Chapter 3 Working with Buckets](#). Alternatively, you can use the S3 API that VMware Cloud Director Object Storage Extension supports. See [Chapter 8 Working with VMware Cloud Director Object Storage Extension S3 API](#).

To organize and categorize your buckets, you can add multiple key-value pairs of tags to your buckets. For example, you can create a bucket to store financial reports from the financial department in your organization. You can tag this bucket with the following key-value pairs:

Key	Value
<i>Department</i>	<i>Finance</i>
<i>Report</i>	<i>Monthly</i>

Bucket names are globally unique and the namespace is shared between all VMware Cloud Director organizations. After you create a bucket, the name of that bucket cannot be used for another bucket in any of the VMware Cloud Director organizations until the bucket is deleted. Bucket names must adhere to the S3 bucket naming requirements. See [Amazon S3 Bucket Naming Requirements](#).

## Understanding Objects

Objects in VMware Cloud Director Object Storage Extension are the files that you upload to your buckets.

You can categorize objects within a bucket by adding key-value pairs of tags. If you are the owner of an object and have **Read** and **Write** permissions on the bucket that stores the object, you can add properties to the objects. You add the properties to the object by defining metadata in the form of a key-value pair.

Organization administrators can access and manage the objects that all users within their organization own. Organization users can access and manage the objects that they own and the objects that are shared with them.

You can preview image, text, PDF, audio, and video files directly in the user interface of VMware Cloud Director Object Storage Extension.

## Understanding How to Work with vApps in VMware Cloud Director Object Storage Extension

A vApp is a package/container of multiple interoperating virtual machines that communicate over a network and use resources and services in your environment. The virtual machines in the vApp are managed as a unit and distributed in OVA and OVF format. With VMware Cloud Director Object Storage Extension, you can store the vApps that you do not use in your VMware Cloud Director environment. When you capture a vApp from VMware Cloud Director and move it to VMware Cloud Director Object Storage Extension, you copy the vApp data from the VMware Cloud Director datastore to the back-end storage appliance that VMware Cloud Director Object Storage Extension uses. By capturing a vApp from VMware Cloud Director, you do not copy the storage reservation to VMware Cloud Director Object Storage Extension.

Later, if you need any of the vApps that you captured and store in VMware Cloud Director Object Storage Extension, you can restore the vApps back to their original location. You can also download vApps as OVA files for backup and archiving purposes.

## Understanding Catalogs in VMware Cloud Director Object Storage Extension

Catalogs in VMware Cloud Director Object Storage Extension are similar to the catalogs in VMware Cloud Director and act as containers for vApp and virtual machine templates.

You can upload ISO, OVA, OVF, and VMDK files to the VMware Cloud Director Object Storage Extension catalogs.

Catalogs in VMware Cloud Director Object Storage Extension can be used as external catalogs for VMware Cloud Director. An **organization administrator** can subscribe a VMware Cloud Director organization to a catalog in VMware Cloud Director Object Storage Extension. The subscription makes all files that are stored in VMware Cloud Director Object Storage Extension available to the VMware Cloud Director organization users without consuming any of the compute resources in the VMware Cloud Director environment. For information about subscribing your VMware Cloud Director organization to an external catalog, see [Subscribe to an External Catalog](#) in the *VMware Cloud Director Tenant Portal Guide*.



When you create a catalog in VMware Cloud Director Object Storage Extension, a bucket is also created and is reserved as a system bucket. You cannot manage that bucket the way you manage buckets created by users.

## Understanding Security Credentials

VMware Cloud Director Object Storage Extension supports S3-compatible API and the AWS Signature V4 authentication. Security credentials are used for authenticating S3 API requests and consist of an access key and a secret key. VMware Cloud Director Object Storage Extension supports user and application types of security credentials.

With S3 API requests authenticated with user credentials, you can access and manage buckets and objects that you own or that are shared with you.

With S3 API requests authenticated with application credentials, you can access and manage objects at the bucket level.

This chapter includes the following topics:

- [Access the VMware Cloud Director Object Storage Extension Tenant Portal](#)
- [Roles and Rights in VMware Cloud Director Object Storage Extension](#)
- [Edit the Server-Side Encryption Configuration](#)

## Access the VMware Cloud Director Object Storage Extension Tenant Portal

You access the VMware Cloud Director Object Storage Extension tenant portal by using the VMware Cloud Director tenant portal.


### Prerequisites

To access the VMware Cloud Director Object Storage Extension tenant portal, your VMware Cloud Director **system administrator** must enable VMware Cloud Director Object Storage Extension for your organization.

### Procedure

- 1 In a Web browser, navigate to the VMware Cloud Director tenant portal URL of your organization.

For example, `https://vcloud.example.com/tenant/myOrg`.

- 2 Enter your user name and password, and click **Log In**.
- 3 From the main menu () , select **Object Storage**.

### Results

The VMware Cloud Director Object Storage Extension tenant portal opens.

## Roles and Rights in VMware Cloud Director Object Storage Extension

Any enabled VMware Cloud Director **organization user** can access VMware Cloud Director Object Storage Extension.

The items that you see and the actions that you can perform depend on the rights assigned to your user account within a VMware Cloud Director organization.

The rights assigned to your user account in VMware Cloud Director define your user role in VMware Cloud Director Object Storage Extension.

**Table 2-1. Mapping Between VMware Cloud Director Rights and VMware Cloud Director Object Storage Extension Roles**

VMware Cloud Director Object Storage Extension Tenant Portal Role	VMware Cloud Director Rights	Notes
Provider Administrator	<ul style="list-style-type: none"> <li>■ General: Administrator View</li> <li>■ Provider VDC: View</li> <li>■ Organization VDC: View</li> <li>■ UI Plugins: View</li> </ul>	None.
Tenant Administrator	<ul style="list-style-type: none"> <li>■ General: Administrator View</li> <li>■ Organization VDC: View</li> <li>■ UI Plugins: View</li> </ul>	<b>Tenant administrators</b> in VMware Cloud Director Object Storage Extension must not have the <b>Provider VDC: View</b> role assigned to their user account in VMware Cloud Director. If you assign the <b>Provider VDC: View</b> role to a <b>Tenant Administrator</b> , the user role in VMware Cloud Director Object Storage Extension changes to <b>Provider Administrator</b> .
Tenant User	UI Plugins: View	<b>Tenant users</b> in VMware Cloud Director Object Storage Extension must not have the <b>General: Administrator View</b> and the <b>General: Administrator View</b> roles assigned to their user account in VMware Cloud Director. If you assign these roles to a <b>Tenant User</b> , the user role in VMware Cloud Director Object Storage Extension changes to <b>Tenant Administrator</b> .

For information about the predefined roles and their rights in VMware Cloud Director, see [Predefined Roles and Their Rights](#).


## Edit the Server-Side Encryption Configuration

By default, VMware Cloud Director Object Storage Extension does not enforce any server-side encryption to the objects that users store in the underlying datastore. Optionally, an **organization administrator** can define a server-side encryption method to protect your data while it is stored in the data center of your **service provider**.

Your files are encrypted as VMware Cloud Director Object Storage Extension writes the data to disks in the data center and decrypts the data when you access it.

Changing the encryption method for your organization does not impact objects that exist in VMware Cloud Director Object Storage Extension.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 Navigate to **Settings > Server-side Encryption** and click **Edit**.
- 4 Select the encryption type for your organization.

Encryption Type	Description
None	By default, VMware Cloud Director Object Storage Extension does not enforce a server-side encryption.
SSE-S3	A server-side encryption method that uses an AES-256 algorithm. An S3 server manages the primary keys.
SSE-C	Use this option, if the <b>organization administrator</b> wants to manage their own encryption algorithms and primary keys. If you select this encryption type, you must select the encryption algorithm and specify or generate an encryption key.

- 5 Select the **I understand the consequences** check box and click **Save**.

# Working with Buckets

# 3

Buckets in VMware Cloud Director Object Storage Extension represent containers to which you upload files.

Depending on your role, you can perform different operations with buckets,

- As an **organization user**, you can create, edit, share, empty, and delete your own buckets.
- As an **organization administrator**, you can create, edit, share, empty, and delete all buckets within your organization.

Users that have **organization administrator** privileges can manage the buckets of all **organization users**.

An **organization administrator** operates buckets using the bucket owner privilege. For example, if you upload an object to a bucket as an **organization administrator**, the owner of the bucket becomes the owner of the object.


This chapter includes the following topics:

- [Create a Bucket](#)
- [Enable or Disable Versioning](#)
- [Working with Bucket Logs](#)
- [Working with Cross-Origin Resource Sharing Rules](#)
- [Add Tags to a Bucket](#)
- [Sharing Buckets](#)
- [Review Shared Buckets](#)
- [Synchronize a Bucket](#)
- [Empty a Bucket](#)
- [Delete a Bucket](#)

## Create a Bucket

Before you can upload objects to VMware Cloud Director Object Storage Extension, you must create a bucket.

**Procedure**

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 Select **Buckets > My Buckets** and click **New Bucket**.
- 4 Enter a name of the bucket.

---

**Important** Bucket names are globally unique across all VMware Cloud Director organizations and must adhere to the S3 bucket names policies. For more information, see [Amazon S3 Bucket Naming Requirements](#).

---

- 5 (Optional) To keep multiple versions of the objects that the bucket stores, select the **Enable Versioning** check box.
- 6 Click **Save**.

**Results**

The new bucket appears in the **Buckets** pane and you can upload objects to it.

## Enable or Disable Versioning

Versioning is a means of keeping multiple versions of an object in the same bucket. You use versioning to preserve, retrieve, and restore every version of every object stored in your buckets. With versioning, you can easily recover from both unintended user actions and application failures.


You enable and disable versioning at the bucket level. You can enable or disable versioning during the creation of a bucket, or you can edit the versioning configuration later. By default, versioning is disabled.

**Prerequisites**

Verify that you have the required set of rights to enable or disable versioning for a bucket.

- If you are an **organization administrator**, you can manage the versioning configuration for the buckets that users in your organization own.
- If you are an **organization user**, you can manage the versioning configuration for the buckets that you own.

**Procedure**

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, click the name of the bucket that you want to edit.
- 4 Click **Properties**.

- 5 In the **Versioning** section, use the toggle button to enable or disable versioning.

## Working with Bucket Logs

Starting with VMware Cloud Director Object Storage Extension 1.5, you can record all activities at the bucket level.

When you configure bucket logging, you define a target bucket that stores the log files. Later, whenever an object is added, modified, or deleted, VMware Cloud Director Object Storage Extension records the action in a log file.

To write bucket logs, VMware Cloud Director Object Storage Extension uses a dedicated log delivery account named System Logger. The log delivery account is a subject to the usual access control restrictions. When you configure bucket logging, VMware Cloud Director Object Storage Extension grants **Write of Bucket** and **Read of ACL** permissions on the target bucket to the System Logger account.

You can interact with log files the same way you interact with other objects in VMware Cloud Director Object Storage Extension. You can preview log files directly in VMware Cloud Director Object Storage Extension, or you can download the logs locally.

If VMware Cloud Director Object Storage Extension uses the ECS storage platform, bucket logging is impossible. The ECS storage platform does not support bucket logging.

If you use Cloudian HyperStore, you can work with bucket logs.

## Enable Bucket Logging


To enable logging for a bucket, select a target bucket that stores the log files and optionally share the log files with other users.

### Prerequisites

Verify that you have the required set of rights to enable bucket logging.

- If you are an **organization administrator**, you can manage the logging configuration for the buckets that users in your organization own.
- If you are an **organization user**, you can configure the logging of buckets if you are the owner of the source and target buckets.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, click the name of the bucket that you want to edit.
- 4 Click **Properties**.
- 5 In the **Logging** card, click the text.

## 6 Enter the logging configuration details and click **Save**.

- a Select the target bucket in which you want to store the log files.

VMware Cloud Director Object Storage Extension grants **Write of Bucket** and **Read of ACL** permissions on the target bucket to the log delivery account named System Logger.

- b (Optional) Enter a prefix for the log files.
- c (Optional) To save the log files to a folder in the target bucket, select the **Prefix as a folder** check box.
- d (Optional) Share the log files with other users.
  - To share the log files with users within your tenant organization, use the toggle buttons in the **Tenant Users** row.
  - To share the log files with authenticated users within all tenant organizations, use the toggle buttons in the **Authenticated Users** row.
  - To share the log files with all users, use the toggle buttons in the **Public** row.
  - To share the log files with specific users within your organization, click the **Add User** button, select the users with whom you want to share the log files, and use the toggle buttons in the corresponding row.

### Results

Whenever an object is added or modified in the logging source bucket, VMware Cloud Director Object Storage Extension creates and adds a bucket log object to the logging target bucket. The owner of the log is the System Logger account.

## Edit Bucket Logging Configuration


You can change the logging target bucket, the logging prefix, or change the sharing permissions of the log files stored in the bucket.

### Prerequisites

Verify that you have the required set of rights to edit the bucket logging configuration.

- If you are an **organization administrator**, you can edit the logging configuration for the buckets that users in your organization own.
- If you are an **organization user**, you can edit the logging configuration of buckets if you are the owner of the source and target buckets.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, click the name of the bucket that you want to edit.

- 4 Click **Properties**.
- 5 In the **Logging** card, click **Edit**.
- 6 Edit the logging configuration as necessary and **Save**.

## Working with Cross-Origin Resource Sharing Rules

Cross-origin resource sharing (CORS) is a mechanism for client web applications loaded in one domain to interact with resources in a different domain. With CORS, you can selectively allow cross-origin access to your VMware Cloud Director Object Storage Extension resources.

Using the VMware Cloud Director Object Storage Extension tenant portal, you can define multiple CORS rules at the bucket level.

CORS rules at the bucket level only take effect on virtual hosted-style S3 API requests. If you access resources using path-style S3 API requests, the global CORS rules take effect.

### Create a Cross-Origin Resource Sharing Rule


Within a cross-origin resource sharing (CORS) rule, you define the allowed request origins, methods, headers, the maximum age of the request, and the exposed headers.

#### Prerequisites

Verify that you have the required set of rights to create CORS rules for a bucket.

- If you are an **organization administrator**, you can create CORS rules for the buckets that users in your organization own.
- If you are an **organization user**, you can create CORS rules for the buckets that you own.

#### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, click the name of the bucket that you want to edit.
- 4 Click **Properties**.
- 5 In the **Cross-Origin Resource Sharing** section, click the text.
- 6 Enter the details of the rule and click **Save**.
  - a Enter an ID for the rule or select the **Auto Generate** check box.
  - b Enter the allowed request origins or select the **All Origins** check box.
  - c Select the allowed request methods.
  - d (Optional) Enter the allowed request headers.



- e (Optional) Enter the exposed headers.
- f (Optional) Enter the maximum age allowed for requests.


## Edit a Cross-Origin Resource Sharing Rule

To address changes in the architecture of your web application, you can edit existing cross-origin resource sharing (CORS) rules.

### Prerequisites

Verify that you have the required set of rights to edit CORS rules for a bucket. To edit CORS rules for a bucket, you must be the owner of the bucket.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, click the name of the bucket that you want to edit.
- 4 Click **Properties**.
- 5 In the **Cross-Origin Resource Sharing** card, click **Edit**.
- 6 Edit the details of the rule as necessary and click **Save**.

## Add Tags to a Bucket

Use tags to categorize your buckets. A tag represents a key-value pair.


If you use Cloudian HyperStore, you can add tags to your buckets. The ECS storage platform does not support tagging.

### Prerequisites

Verify that you have the required set of rights to add tags to a bucket.

- If you are an **organization administrator**, you can add tags to buckets that users in your organization own.
- If you are an **organization user**, you can add tags to the buckets that you own.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, click the name of the bucket that you want to edit.
- 4 On the **Properties** tab, click the link in the **Tags** section.
- 5 Enter a key-value for the tag and click **Save**.

## Sharing Buckets

By using the VMware Cloud Director Object Storage Extension tenant portal, you can share buckets with specific users, or with all users in your tenant organization. You can also make buckets public and share buckets over the Internet.

You can share one bucket at a time. To share a bucket, you edit the access permissions to the bucket by using the built-in canned access control lists, or by creating a custom access control list.

### Share a Bucket Using a Canned Access Control List

Canned access control lists are predefined, built-in access control lists that you can use to share buckets within your organization or publicly over the Internet.

---

**Note** Setting a canned access control list to a bucket overwrites existing permissions configuration for the bucket.


---

#### Prerequisites

Verify that you have the required set of rights to share a bucket.

- If you are an **organization administrator**, you can share buckets that users in your organization own.
- To share a bucket as an **organization user**, you must be the owner of the bucket.
- Alternatively, the owner must assign one of the following sets of permissions for the bucket to your user account.
  - **Read of Bucket, Write of Bucket, Read of ACL, and Write of ACL**
  - **Read of Bucket, Read of ACL, and Write of ACL**
  - **Full Control**

#### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, click the name of the bucket that you want to share.
- 4 On the **Permissions** tab, click **Set Canned ACL**.
- 5 Select a canned access control list name for the bucket and click **Set ACL**.

Option	Description
<b>Private</b>	Only the bucket owner and the <b>organization administrator</b> can access the bucket.
<b>Public Read</b>	Grants <b>Read</b> permissions on the bucket to all users.
<b>Public Read/Write</b>	Grants <b>Read</b> and <b>Write</b> permissions on the bucket to all users.

Option	Description
<b>Tenant Read</b>	Grants <b>Read</b> permissions on the bucket to all users within the VMware Cloud Director organization. If you use the ECS storage platform, this option is not available.
<b>Tenant Read/Write</b>	Grants <b>Read</b> and <b>Write</b> permissions on the bucket to all users within the VMware Cloud Director organization. If you use the ECS storage platform, this option is not available.
<b>System Logger</b>	To write bucket logs, VMware Cloud Director Object Storage Extension uses the System Logger account. Modifying the permissions of the System Logger account for a logging target bucket might result in failure to write bucket logs. For more information, see <a href="#">Working with Bucket Logs</a> . If you use the ECS storage platform, this option is not available.

## Share a Bucket Using a Custom Access Control List

You can share buckets with users in your organization by creating a custom access control list.

The following table describes the available access control list options.


Option	Description
<b>Full Control</b>	Grants <b>Read</b> and <b>Write</b> permissions on the bucket, and <b>Read</b> and <b>Write</b> permissions for the access control list of the bucket.
<b>Read of Bucket</b>	Grants <b>Read</b> permissions on the bucket.
<b>Write of Bucket</b>	Grants <b>Write</b> permissions on the bucket.
<b>Read of ACL</b>	Grants <b>Read</b> permissions on the access control list of the bucket.
<b>Write of ACL</b>	Grants <b>Write</b> permissions on the access control list of the bucket.

### Prerequisites

Verify that you have the required set of rights to share a bucket.

- If you are an **organization administrator**, you can share buckets that users in your organization own.
- If you are an **organization user**, you must either be the owner of the bucket, or the owner must assign to your user account one of the following sets of bucket permissions.
  - **Read of Bucket, Write of Bucket, Read of ACL, and Write of ACL**
  - **Read of Bucket, Read of ACL, and Write of ACL**
  - **Full Control**

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.


- 3 In the **Buckets** pane, click the name of the bucket that you want to share.
- 4 On the **Permissions** tab, click **Edit**.
- 5 Configure the required set of permissions for the bucket and click **Save**.
  - To share the bucket with users from your tenant organization, use the toggle buttons in the **Tenant Users** row.  
If you use the ECS storage platform, this option is not available.
  - To share the bucket with authenticated users from all tenant organizations, use the toggle buttons in the **Authenticated Users** row.
  - To share the bucket with all users, use the toggle buttons in the **Public** row.
  - To share the bucket with specific users within your organization, click the **Add User** button, select the user, and use the toggle buttons in the corresponding row.
  - To write bucket logs, VMware Cloud Director Object Storage Extension uses the System Logger account. Modifying the permissions of the System Logger account for a logging target bucket might result in failure to write bucket logs. For more information, see [Working with Bucket Logs](#).  
If you use the ECS storage platform, this option is not available.

## Review Shared Buckets

As an **organization user**, you can review all buckets that other users shared with you. As an **organization administrator**, you can review the buckets of all users within your organization.

If you use the Cloudian HyperStore platform, you can review shared buckets. The ECS storage platform does not support reviewing shared buckets.


### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, click **Shared Buckets**.

## Synchronize a Bucket

To reflect the recent changes that are made in the back end, you can force the bucket-level synchronization between the VMware Cloud Director tenant portal and the back-end services.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.

- 3 In the **Buckets** pane, click the name of the bucket that you want to synchronize and click **Sync**.

#### Results

After the synchronization process completes, you can see all changes to the contents of the bucket.

## Empty a Bucket


To clean up the inventory of VMware Cloud Director Object Storage Extension and to free storage space, you can empty a bucket. By emptying a bucket, you delete all objects from the bucket at once and preserve the access control configuration of the bucket.

#### Prerequisites

Verify that you have the required set of rights to empty a bucket.

- If you are an **organization administrator**, you can empty buckets that users in your organization own.
- If you are an **organization user**, you can delete a bucket if you are the owner of the bucket, or the owner must assign to your user account **Bucket Read** and **Bucket Write** permissions on the bucket.

#### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, select the bucket that you want to empty.
- 4 Click **Empty**.
- 5 If versioning is enabled for the bucket, you can optionally select the **All versions** check box, so that all versions of all objects in the bucket are deleted.

If you do not select the check box, you delete only the latest versions of the objects in the bucket.

- 6 To confirm the operation, click **Empty**.

## Delete a Bucket


To clean up buckets that you no longer need from VMware Cloud Director Object Storage Extension, you can delete the buckets. You can delete one bucket at a time.

As an **organization user** you cannot delete shared buckets and reserved buckets that contain vApps and catalogs.

## Prerequisites

- Verify that you have the required set of rights to delete a bucket.
  - If you are an **organization administrator**, you can delete buckets that users in your organization own.
  - If you are an **organization user**, you can only delete the buckets that you own.
- Verify that the bucket you want to delete does not store any objects.

## Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, select the bucket that you want to delete.
- 4 Click **Delete** and confirm the deletion.

# Working with Objects

# 4

Objects are the files that you upload to VMware Cloud Director Object Storage Extension. You manage objects by using the VMware Cloud Director Object Storage Extension tenant portal.

As an **organization user**, you can upload, edit, share, copy, preview, download, and delete the objects that you own. You can also operate with the objects that are shared with you. The operations that you can perform depend on the permissions that are assigned to your user account for a particular object.

As an **organization administrator**, you can manage the objects of all organization users using the privilege of the object owner.

This chapter includes the following topics:

- [Working with Folders](#)
- [Upload Files to VMware Cloud Director Object Storage Extension](#)
- [Add Tags and Metadata to an Object](#)
- [Sharing Objects](#)
- [Copy an Object](#)
- [Preview an Object](#)
- [Download an Object](#)
- [Delete an Object](#)

## Working with Folders

Starting with VMware Cloud Director Object Storage Extension 1.0.1 you can use folders and subfolders to group and organize objects.

## How Do I Use Folders Within VMware Cloud Director Object Storage Extension Buckets

Buckets and objects are the primary resources in VMware Cloud Director Object Storage Extension. VMware Cloud Director Object Storage Extension has a flat structure with no hierarchy like in a file system. However, to achieve organizational simplicity, VMware Cloud Director Object Storage Extension supports the folder concept as a means of grouping objects. VMware Cloud Director Object Storage Extension supports the folder concept by using the full name of a folder as a prefix for the object names within the folder. In the context of folders, object names are called key names.

For example, you can create a folder called *monthly-reports* and store an object named *report-jan.xlsx* in the folder. The object is then stored with the key name *monthly-reports/report-jan.xlsx*, where *monthly-reports/* is the prefix.

You can create folders within folders but you cannot create buckets within buckets. You can directly upload objects to a folder. You can copy an object from a folder to a bucket. By using the VMware Cloud Director Object Storage Extension user interface, you cannot directly copy an object from one folder to another folder. To copy an object to another folder, use the *VMware Cloud Director Object Storage Extension API*. You can create and delete folders, but you cannot rename a folder. You cannot edit access permissions at the folder level.

### Limitations for Catalog Buckets

When working with folders within catalog buckets, consider the following limitations:

- You can have only one level of folders. No subfolders are allowed.
- You can only upload OVA and ISO files to the main directory of a catalog bucket.
- You can only upload OVF and VMDK files to a folder in a catalog bucket.
- You can upload only one OVF file to a folder in a catalog bucket.

### Create a Folder

To organize the objects in your buckets, you can create folders and group the objects as appropriate.

Once a folder is created, you cannot rename it.


#### Prerequisites

Verify that you have the required set of rights to create a folder in a bucket.

- If you are an **organization administrator**, you can create folders in the buckets that users in your organization own.
- If you are an **organization user**, to create a folder, you must be the owner of the bucket, or the owner of the bucket must assign **Read** and **Write** permissions for the bucket to your user account.



**Procedure**

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, navigate to the bucket in which you want to create a folder.
- 4 Click **Create Folder** and enter a name for the folder.
- 5 To create the folder, click **Create**.

**Delete a Folder**


To clean up the inventory of VMware Cloud Director Object Storage Extension and to free storage space, you can delete a folder. By deleting a folder, you delete all objects in the folder.

**Prerequisites**

Verify that you have the required set of rights to empty a bucket.

- If you are an **organization administrator**, you can delete folders that users in your organization own.
- If you are an **organization user**, to delete a folder, you must be the owner of the bucket that stores the folder, or the owner must assign to your user account **Bucket Read** and **Bucket Write** permissions on the bucket.

**Procedure**

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, click the name of the bucket that stores the folder that you want to delete.
- 4 If versioning is enabled for the bucket, hide object versions by using the Show Versions toggle button.
- 5 Select the folder that you want to delete.
- 6 From the **Actions** drop-down menu, select **Delete**.
- 7 If versioning is enabled for the bucket that stores the folder, you can optionally select the **All versions** check box.

If you select the **All versions** check box, you delete all versions for all objects in the folder. If you do not select the check box, you delete only the latest versions of all objects in the folder.

- 8 To confirm the deletion, select the **Confirm deletion** check box and click **Delete**.

# Upload Files to VMware Cloud Director Object Storage Extension

Objects in VMware Cloud Director Object Storage Extension are the files that you upload.


**Important** When uploading files to VMware Cloud Director Object Storage Extension, do not navigate out of the VMware Cloud Director Object Storage Extension tenant portal until the upload process completes. Leaving the VMware Cloud Director Object Storage Extension tenant portal within the same user session interrupts the upload process.

## Prerequisites

Verify that you have the required set of rights to upload files to a bucket.

- As an **organization administrator**, you can upload an object to the buckets that users in your organization own.
- As an **organization user**, you can upload an object if you are the owner of the bucket, or the owner must assign to your user account **Write of Bucket** permissions on the bucket .

## Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, navigate to the bucket or folder to which you want to upload files.
- 4 Click **Upload**.
- 5 Select whether to overwrite the objects with the same name.

By default, VMware Cloud Director Object Storage Extension overwrites files with the same name. If an object with the same name exists in the bucket and versioning is enabled for the bucket, you can upload a new version of the object.

- 6 Click the folder icon () , navigate to the files that you want to upload, and click **Upload**.

## Add Tags and Metadata to an Object

To improve the categorization of objects in VMware Cloud Director Object Storage Extension, bucket owners can optionally add tags to individual objects. As a bucket owner, you can also add properties to objects by adding user-defined metadata. Both the object tags and the object metadata represent a key-value pair.

If a bucket owner adds tags to an object owned by another user, and the object owner does not have **FULL\_CONTROL** privileges for the bucket, the object owner cannot edit the metadata of the object anymore.

If you use the Cloudian HyperStore storage platform, you can add tags to your objects. The ECS storage platform does not support tagging.

---

**Important** Adding metadata to an object overwrites the original object and resets permissions and other associations for the object.


---

You cannot edit the metadata of bucket log objects owned by the System Logger account.

### Prerequisites

- Verify that you have the required set of rights to add tags to an object.
  - If you are an **organization administrator**, you can add tags to objects that users in your organization own.
  - If you are an **organization user**, you can add tags to objects, if you are the owner of the bucket that stores the object.
- Verify that you have the required set of rights to edit the metadata of an object.
  - If you are an **organization administrator**, to add metadata to an object, make sure that the object owner has **Write of Bucket** permissions on the bucket that stores the object.
  - If you are an **organization user**, to add metadata to an object, you must be the object owner and your user account must have **Write of Bucket** permissions.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, navigate to the bucket or folder that stores the object that you want to edit.
- 4 Click the name of the object that you want to edit.
- 5 Add a tag to the object
  - a Click the link in the **Tags** section.
  - b Enter a key-value for the tag.
  - c Click **Save**.
- 6 Add metadata to the object.
  - a Click the link in the **Metadata** section.
  - b Enter a key-value for the metadata entry.
  - c To indicate that you understand the effect of adding metadata to an object, select the check box.
  - d Click **Save**.

## Sharing Objects

By using the VMware Cloud Director Object Storage Extension tenant portal, you can share objects with specific users, or with all users within your tenant organization. You can also make objects public and share objects over the Internet.

You can share one object at a time. To share an object, you edit the access permissions of the object by using the built-in canned access control lists, or by creating a custom access control list.

If versioning is enabled for the bucket in which the object that you want to share resides, you can share a specific version of the object.

### Share an Object by Using a Canned Access Control List

Canned access control lists are predefined, built-in access control lists that you can use to share objects within your organization or publicly over the Internet.

---

**Note** Setting a canned access control list to an object overwrites existing permissions configuration for the object.


---

#### Prerequisites

Verify that you have the required set of rights to share objects.

- If you are an **organization administrator**, you can share objects that users in your organization own.
- If you are an **organization user**, you can share objects, if you are the owner of the object, or the owner must assign either **Full Control**, or **Read of ACL** and **Write of ACL** permissions on the object.

#### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, navigate to the bucket or folder in which the object that you want to share resides.
- 4 If you want to share a specific version of the object, display all versions of the object by using the **Show Versions** toggle button.
- 5 Click the name of the object or the object version that you want to share.
- 6 On the **Permissions** tab, click **Set Canned ACL**.

- 7 Select a canned access control list name for the object and click **Set ACL**.

Option	Description
<b>Private</b>	Only the object owner and the <b>organization administrator</b> can access the object.
<b>Public Read</b>	Grants <b>read</b> permissions on the object to all users and makes the object public.
<b>Bucket Owner Read</b>	Grants <b>read</b> permissions on the object to the bucket owner.
<b>Bucket Owner Full-Control</b>	Grants <b>full control</b> permissions on the object to the bucket owner.
<b>Tenant Read</b>	Grants <b>read</b> permissions on the object to all users within the VMware Cloud Director organization. If you use the ECS storage platform, this option is not available.

## Share an Object by Using a Custom Access Control List

To share an object with specific users within or outside of your organization, you can create a custom access control list for the object that you want to share.

The following table describes the available access control list options.


Option	Description
Full Control	Grants <b>Read</b> permissions on the object and <b>Read</b> , and <b>Write</b> permissions on the access control list of the object.
Read of Object	Grants <b>Read</b> permissions for the object.
Read of ACL	Grants <b>Read</b> permissions for the access control list of the object.
Write of ACL	Grants <b>Write</b> permissions for the access control list of the object.

### Prerequisites

Verify that you have the required set of rights to share objects.

- If you are an **organization administrator**, you can share objects that users in your organization own.
- If you are an **organization user**, you must be the owner of the object, or the owner must assign to your user account either **Full Control**, or **Read of ACL** and **Write of ACL** permissions on the object.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, navigate to the bucket or folder that stores the object that you want to share.

- 4 If you want to share a specific version of the object, display all versions of the object by using the **Show Versions** toggle button.
- 5 Click the name of the object or the object version that you want to share.
- 6 On the **Permissions** tab, click **Edit**.
- 7 Configure the required set of permissions on the object and click **Save**.
  - To share the object with users from your tenant organization, use the toggle buttons in the **Tenant Users** row. If you use the ECS storage platform, this option is not available.
  - To share the object with authenticated users from all tenant organizations, use the toggle buttons in the **Authenticated Users** row.
  - To share the object with all users, use the toggle buttons in the **Public** row.
  - To share the object with a specific user within your organization, click the **Add User** button, select the user from the drop-down menu, or enter the organization user name of the user, and use the toggle buttons in the corresponding row.

## Copy an Object

You can copy objects from one bucket to another by using the VMware Cloud Director Object Storage Extension tenant portal.

If you are an **organization administrator** and you copy an object owned by one user to a bucket that another user owns, the owner of the destination bucket is permanently granted with **Read of Object** permissions on the source object.

---

**Important** When you copy files, do not navigate out of the VMware Cloud Director Object Storage Extension tenant portal until the process completes. Leaving the VMware Cloud Director Object Storage Extension tenant portal within the same user session interrupts the process.


---

### Prerequisites

Verify that you have the required set of rights to copy an object.

- If you are an **organization administrator**, you can copy objects that users in your organization own.
- If you are an **organization user**, you must be the owner of the object, or the owner must assign **Read of Object** permissions on the object to your user account. To copy objects to buckets that other users own, use *VMware Cloud Director Object Storage Extension API Reference*.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, navigate to the bucket or folder that stores the object that you want to copy.

- 4 Select the objects that you want to copy.
- 5 From the **Actions** drop-down menu, select **Copy to**.
- 6 Select the destination bucket.
- 7 Select whether you want to overwrite the objects with the same name.

By default, VMware Cloud Director Object Storage Extension overwrites files with the same name.

- 8 Confirm that you understand the effect of copying an object and click **Copy**.

## Preview an Object

You can preview a list of file formats directly from the VMware Cloud Director Object Storage Extension tenant portal.

- Image files, such as JPEG, PNG, and GIF
- Text files, such as plain text, HTML, XML, and JSON
- Portable Document Format files (PDF)
- Audio and video files, such as MP4, MPEG, WAV, WebM


If versioning is enabled for the bucket that stores the object that you want to preview, you can preview a specific version of the object.

### Prerequisites

Verify that you have the required set of rights to preview an object.

- If you are an **organization administrator**, you can preview all objects owned by or shared with users within your organization.
- If you are an **organization user**, you can preview objects that you own or that are shared with you. As an **organization user**, to preview objects, **Read of Object** permissions on the object must be assigned to your user account.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, navigate to the bucket or folder that stores the object you want to preview.
- 4 If you want to preview an earlier version of the object, display all versions of the object by using the **Show Versions** toggle button.
- 5 Click the name of the object or the object version that you want to preview.

## 6 Click **Preview**.

A preview of the object appears in the VMware Cloud Director Object Storage Extension tenant portal.

## Download an Object

You can download only one object at a time.


If versioning is enabled for the bucket that stores the object that you want to download, you can download a specific version of the object.

### Prerequisites

Verify that you have the required set of rights to download an object.

- If you are an **organization administrator**, you can download all objects owned by or shared with users within your organization.
- If you are an **organization user**, to download objects, you must be the owner of the object, or **Read of Object** permissions must be assigned to your user account.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, navigate to the bucket or folder that stores the object that you want to download.
- 4 If you want to download a specific version of the object, display all versions of the object by using the **Show Versions** toggle button.
- 5 Select the object or the object version that you want to download.
- 6 From the **Actions** drop-down menu, select **Download**.
- 7 Navigate to the location to which you want to download the object and click **Save**.

### Results

After the download process completes, the file is available in the destination directory.

## Delete an Object

To free storage space in VMware Cloud Director Object Storage Extension, you can delete the objects that you no longer need. You can delete multiple objects simultaneously.

After you delete an object from VMware Cloud Director Object Storage Extension, you cannot restore it.




## Prerequisites

Verify that you have the required set of rights to delete an object.

- If you are an **organization administrator**, you can delete objects that users in your organization own.
- If you are an **organization user**, to delete an object, you must be the owner of the object, or the owner must assign **Read of Bucket** and **Write of Bucket** permissions on the bucket that stores the object to your user account.

## Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Buckets** pane, navigate to the bucket or folder that stores the objects that you want to delete.
- 4 If you want to delete a specific version of an object, display all versions of the object by using the **Show Versions** toggle button.
- 5 Select the object or the object version that you want to delete.
- 6 From the **Actions** drop-down menu, select **Delete** and confirm the deletion.

## Results

If versioning is not enabled for the bucket that stores the object you deleted, the object is deleted and cannot be restored. If versioning is enabled for the bucket and you do not select a specific version to be deleted, you delete only the last version of the object. To retrieve earlier versions of the object, use the **Show Versions** toggle button.

# Working with Multiple Sites

# 5

The VMware Cloud Director Multisite feature enables a service provider or a tenant of multiple, geographically distributed VMware Cloud Director installations (server groups) to manage and monitor those installations and their organizations as single entities.

For more information about the VMware Cloud Director Multisite feature, see the *VMware Cloud Director Service Provider Admin Portal Guide* and the *VMware Cloud Director Tenant Portal Guide*.

Starting with VMware Cloud Director Object Storage Extension 1.0.1, you can deploy and configure VMware Cloud Director Object Storage Extension within a multisite VMware Cloud Director environment. For more information about configuring VMware Cloud Director Object Storage Extension within a multisite VMware Cloud Director environment, see *Installing, Configuring, and Upgrading VMware Cloud Director Object Storage Extension*.

When VMware Cloud Director Object Storage Extension is configured within a multisite VMware Cloud Director environment, tenant users can preview and download objects in the remote site.

This chapter includes the following topics:

- [Preview an Object in a Remote Site](#)
- [Download an Object from a Remote Site](#)
- [Switch to a Remote Site](#)

## Preview an Object in a Remote Site


You can preview a list of file formats directly from the VMware Cloud Director Object Storage Extension tenant portal.

- Image files, such as JPEG, PNG, and GIF
- Text files, such as plain text, HTML, XML, and JSON
- Portable Document Format files (PDF)
- Audio and video files, such as MP4, MPEG, WAV, WebM

### Prerequisites

Verify that you are the owner of the object in the remote site that you want to preview. In the remote site, you can only preview the objects that you own.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the upper-left corner of the **Buckets** pane, use the drop-down menu to select the remote site.
- 4 Navigate to the bucket or folder storing the object that you want to preview.
- 5 Click the name of the object that you want to preview.
- 6 Click **Preview**.

A preview of the object appears in the VMware Cloud Director Object Storage Extension tenant portal.

## Download an Object from a Remote Site


You can download objects from remote sites. You can download only one object at a time.

### Prerequisites

Verify that you have the required set of rights to download an object.

- If you are an **organization administrator**, you can download the objects that are owned by or shared with users within your organization.
- If you are an **organization user**, to download objects, you must be the owner of the object, or you must have the **Read of Object** permission assigned to your user account.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the upper-left corner of the **Buckets** pane, use the drop-down menu to select the remote site.
- 4 Navigate to the bucket or folder storing the object that you want to download and select it.
- 5 From the **Actions** drop-down menu, select **Download**.
- 6 Navigate to the location to which you want to download the object and click **Save**.



### Results

After the download process completes, the file is available in the destination directory.

## Switch to a Remote Site

**Organization users** can only preview and download objects that they own from remote sites. To work with objects that are shared with you, or to perform other actions with the objects that you own from remote sites, you must switch to the remote site.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the upper-left corner of the **Buckets** pane, select the site to which you want to switch to.
- 4 Click the **pop-out** icon () next to the site to which you want to switch.

The user interface of VMware Cloud Director Object Storage Extension in the remote site opens in a new browser window.

# Working with VMware Cloud Director Objects

# 6

With VMware Cloud Director Object Storage Extension, you can back up, restore, and share VMware Cloud Director vApps.

You can also create and publish VMware Cloud Director Object Storage Extension catalogs to VMware Cloud Director. Using the VMware Cloud Director Object Storage Extension catalogs, you can synchronize and share VMware Cloud Director catalogs.

This chapter includes the following topics:

- [Working with vApps in VMware Cloud Director Object Storage Extension](#)
- [Working with Catalogs](#)

## Working with vApps in VMware Cloud Director Object Storage Extension

You can use VMware Cloud Director Object Storage Extension to store vApps that you do not currently use. This way, you can free storage space from VMware Cloud Director datastores. Later, you can restore the vApp back in the datastore and continue to use the same vApp in VMware Cloud Director.

### Capture vApps

By capturing a vApp, you copy all data that the vApp consumes to VMware Cloud Director Object Storage Extension. By capturing a vApp, you create a backup copy of the data that the vApp contains. You can later restore the vApp back to its original location or download the vApp locally for archiving purposes.

By capturing a vApp, you do not copy the storage reservation from VMware Cloud Director to VMware Cloud Director Object Storage Extension.


You can capture up to 10 vApps simultaneously.

#### Prerequisites

- Verify that you have the required set of rights to capture vApps.
  - If you are an **organization administrator**, you have all required VMware Cloud Director rights to manage vApps.

- If you are an **organization user**, verify that you have the **vApp: View VM Metrics** and **vApp: Download** rights assigned to your user account in VMware Cloud Director.
- Verify that the vApp you want to capture is turned off.

#### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **vApps** pane, click **Capture**.
- 4 Select the vApps that you want to capture and click **Next**.
- 5 (Optional) Enter different names for the vApps and enter a description.
- 6 Click **Capture**.

#### Results

After the capture task completes, the captured vApps are listed in the VMware Cloud Director Object Storage Extension tenant portal vApp list. You can share, download, delete, or restore the vApps.

## Share a vApp

You can share vApps that are stored in VMware Cloud Director Object Storage Extension with other users within your organization or publicly over the Internet.


You can share one vApp at a time.

#### Prerequisites

Verify that you have the required set of rights to share a vApp.

- If you are an **organization administrator**, you can share all vApps that users in your organization own.
- If you are an **organization user**, to share a vApp as, you must be the vApp owner.

#### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **vApps** pane, select the vApp that you want to share.
- 4 From the **Actions** drop-down menu, select **Share**.


- 5 Select the sharing status for the vApp and click **Set Sharing Status**.

Option	Description
<b>Private</b>	Only the object owner and the <b>organization administrator</b> can manage the vApp in VMware Cloud Director Object Storage Extension.
<b>Tenant</b>	Grants <b>read</b> permissions for the vApp to all users within the same organization. If you use the ECS storage platform, this option is not available.
<b>Public</b>	Grants <b>read</b> permissions for the vApp to all users.

## Review Shared vApps

As an **organization user**, you can review all vApps that other users shared with you. As an **organization administrator**, you can review all the vApps within your organization.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **vApps** pane, click **Shared vApps**.

## Download a vApp

For archiving purposes, or to save storage space in VMware Cloud Director Object Storage Extension, you can download vApps locally as an OVA file.


You can download one vApp at a time.

### Prerequisites

Verify that you have the required set of rights to download a vApp.

- If you are an **organization administrator**, you can download all vApps that users in your organization own.
- If you are an **organization user**, to download a vApp as, you must be the vApp owner or the owner must share the vApp with you.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **vApps** pane, select the vApp that you want to download.
- 4 From the **Actions** drop-down menu, select **Download**.
- 5 Select the location to which you want to download the vApp and start the download process.

## Upload a vApp

You can upload an archived vApp to VMware Cloud Director Object Storage Extension and later restore, and use the vApp in VMware Cloud Director.



You can upload up to 10 vApps at once. The vApp files that you upload must have the OVA file extension.

---

**Important** When uploading files to VMware Cloud Director Object Storage Extension, do not navigate out of the VMware Cloud Director Object Storage Extension tenant portal until the upload process completes. Leaving the VMware Cloud Director Object Storage Extension tenant portal within the same user session interrupts the upload process.

---

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **vApps** pane, click **Upload**.
- 4 Select whether you want to overwrite objects with the same name.  
By default, VMware Cloud Director Object Storage Extension overwrites files with the same name.
- 5 Click the folder icon () , navigate to the files that you want to upload, and click **Upload**.

## Restore a vApp

To use a vApp that you store in VMware Cloud Director Object Storage Extension, you restore the vApp back to VMware Cloud Director. You can restore one vApp at a time.

When you restore a vApp, you can edit the hardware properties of each virtual machine that the vApp contains.


### Prerequisites

- Verify that you have the required set of rights to restore a vApp.
  - As an **organization administrator**, you have all required VMware Cloud Director rights to manage vApps.  
As an **organization administrator**, you can restore all vApps that users in your organization own.
  - As an **organization user**, verify that you have the **vApp: Upload**, **vApp: Create / Reconfigure**, and the **Organization vDC: View** permissions assigned to your user account in VMware Cloud Director.  
As an **organization user**, you can restore a vApp, if you are the vApp owner, or the owner has shared the vApp with you.



- Verify that the target organization virtual data center has enough compute resources to accommodate the vApp that you restore.

#### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **vApps** pane, select the vApp that you want to restore and click **Restore**.
- 4 (Optional) Edit the name of the vApp.
- 5 Select the target virtual data center for the vApp.
- 6 (Optional) Edit the hardware settings of the virtual machines that the vApp contains.
- 7 To start the restore task, click **Restore**.

#### Results

After the restore task completes, the vApp is available in the inventory of VMware Cloud Director.

#### What to do next

You can start using the vApp in VMware Cloud Director.

If you no longer need a backup copy of the same vApp, you can delete the vApp from VMware Cloud Director Object Storage Extension.

## Delete vApps

When you no longer need a vApp in VMware Cloud Director Object Storage Extension, you can delete it.


You can delete multiple vApps simultaneously. You cannot restore vApps that you delete from VMware Cloud Director Object Storage Extension.

#### Prerequisites

Verify that you have the required set of rights to delete vApps.

- If you are an **organization administrator**, you can delete all vApps that users in your organization own.
- If you are an **organization user**, to delete a vApp, you must be the vApp owner. **Organization users** cannot delete shared vApps.

#### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **vApps** pane, select the vApps that you want to delete.

- 4 From the **Actions** drop-down menu, select **Delete** and confirm the operation.

#### Results

The vApps that you delete are no longer stored in VMware Cloud Director Object Storage Extension.

## Working with Catalogs


A catalog in VMware Cloud Director Object Storage Extension is a container for ISO, OVA, OVF, MF, and VMDK files.

### Create a Catalog

When you create a catalog, VMware Cloud Director Object Storage Extension creates a catalog bucket and reserves it as a system bucket.

Although the catalog bucket appears in the **Buckets** pane in VMware Cloud Director Object Storage Extension, you cannot interact with catalog buckets the same way you interact with regular buckets. You interact with catalog buckets from the **Catalogs** pane.

#### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Catalogs** pane, click **New Catalog**.
- 4 Enter a name for the catalog and click **Save**.

#### Results

The new catalog appears in the list of catalogs in the **Catalogs** pane.

#### What to do next

You can upload files to the catalog.

### Create a Template in a Catalog

Templates are the folders within catalogs in VMware Cloud Director Object Storage Extension.

For every OVA file that you upload, VMware Cloud Director Object Storage Extension creates a folder with the OVA filename and extracts the OVF, MF, and VMDK files to the folder.


You can also manually create a template within a catalog and upload OVF and VMDK files to that folder.

## Prerequisites

Verify that you have the required set of rights to create a template in a catalog.

- If you are an **organization administrator**, you can create templates in all catalogs that users in your organization own.
- If you are an **organization user**, you can create templates in catalogs that you own.

## Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Catalogs** pane, click the name of the catalog in which you want to create a template.
- 4 Click **Create Template**, enter a name for the template, and confirm the creation.

## Upload Files to a Catalog

You can upload ISO and OVA files to a catalog in VMware Cloud Director Object Storage Extension.

For every OVA file that you upload, VMware Cloud Director Object Storage Extension creates a folder with the OVA filename and extracts the OVF, MF, and VMDK files to the folder. You cannot modify the objects in such folders, you can only delete them.

You can manually create a template within a catalog and upload OVF and VMDK files to that folder.

If you replace the OVA or ISO files within a published catalog, the operation increases the version of the vApp Template or the media item within the catalog.

You cannot upload OVF and VMDK files to the main directory of a catalog.

---

**Important** When uploading files to VMware Cloud Director Object Storage Extension, do not navigate out of the VMware Cloud Director Object Storage Extension tenant portal until the upload process completes. Leaving the VMware Cloud Director Object Storage Extension tenant portal within the same user session interrupts the upload process.

---



## Prerequisites

Verify that you have the required set of rights to upload files to a catalog.

- If you are an **organization administrator**, you can upload files to all catalogs that users in your organization own.
- If you are an **organization user**, to upload files to a catalog, you must be the catalog owner.

## Procedure

- 1 Log in to the VMware Cloud Director tenant portal.

- 2 From the main menu () , select **Object Storage**.
- 3 In the **Catalogs** pane, click the name of the catalog or the template to which you want to upload files.
- 4 Click **Upload**.
- 5 Click the folder icon () , navigate to the files that you want to upload, and click **Upload**.

## Import a Catalog to VMware Cloud Director

If you created a catalog in VMware Cloud Director Object Storage Extension and uploaded media files to the catalog, you can import the catalog to VMware Cloud Director. When you import a catalog to VMware Cloud Director, **organization users** can work with the catalog contents directly in VMware Cloud Director.


When you import a catalog from VMware Cloud Director Object Storage Extension to VMware Cloud Director, you create a catalog in VMware Cloud Director that contains all objects stored in the VMware Cloud Director Object Storage Extension catalog.

### Prerequisites

Verify that you have the required set of rights to import catalogs to VMware Cloud Director.

- As an **organization administrator**, you have all required VMware Cloud Director rights to manage catalogs.
- As an **organization user**, verify that you have the following rights assigned to your user account in VMware Cloud Director:
  - **Catalog: Create / Delete a Catalog**
  - **Organization vDC: View**
  - **Organization vDC Network: View Properties**

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Catalogs** pane, select the catalog that you want to import and click **Import**.
- 4 (Optional) Change the catalog name.  
The name that you enter is used as the catalog name in VMware Cloud Director.
- 5 To start the import process, click **Import**.

### Results

After the task completes, you can start using the objects in the VMware Cloud Director tenant portal.

## Publish a Catalog

When you publish a catalog, you make the catalog available for a subscription from VMware Cloud Director.


When you publish a catalog, VMware Cloud Director Object Storage Extension creates JSON files that contain all metadata and descriptors which the VMware Cloud Director catalogs require for an external subscription. For more information, see [Subscribe to an External Catalog](#).

### Prerequisites

Verify that you have the required set of rights to publish a catalog.

- If you are an **organization administrator**, you can publish all catalogs that users in your organization own.
- If you are an **organization user**, to publish a catalog, you must be the catalog owner.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Catalogs** pane, select the catalog that you want to publish and click **Publish**.
- 4 Note the subscription URL and password, as you need them to configure the subscription in the VMware Cloud Director tenant portal.
- 5 Click **OK**.

### What to do next

After the catalog publishing task completes, you can configure the subscription to the catalog.

## Share a Catalog


You can share VMware Cloud Director Object Storage Extension catalogs with other users within your organization or publicly over the Internet.

### Prerequisites

- Verify that you have the required set of rights to share a catalog.
  - If you are an **organization administrator**, you can share all catalogs that users in your organization own.
  - If you are an **organization user**, to share a catalog, you must be the catalog owner.
- Verify that the catalog you want to share is published. You cannot share catalogs that are not published.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.


- 2 From the main menu () , select **Object Storage**.
- 3 In the **Catalogs** pane, select the catalog that you want to share.
- 4 From the **Actions** drop-down menu, select **Share**.
- 5 Select the sharing status for the catalog and click **Set Sharing Status**.

Option	Description
Private	Only the object owner and the <b>organization administrator</b> can manage the catalog in VMware Cloud Director Object Storage Extension.
Tenant	Grants all users within the same organization with <b>Read</b> permissions on the catalog. If you use the ECS storage platform, this option is not available.
Public	Grants all users with <b>Read</b> permissions on the catalog.

## Review Shared Catalogs

As an **organization user**, you can review all catalogs that other users shared with you. As an **organization administrator**, you can review all the catalogs within your organization.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Catalogs** pane, click **Shared Catalogs**.

## Unpublish a Catalog


When you unpublish a catalog, you restrict the subscription to the catalog from VMware Cloud Director and stop the existing subscriptions.

### Prerequisites

Verify that you have the required set of rights to unpublish a catalog.

- If you are an **organization administrator**, you can unpublish all catalogs that users in your organization own.
- If you are an **organization user**, to unpublish a catalog, you must be the catalog owner.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Catalogs** pane, select the catalog that you want to unpublish and click **Unpublish**.

## Results

After the unpublishing task completes, subscription to the catalog from VMware Cloud Director is not possible.


## Empty a Catalog

To clean up the inventory of VMware Cloud Director Object Storage Extension and to free storage space, you can empty a catalog. By emptying a catalog, you delete all objects from the catalog.

### Prerequisites

- Verify that you have the required set of rights to empty a catalog.
  - If you are an **organization administrator**, you can empty all catalogs that users in your organization own.
  - If you are an **organization user**, to empty a catalog, you must be the catalog owner.
- Verify that the catalog you want to empty is not published. You cannot delete catalogs that are published for an external subscription.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 In the **Catalogs** pane, select the catalog that you want to empty.
- 4 From the **Actions** drop-down menu, select **Empty** and confirm the operation.

## Delete a Catalog


To clean up the inventory of VMware Cloud Director Object Storage Extension, you can delete the catalogs that you no longer need.

### Prerequisites

- Verify that you have the required set of rights to delete a catalog.
  - If you are an **organization administrator**, you can delete all catalogs that users in your organization own.
  - If you are an **organization user**, to delete a catalog, you must be the catalog owner.
- Verify that the catalog you want to delete is not published. You cannot delete catalogs that are published for an external subscription.
- Verify that the catalog you want to delete does not store any objects. If there are objects in the catalog, first you must empty the catalog. See [Empty a Catalog](#).

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.

- 2 From the main menu () , select **Object Storage**.
- 3 In the **Catalogs** pane, select the catalog that you want to delete.
- 4 From the **Actions** drop-down menu, select **Delete** and confirm the deletion.



# Working with Security Credentials

# 7

Security credentials are a pair of an access key and a secret key. You use the keys pair for AWS Signature v4 authentication.

Cloudian HyperStore supports user and application types of security credentials. You can use the keys pair to authenticate S3 API requests and to access and manage objects and buckets.

With S3 API requests, authenticated with user credentials, you can manage all objects that you own or the objects that are shared with you.

With application credentials, you control the S3 API access at the bucket level.

If VMware Cloud Director Object Storage Extension is configured with ECS storage, you can only use user credentials to authenticate S3 API requests. With ECS, each user account has a single pair of an access and secret keys.

You can rotate the user credential. The rotation only updates the secret key. When you rotate a user credential, the old secret key remains active for five minutes.

This chapter includes the following topics:

- [Working with User Credentials](#)
- [Working with Application Credentials](#)

## Working with User Credentials

Users own and manage their user credentials. VMware Cloud Director Object Storage Extension reserves one security credential for system management purposes. You cannot delete or deactivate that credential.


**Organization administrators** and **organization users** can use user credentials only to access and manage buckets and objects that they own or that are shared with them.

### Create a User Credential

To manage your buckets and objects in VMware Cloud Director Object Storage Extension by using S3 API, create a user credential. By default, when you create a user credential, VMware Cloud Director Object Storage Extension activates the credential and you can use it right away.

You can create up to five user credentials.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 Select **Security Credentials > User Credentials** and click **Create**.


### Results

A new security credential appears in the list of user credentials.

## Activate or Deactivate a User Credential

To restrict or grant the S3 API access to your buckets and objects, you can activate and deactivate your user credentials.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 Select **Security Credentials > User Credentials** and select the user credential that you want to activate or deactivate.
- 4 Use the toggle button in the Status column and confirm the operation.


## Delete a User Credential

To clean up the inventory of VMware Cloud Director Object Storage Extension, delete the user credentials that you no longer need.

### Prerequisites

Verify that the user credential is deactivated. You cannot delete active user credentials.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 Select **Security Credentials > User Credentials** and select the user credential that you want to delete.
- 4 Click **Delete** and confirm the operation.

## Working with Application Credentials

Users own and manage their application credentials.


**Organization administrators** and **organization users** can use application credentials only to access and manage buckets that they own.

Application credentials add constraints to the bucket access. With an application credential, an API client cannot create buckets or delete existing buckets. If you specify bucket names during the creation of application credentials, you only allow accessing and managing the specified bucket.

## Create an Application Credential

To manage objects in a specific bucket or buckets by using S3 API, create an application credential. By default, when you create an application credential, VMware Cloud Director Object Storage Extension activates the credential and you can use it right away.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 Select **Security Credentials > Application Credentials** and click **Create**.
- 4 Enter a name for the application credential.
- 5 Select the buckets that can be accessed with the application credential and click **Create**.


### Results

A new security credential appears in the list of application credentials.

## Activate or Deactivate an Application Credential

To restrict or grant the S3 API access to your buckets, you can activate and deactivate your application credentials.

### Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 Select **Security Credentials > Application Credentials** and select the application credential that you want to activate or deactivate.
- 4 Use the toggle button in the Status column and confirm the operation.


## Delete an Application Credential

To clean up the inventory of VMware Cloud Director Object Storage Extension, delete the application credentials that you no longer need.

## Prerequisites

Verify that the application credential is deactivated. You cannot delete active application credentials.

## Procedure

- 1 Log in to the VMware Cloud Director tenant portal.
- 2 From the main menu () , select **Object Storage**.
- 3 Select **Security Credentials > Application Credentials** and select the application credential that you want to delete.
- 4 Click **Delete** and confirm the operation.

# Working with VMware Cloud Director Object Storage Extension S3 API



VMware Cloud Director Object Storage Extension provides a set of S3 compatible APIs for bucket and object operations.

The VMware Cloud Director Object Storage Extension API support AWS Signature v4, VMware Cloud Director authorization token, and JSON Web Token (JWT) authentication methods.

The VMware Cloud Director Object Storage Extension API support JSON and XML formats.

By default, the S3 APIs of VMware Cloud Director Object Storage Extension are available at <https://object-storage-extension-host-address/api/v1/s3>. Depending on the network configuration of your service provider, the address of VMware Cloud Director Object Storage Extension and the root path for the S3 API might be different from the default configuration.

The VMware Cloud Director Object Storage Extension S3 API documentation is available with the product at <https://object-storage-extension-host-address/docs> and in the VMware API Explorer at <https://code.vmware.com/apis>, under the VMware Cloud Director Object Storage Extension product category.

## Using Security Credentials and VMware Cloud Director Object Storage Extension API

To see how you work with security credentials and VMware Cloud Director Object Storage Extension API, use the following example.

- 1 Create a user credential by using the VMware Cloud Director Object Storage Extension tenant portal.

By default, newly created user credentials are activated during creation.

- 2 Copy the access and secret keys.
- 3 Note the name of a bucket as it is displayed in the VMware Cloud Director Object Storage Extension tenant portal.
- 4 In your API client, use the AWS Signature authentication method to authenticate your API request by entering the API endpoint and the access and security keys.

For example, enter the following connection information:

API Endpoint	<code>https://Cloud-Director-Object-Storage-Extension-IP-Andreas:443/api/v1/s3</code>
Access key	<code>5a5af54cf34a172a511f</code>
Secret key	<code>omSG+UXSoyD1fbdFt0iia3I8I+f0QLSiIn5wpq1L</code>

- 5 To list all buckets owned by the owner of the user credential, run an S3 API **GET** request .

For example:

```
GET /api/v1/s3/ HTTP/1.1
Host: vCloud-Director-Object-Storage-Extension-IP-address:443
Accept: application/xml
X-Amz-Content-Sha256: e3b0c44298fc1c149afb4c8996fb92427ae41e4649b934ca495991b7852b855
X-Amz-Date: 20190717T014259Z
Authorization: AWS4-HMAC-SHA256 Credential=5a5af54cf34a172a511f/20190717/us-east-1/s3/aws4_request, SignedHeaders=accept;host;x-amz-content-sha256;x-amz-date, Signature=ala0cfdc34fd4275f567ef673f14d8ff963242d29c13515506a3a913e7f38415
cache-control: no-cache
```

The system returns the following XML representation of the contents of the bucket:

```
<listBucketResult>
  <Name>bucket-name</Name>
  <KeyCount>1</KeyCount>
  <MaxKeys>1000</MaxKeys>
  <Contents>
    <Key>object-name</Key>
    <Owner>
      <ID>system-id-of-the-user</ID>
      <DisplayName>display-name-of-the-user</DisplayName>
    </Owner>
    <StorageClass>Storage-Class</StorageClass>
    <Size>object-size-in-KB</Size>
    <LastModified>last-modified-date</LastModified>
  </Contents>
  <IsTruncated>true-or-false</IsTruncated>
  <ContinuationToken>1-or-0</ContinuationToken>
</listBucketResult>
```

To obtain a user or an application credential, see [Chapter 7 Working with Security Credentials](#).