

Setting Up Published Desktops and Applications in Horizon Console

DEC 2019

VMware Horizon 7 7.11



vmware®

You can find the most up-to-date technical documentation on the VMware website at:

<https://docs.vmware.com/>

If you have comments about this documentation, submit your feedback to

docfeedback@vmware.com

VMware, Inc.
3401 Hillview Ave.
Palo Alto, CA 94304
www.vmware.com

Copyright © 2018-2019 VMware, Inc. All rights reserved. [Copyright and trademark information.](#)

Contents

1	Setting Up Published Desktops and Applications in Horizon Console	6
2	Introduction to Published Desktops and Applications	7
	Farms, RDS Hosts, and Published Desktops and Applications	7
	Advantages of Published Desktop Pools	8
	Advantages of Application Pools	8
3	Setting Up Remote Desktop Services Hosts	10
	Remote Desktop Services Hosts	10
	Prepare Windows Server Operating Systems for Remote Desktop Services (RDS) Host Use	12
	Install Remote Desktop Services on Windows Server 2008 R2	14
	Install Remote Desktop Services on Windows Server 2012, 2012 R2, 2016, or 2019	15
	Install Desktop Experience on Windows Server 2008 R2	16
	Install Desktop Experience on Windows Server 2012, 2012 R2, 2016, or 2019	16
	Restrict Users to a Single Session	17
	Install Horizon Agent on a Remote Desktop Services Host	18
	Horizon Agent Custom Setup Options for an RDS Host	19
	Silent Installation Properties for Horizon Agent	21
	Printing From a Remote Application Launched Inside a Nested Session	26
	Enable Time Zone Redirection for Published Desktop and Application Sessions	26
	Enable Windows Basic Theme for Applications	27
	Configure Group Policy to Start Runonce.exe	27
	RDS Host Performance Options	28
	Configuring 3D Graphics for RDS Hosts	28
	Understanding RDS Per-Device Client Access Licensing in Horizon 7	30
4	Creating Farms in Horizon Console	32
	Preparing a Parent Virtual Machine for an Automated Farm	33
	Prepare an RDS Host Parent Virtual Machine	33
	Activating Windows on Linked-Clone RDS Hosts	35
	Disable Windows Hibernation in the Parent Virtual Machine	36
	Worksheet for Creating a Manual Farm in Horizon Console	36
	Create a Manual Farm in Horizon Console	37
	Worksheet for Creating an Automated Instant-Clone Farm in Horizon Console	38
	Create an Automated Instant-Clone Farm in Horizon Console	44
	Worksheet for Creating an Automated Linked-Clone Farm in Horizon Console	44
	Create an Automated Linked-Clone Farm in Horizon Console	50

5 Creating Published Desktop Pools in Horizon Console 51

- [Understanding Published Desktop Pools 51](#)
- [Published Desktop Pools Settings 52](#)
- [Create a Published Desktop Pool in Horizon Console 53](#)
- [Troubleshooting Instant Clones in the Internal VM Debug Mode 54](#)

6 Creating Application Pools in Horizon Console 56

- [Worksheet for Creating an Application Pool Manually in Horizon Console 56](#)
- [Create an Application Pool in Horizon Console 60](#)

7 Managing Application Pools, Farms, and RDS Hosts 62

- [Managing Application Pools in Horizon Console 62](#)
 - [Edit an Application Pool in Horizon Console 62](#)
 - [Delete an Application Pool in Horizon Console 63](#)
 - [Duplicate an Application Pool in Horizon Console 63](#)
 - [Change the Icon of a Published Application 63](#)
 - [Remove the Icon of a Published Application 64](#)
- [Managing Farms in Horizon Console 64](#)
 - [Edit a Farm in Horizon Console 64](#)
 - [Delete a Farm in Horizon Console 65](#)
 - [Disable or Enable a Farm in Horizon Console 65](#)
 - [Schedule Maintenance for an Automated Instant-Clone Farm in Horizon Console 65](#)
- [Managing RDS Hosts in Horizon Console 68](#)
 - [Edit an RDS Host in Horizon Console 68](#)
 - [Add an RDS Host to a Manual Farm in Horizon Console 68](#)
 - [Remove an RDS Host from a Farm in Horizon Console 69](#)
 - [Remove an RDS Host from Horizon 7 69](#)
 - [Disable or Enable an RDS Host in Horizon Console 70](#)
 - [Monitor RDS Hosts in Horizon Console 70](#)
 - [Status of RDS Hosts in Horizon Console 71](#)
- [Manage Published Desktop and Application Sessions in Horizon Console 72](#)
- [Configuring Load Balancing for RDS Hosts in Horizon Console 73](#)
 - [Configure Load Balancing Settings on an RDS Host in Horizon Console 74](#)
 - [Load Balancing Settings 74](#)
 - [Writing a Load Balancing Script for an RDS Host 75](#)
 - [Enable the VMware Horizon View Script Host Service on an RDS Host 77](#)
 - [Configure a Load Balancing Script on an RDS Host 77](#)
 - [Verify a Load Balancing Script 78](#)
- [Configure an Anti-Affinity Rule for an Application Pool in Horizon Console 79](#)
 - [Anti-Affinity Feature Constraints 80](#)

8 Entitling Users and Groups in Horizon Console 81

[Add Entitlements to a Desktop or Application Pool in Horizon Console 81](#)

[Remove Entitlements from a Desktop or Application Pool in Horizon Console 82](#)

[Review Desktop or Application Pool Entitlements 82](#)

[Configuring Shortcuts for Entitled Pools 83](#)

[Create Shortcuts for a Desktop Pool in Horizon Console 84](#)

[Create Shortcuts for an Application Pool in Horizon Console 85](#)

[Implementing Client Restrictions for Desktop and Application Pools 86](#)

Setting Up Published Desktops and Applications in Horizon Console

1

Setting Up Published Desktops and Applications in Horizon Console describes how to create, and deploy pools of desktops and applications that run on Microsoft Remote Desktop Services (RDS) hosts. It includes information about configuring policies, entitling users and groups, and configuring remote application features.

Intended Audience

This information is intended for anyone who wants to create and provision desktop and application pools. The information is written for Windows system administrators who are familiar with virtual machine technology and data center operations.

Introduction to Published Desktops and Applications

2

With Horizon 7, you can create published desktops associated with a farm, which is a group of Windows Remote Desktop Services (RDS) hosts. You can also deliver a published application to many users by creating application pools. The published applications in application pools run on a farm of RDS hosts.

This chapter includes the following topics:

- [Farms, RDS Hosts, and Published Desktops and Applications](#)
- [Advantages of Published Desktop Pools](#)
- [Advantages of Application Pools](#)

Farms, RDS Hosts, and Published Desktops and Applications

You can use Microsoft Remote Desktop Services (RDS) to provide users with desktop sessions on RDS hosts and deliver applications to many users.

RDS Host

RDS hosts are server computers that have Windows Remote Desktop Services and Horizon Agent installed. These servers host applications that users can access remotely. To access RDS applications, Horizon Client 3.0 or later is required.

Farms

Farms are collections of RDS hosts and facilitate the management of those hosts. Farms can have a variable number of RDS hosts and provide a common set of published applications or RDS published desktops to users. When you create an RDS application pool, you must specify a farm. The RDS hosts in the farm provide application sessions to users. A farm can contain up to 500 RDS host servers.

Published Desktops

Published desktops are desktop pools, which provide users with desktop sessions on RDS hosts. Multiple users can have desktop sessions on an RDS host simultaneously.

Published Applications

Published applications are application pools that run on a farm of RDS hosts. Published applications let you deliver seamless applications to many users.

Advantages of Published Desktop Pools

Horizon 7 offers the ability to create published desktop pools as its basis of centralized management.

You can create a published desktop pool from a physical system such as an RDS host. Use published desktop pools to provide multiple users with desktop sessions on an RDS host.

Advantages of Application Pools

With application pools, you give users access to applications that run on servers in a data center instead of on their personal computers or devices.

Application pools offer several important benefits:

- Accessibility

Users can access applications from anywhere on the network. You can also configure secure network access.

- Device independence

With application pools, you can support a range of client devices, such as smart phones, tablets, laptops, thin clients, and personal computers. The client devices can run various operating systems, such as Windows, iOS, Mac OS, or Android.

- Access control

You can easily and quickly grant or remove access to applications for one user or a group of users.

- Accelerated deployment

With application pools, deploying applications can be accelerated because you only deploy applications on servers in a data center and each server can support multiple users.

- Manageability

Managing software that is deployed on client computers and devices typically requires significant resources. Management tasks include deployment, configuration, maintenance, support, and upgrades. With application pools, you can simplify software management in an enterprise because the software runs on servers in a data center, which requires fewer installed copies.

- Security and regulatory compliance

With application pools, you can improve security because applications and their associated data are centrally located in a data center. Centralized data can address security concerns and regulatory compliance issues.

- Reduced cost

Depending on software license agreements, hosting applications in a data center can be more cost-effective. Other factors, including accelerated deployment and improved manageability, can also reduce the cost of software in an enterprise.

Setting Up Remote Desktop Services Hosts

3

Microsoft Remote Desktop Services (RDS) hosts provide desktop sessions and applications that users can access from client devices. If you plan to create published desktop pools or application pools, you must first set up RDS hosts.

This chapter includes the following topics:

- [Remote Desktop Services Hosts](#)
- [Prepare Windows Server Operating Systems for Remote Desktop Services \(RDS\) Host Use](#)
- [Install Remote Desktop Services on Windows Server 2008 R2](#)
- [Install Remote Desktop Services on Windows Server 2012, 2012 R2, 2016, or 2019](#)
- [Install Desktop Experience on Windows Server 2008 R2](#)
- [Install Desktop Experience on Windows Server 2012, 2012 R2, 2016, or 2019](#)
- [Restrict Users to a Single Session](#)
- [Install Horizon Agent on a Remote Desktop Services Host](#)

Remote Desktop Services Hosts

An RDS host is a server computer that hosts applications and desktop sessions for remote access. An RDS host can be a virtual machine or a physical server.

An RDS host has the Microsoft Remote Desktop Services role, the Microsoft Remote Desktop Session Host service, and Horizon Agent installed. Remote Desktop Services was previously known as Terminal Services. The Remote Desktop Session Host service allows a server to host applications and remote desktop sessions. With Horizon Agent installed on an RDS host, users can connect to applications and desktop sessions by using the display protocol PCoIP or Blast Extreme. Both protocols provide an optimized user experience for the delivery of remote content, including images, audio and video.

The performance of an RDS host depends on many factors. For information on how to tune the performance of different versions of Windows Server, see <http://msdn.microsoft.com/library/windows/hardware/gg463392.aspx>.

Horizon 7 supports at most one desktop session and one application session per user on an RDS host.

Horizon 7 supports both local printer redirection and native network printers.

Local printer redirection is designed for the following use cases:

- Printers directly connected to USB or serial ports on the client device
- Specialized printers such as bar code printers and label printers connected to the client
- Network printers on a remote network that are not addressable from the virtual session

Network printers are managed using corporate print servers, which allows for greater management and control of printer resources. Native printer drivers for all possible printers need to be installed on the virtual machine or RDSH host. If you consider this challenging, there are third-party options such as advanced versions of ThinPrint that can provide network printing without the need to install additional printer drivers on each virtual machine or RDSH host. The Print and Document Services option included with Microsoft Windows Server is another option for managing your network printers.

When users submit print jobs concurrently from published desktops or applications that are hosted on the same RDS host, the ThinPrint server on the RDS host processes the print requests serially rather than in parallel. This can cause a delay for some users.

If a user launches an application and also a published desktop, and both are hosted on the same RDS host, they share the same user profile. If the user launches an application from the desktop, conflicts may result if both applications try to access or modify the same parts of the user profile, and one of the applications may fail to run properly.

The process of setting up published applications or desktops for remote access involves the following tasks:

- 1 Set up RDS hosts.
- 2 Create a farm. See [Chapter 4 Creating Farms in Horizon Console](#).
- 3 Create a published application pool or a published desktop pool. See [Chapter 6 Creating Application Pools in Horizon Console](#) or [Chapter 5 Creating Published Desktop Pools in Horizon Console](#).
- 4 Entitle users and groups. See [Chapter 8 Entitling Users and Groups in Horizon Console](#).
- 5 (Optional) Enable time zone redirection for published desktop and application sessions. See [Enable Time Zone Redirection for Published Desktop and Application Sessions](#).

Note If smart card authentication is enabled, make sure that the Smart Card service is disabled on RDS hosts. Otherwise, authentication might fail. By default, this service is disabled.

Caution When a user launches an application, for example, a Web browser, it is possible for a user to gain access to the local drives on the RDS host that is hosting the application. This can happen if the application provides functions that cause Windows Explorer to run. Do not create published desktop pools and application pools on the same farm so that desktop sessions are not affected.

Installing Applications

If you plan to create application pools, you must install the applications on the RDS hosts. If you want Horizon 7 to automatically display the list of installed applications, you must install the applications so that they are available to all users from the **Start** menu. You can install an application at any time before you create the application pool. If you plan to manually specify an application, you can install the application at any time, either before or after creating an application pool.

Important When you install an application, you must install it on all the RDS hosts in a farm and in the same location on each RDS host. If you do not, a health warning will appear on the Horizon Console dashboard. In such a situation, if you create an application pool, users might encounter an error when they try to run the application.

Horizon 7 supports Universal Windows Platform (UWP) applications that run on Windows 10 virtual desktop (WVD) hosts on Horizon Cloud Service on Azure or a desktop pool. You can set a policy to enable or disable these applications in the Unity Touch and Hosted Apps folder in the Group Policy Management Editor. When the policy is disabled, the application status shows as unavailable in Horizon Agent and a user cannot access the application. To configure the policy, see the *Configuring Remote Desktop Features in Horizon 7* document.

When you create an application pool, Horizon 7 automatically displays the applications that are available to all users rather than individual users from the **Start** menu on all of the RDS hosts in a farm. You can choose any applications from that list. In addition, you can manually specify an application that is not available to all users from the **Start** menu. There is no limit on the number of applications that you can install on an RDS host.

Prepare Windows Server Operating Systems for Remote Desktop Services (RDS) Host Use

To use a Windows Server 2008 R2, Windows Server 2012, Windows Server 2012 R2, Windows Server 2016, or Windows Server 2019 virtual machine as an RDS host, you must perform certain steps before you install Horizon Agent in the virtual machine.

When the Remote Desktop Session Host (RDSH) role is not present, the Horizon Agent installer prompts you to install Horizon Agent in RDS mode or desktop mode. If RDS mode is selected, the installer will install the RDSH role as well as the Desktop Experience role for the supported operating systems (Windows Server 2008 R2 to Windows Server 2012 R2) and the RDSH role for Windows Server 2016 and later, and prompt you to reboot the system. At this time the installer has not yet installed Horizon Agent. After rebooting the system you must run the installer again to continue installing Horizon Agent in RDS mode.

When the Remote Desktop Session Host role is present, the Horizon Agent installer does not display these options. The installer treats the Windows Server machine as an RDS host instead of a single-session Horizon 7 desktop and installs Horizon Agent in RDS mode. During this installation, the Horizon Agent installer will not automatically install the Desktop Experience role. If you need the Desktop Experience role, you must install the role manually. See [Install Desktop Experience on Windows Server 2008 R2](#) or [Install Desktop Experience on Windows Server 2012, 2012 R2, 2016, or 2019](#).

Note The Desktop Experience Role is required for the following features:

- HTML Access
- Scanner redirection
- Windows Aero

For Windows Server 2008 R2, 2012, and 2012 R2, if the Horizon Agent installer does not find an RDSH role and you select RDS mode, then the Horizon Agent installer will automatically install the Desktop Experience role with the RDSH role. You do not have to explicitly install the Desktop Experience role. Windows Server 2016 and later do not have a separate installable Desktop Experience role. The Desktop Experience option is available only during the OS installation, so the Horizon Agent installer installs the RDSH role on Windows Server 2016 and later.

Prerequisites

- Verify that the RDS host is part of the Active Directory domain for the Horizon 7 deployment.
- Familiarize yourself with the steps to install the Desktop Experience feature on supported Windows Server operating systems. See [Install Remote Desktop Services on Windows Server 2008 R2](#) or [Install Remote Desktop Services on Windows Server 2012, 2012 R2, 2016, or 2019](#).
- On Windows Server 2012 or Windows Server 2016 machines, familiarize yourself with the steps to configure the Windows Firewall service to restart after failures occur. See *Configure the Windows Firewall Service to Restart After Failures* in the *Setting Up Virtual Desktops in Horizon Console* document.
- If the machine has the Microsoft Visual C++ Redistributable package installed, verify that the version of the package is 2005 SP1 or later. If the package version is 2005 or earlier, you can either upgrade or uninstall the package.
- Download the Horizon Agent installer file from the VMware product page at <http://www.vmware.com/go/downloadview>.

Procedure

- 1 Log in as an administrator.
- 2 To start the Horizon Agent installation program, double-click the installer file.

The installer filename is VMware-Horizon-Agent-x86-y.y.y-xxxxxx.exe, where y.y.y is the version number and xxxxxx is the build number.

- 3 Accept the VMware license terms.

- 4 Select **RDS mode** to install the RDSH role and/or the Desktop Experience role. After it is installed, the installer will prompt you to restart the system. After the system is restarted, launch the installer again to continue installing Horizon Agent in RDS mode.
- 5 Install Windows Server 2008 R2 Service Pack 1 (SP1).

If you do not install SP1 with Windows Server 2008 R2, an error occurs when you install Horizon Agent.
- 6 On Windows Server 2012 R2 or Windows Server 2016 machines, configure the Windows Firewall service to restart after failures occur.

What to do next

Install Horizon Agent on the remote desktop services host. See [Install Horizon Agent on a Remote Desktop Services Host](#).

Install Remote Desktop Services on Windows Server 2008 R2

Remote Desktop Services (RDS) is one of the roles that a Windows Server can have. You must install this role to set up an RDS host that runs Windows Server 2008 R2.

To use a Windows Server virtual machine as an RDS host, see [Prepare Windows Server Operating Systems for Remote Desktop Services \(RDS\) Host Use](#).

Prerequisites

- Verify that the RDS host is running Windows Server 2008 R2 Service Pack 1 (SP1).
- Verify that the RDS host is part of the Active Directory domain for the Horizon 7 deployment.
- Install the Microsoft hotfix rollup that is documented in <http://support.microsoft.com/kb/2775511>.
- Install the Microsoft update <https://support.microsoft.com/en-us/kb/2973201>.

Procedure

- 1 Log in to the RDS host as an administrator.
- 2 Start Server Manager.
- 3 Select **Roles** in the navigation tree.
- 4 Click **Add Roles** to start the **Add Role** wizard.
- 5 Select the role **Remote Desktop Services**.
- 6 On the Select Role Services page, select **Remote Desktop Session Host**.
- 7 On the Specify Authentication Method page, select either **Require Network Level Authentication** or **Do not require Network Level Authentication**, whichever is appropriate.
- 8 On the Configure Client Experience page, select the functionality that you want to provide to users.

- 9 Follow the prompts and finish the installation.

What to do next

If you plan to use HTML Access or scanner redirection, install the Desktop Experience feature. The steps for installing Desktop Experience differ on Windows Server 2008 R2 and Windows Server 2012 or 2012 R2.

Restrict users to a single desktop session. See [Restrict Users to a Single Session](#).

Install Remote Desktop Services on Windows Server 2012, 2012 R2, 2016, or 2019

Remote Desktop Services is one of the roles that a Windows Server 2012, 2012 R2, 2016, or 2019 can have. You must install this role to set up an RDS host.

To use a Windows Server virtual machine as an RDS host, see [Prepare Windows Server Operating Systems for Remote Desktop Services \(RDS\) Host Use](#).

Prerequisites

- Verify that the RDS host is running Windows Server 2012 or Windows Server 2012 R2 or Windows Server 2016 or Windows Server 2019.
- Verify that the RDS host is part of the Active Directory domain for the Horizon 7 deployment.

Procedure

- 1 Log in to the RDS host as an administrator.
- 2 Start Server Manager.
- 3 Select **Add roles and features**.
- 4 On the Select Installation Type page, select **Role-based or feature-based installation**.
- 5 On the Select Destination Server page, select a server.
- 6 On the Select Server Roles page, select **Remote Desktop Services**.
- 7 On the Select Features page, accept the defaults.
- 8 On the Remote Desktop Services, Role Services page, select the **Remote Desktop Session Host** role and accept the prompts to add in the additional features required to support the Desktop Session Host role.
- 9 Follow the prompts to finish the installation.
- 10 Restart the Windows server.

What to do next

If you plan to use HTML Access or scanner redirection, install the Desktop Experience feature. The steps for installing Desktop Experience differ on Windows Server 2008 R2, Windows Server 2012, Windows Server 2012 R2, Windows Server 2016, and Windows Server 2019.

Restrict users to a single desktop session. See [Restrict Users to a Single Session](#).

Install Desktop Experience on Windows Server 2008 R2

For published desktops and applications, and for virtual desktops that are deployed on single-user virtual machines that run Windows Server, scanner redirection requires that you install the Desktop Experience feature on the RDS hosts and the single-user virtual machines.

To use a Windows Server virtual machine as an RDS host, see [#unique_20](#).

Procedure

- 1 Log in as an administrator.
- 2 Start Server Manager.
- 3 Click **Features**.
- 4 Click **Add Features**.
- 5 On the Select Features page, select the **Desktop Experience** checkbox.
- 6 Review the information about other features that are required by the Desktop Experience feature, and click **Add Required Features**.
- 7 Follow the prompts and finish the installation.

Install Desktop Experience on Windows Server 2012, 2012 R2, 2016, or 2019

For published desktops and applications, and for virtual desktops that are deployed on single-user virtual machines that run Windows Server, scanner redirection requires that you install the Desktop Experience feature on the RDS hosts and the single-user virtual machines.

Windows Server 2012, Windows Server 2012 R2, Windows Server 2016, and Windows Server 2019 are supported on machines that are used as RDS hosts. Windows Server 2012 R2, Windows Server 2016, and Windows Server 2019 is supported on single-user virtual machines.

Note A Windows Server 2016 and Windows Server 2019 installation with the Desktop Experience option, installs the standard user interface and all tools, including the client experience and the desktop experience features. For Windows Server 2012 RS, the client experience and desktop experience features require a separate installation. For Windows Server 2016 or Windows Server 2019 installation, select **Windows Server 2016** or **Windows Server 2019** or **Windows Server (Server with Desktop Experience)**. If you do not make a choice in the Setup wizard, Windows Server 2016 or Windows Server 2019 is installed as the Server Core installation option. You cannot switch between the installation options. If you install **Windows Server (Server with Desktop Experience)**, and later decide to use **Windows Server 2016** or **Windows Server 2019**, you must perform a fresh installation of Windows Server 2016 or Windows Server 2019.

Procedure

- 1 Log in as an administrator.
- 2 Start Server Manager.
- 3 Select **Add roles and features**.
- 4 On the Select Installation Type page, select **Role-based or feature-based installation**.
- 5 On the Select Destination Server page, select a server.
- 6 On the Select Server Roles page, accept the default selection and click **Next**.
- 7 On the Select Features page, under **User Interfaces and Infrastructure**, select **Desktop Experience**.
- 8 Follow the prompts and finish the installation.

Restrict Users to a Single Session

Horizon 7 supports at most one desktop session and one application session per user on an RDS host. You must configure the RDS host to restrict users to a single session. For Windows Server 2008 R2, Windows Server 2012, and Windows Server 2012 R2, you can restrict users to a single session by enabling the group policy setting

Restrict Remote Desktop Services users to a single Remote Desktop Services session. This setting is located in the folder Computer Configuration\Administrative Templates\Windows Components\Remote Desktop Services\Remote Desktop Session Host\Connections. For Windows Server 2008 R2, you can also use the following procedure to restrict users to a single session. This does not apply to Windows Server 2016.

Prerequisites

- Install the Remote Desktop Services role as described in [Install Remote Desktop Services on Windows Server 2008 R2](#).

Procedure

- 1 Click **Start > Administrative Tools > Remote Desktop Services > Remote Desktop Session Host Configuration**.
- 2 On the Edit Settings pane, under General, double-click **Restrict each user to a single session**.
- 3 In the Properties dialog box, on the General tab, select **Restrict each user to a single session** and click **OK**.

What to do next

Install Horizon Agent on the RDS host. See [Install Horizon Agent on a Remote Desktop Services Host](#).

Install Horizon Agent on a Remote Desktop Services Host

Horizon Agent communicates with Connection Server and supports the display protocols PCoIP and Blast Extreme. You must install Horizon Agent on an RDS Host.

Prerequisites

- Verify that you have prepared Active Directory. See the *Horizon 7 Installation* document.
- To use a Windows Server virtual machine as an RDS host, see [Prepare Windows Server Operating Systems for Remote Desktop Services \(RDS\) Host Use](#).
- Install the Remote Desktop Services role as described in [Install Remote Desktop Services on Windows Server 2008 R2](#) or [Install Remote Desktop Services on Windows Server 2012, 2012 R2, 2016, or 2019](#).
- Restrict users to a single desktop session. See [Restrict Users to a Single Session](#).
- Familiarize yourself with the Horizon Agent custom setup options. See [Horizon Agent Custom Setup Options for an RDS Host](#).
- If the machine has the Microsoft Visual C++ Redistributable package installed, verify that the version of the package is 2005 SP1 or later. If the package version is 2005 or earlier, you can either upgrade or uninstall the package.
- Download the Horizon Agent installer file from the VMware product page at <http://www.vmware.com/go/downloadview>.

Procedure

- 1 Log in as an administrator.

- 2 To start the Horizon Agent installation program, double-click the installer file.

The installer filename is VMware-Horizon-Agent-x86-y.y.y-xxxxxx.exe, where y.y.y is the version number and xxxxxx is the build number.

- 3 Select the Internet Protocol (IP) version, **IPv4** or **IPv6**.

You must install all Horizon 7 components with the same IP version.

- 4 Select your custom setup options.

Do not select the View Composer Agent option if you are installing Horizon Agent on an RDS host that will be in a manual farm.

- 5 In the **Server** text box, type the host name or IP address of a Connection Server host.

Horizon Agent installer prompts this step only if you are installing Horizon Agent on an RDS host that will be in a manual farm. During installation, the installer registers the RDS host with this Connection Server instance. After registration, the specified Connection Server instance and any additional instances in the same Connection Server group can communicate with the RDS host.

- 6 Select an authentication method to register the RDS host with the Connection Server instance.

Option	Description
Authenticate as the currently logged in user	The Username and Password text boxes are disabled and you are logged in to the Connection Server instance with your current username and password.
Specify administrator credentials	You must provide the username and password of a Connection Server administrator in the Username and Password text boxes.

The user account must be a domain user with access to View LDAP on the Connection Server instance. A local user does not work.

- 7 Follow the prompts and finish the installation.

What to do next

Create a farm. See [Chapter 4 Creating Farms in Horizon Console](#).

Horizon Agent Custom Setup Options for an RDS Host

When you install Horizon Agent on an RDS host, you can select custom setup options. In addition, Horizon Agent installs certain features automatically on all guest operating systems on which they are supported. These features are not optional.

To change custom setup options after you install the latest Horizon Agent version, you must uninstall and reinstall Horizon Agent. For patches and upgrades, you can run the new Horizon Agent installer and select a new set of options without uninstalling the previous version.

Table 3-1. Horizon Agent Custom Setup Options for an RDS Host in an IPv4 Environment

Option	Description
USB Redirection	<p>Gives users access to locally connected USB storage devices.</p> <p>Specifically, redirection of USB flash drives and hard disks is supported in published desktops and published applications. Redirection of other types of USB devices, and other types of USB storage devices such as security storage drives and USB CD-ROM, is not supported in published desktops and published applications.</p> <p>This setup option is not selected by default. You must select the option to install it. This option is available on RDS hosts that run Windows Server 2012 or 2012 R2 but not Windows Server 2008 R2.</p> <p>For information about using USB redirection securely, see the <i>Horizon 7 Security</i> document. For example, you can use group policy settings to disable USB redirection for specific users.</p>
HTML Access	<p>Enables users to connect to published desktops and published applications by using HTML Access. The HTML Access Agent is installed when this setup option is selected. This agent must be installed on RDS hosts to enable users to make connections with HTML Access</p>
3D RDSH	<p>Provides 3D graphics support to applications that run on this RDS host.</p>
View Composer Agent	<p>Select this option if this machine is a parent virtual machine for the creation of an automated farm. Do not select this option if this machine is an RDS host in a manual farm.</p>
Client Drive Redirection	<p>Enables Horizon Client users to share local drives with their published desktops and published applications.</p> <p>After this setup option is installed, no further configuration is required on the RDS host.</p> <p>Client drive redirection is also supported on remote desktops that run on single-user virtual machines and on unmanaged machines.</p>

Table 3-1. Horizon Agent Custom Setup Options for an RDS Host in an IPv4 Environment (continued)

Option	Description
Virtual Printing	<p>Enables users to print to any printer available on their client computers. Users do not need to install additional drivers on their desktops.</p> <p>Virtual printing is supported on the following remote desktops and applications:</p> <ul style="list-style-type: none"> ■ Desktops that are deployed on single-user machines, including Windows desktop and Windows server machines ■ Published desktops and published applications that are deployed on RDS hosts, where the RDS hosts are virtual machines or physical machines ■ Published applications that are launched from Horizon Client inside remote desktops (nested sessions) <p>The virtual printing feature is supported only when you install it from Horizon Agent. If you install it with VMware Tools, it is not supported.</p> <p>If you select this option, you cannot select VMware Integrated Printing.</p>
Help Desk Plugin for Horizon Agent	You must have a Horizon Enterprise edition license or Horizon Apps Advanced edition license for Horizon 7 to use the Help Desk Tool. This option is installed and enabled by default.
vRealize Operations Desktop Agent	Enables vRealize Operations Manager to work with vRealize Operations Manager for Horizon.
Scanner Redirection	<p>Redirects scanning devices that are connected to the client system so that they can be used on the published desktop or published application.</p> <p>You must install the Desktop Experience feature in the Windows Server operating system on the RDS hosts to make this option available in the Horizon Agent installer.</p> <p>This setup option is not installed by default on Windows Server guest operating systems. You must select the option to install it.</p>
Serial Port Redirection	<p>Redirects serial COM ports that are connected to the client system so that they can be used on the published desktop or published application.</p> <p>This option is not selected by default. You must select the option to install it.</p>
VMware Client IP Transparency	<p>Enables remote connections to Internet Explorer to use the client's IP address instead of the remote desktop machine's IP address.</p> <p>This setup option is not selected by default. You must select the option to install it.</p>
Instant Clone	<p>Enables the creation of instant-clone virtual machines on a farm of RDS hosts.</p> <p>This setup option is not installed by default on Windows Server guest operating systems. You must select the option to install it.</p>
Horizon Performance Tracker	Monitors the performance of the display protocol and system resource usage. This option is not selected by default. You must select the option to install it. .NET Framework 4.0 or later is required if you install Horizon Performance Tracker.
VMware Integrated Printing	<p>Enables users to print to any printer available on their client machines. Location-based printing is supported.</p> <p>VMware Integrated Printing is supported on the following remote desktops and applications:</p> <ul style="list-style-type: none"> ■ Desktops that are deployed on single-user machines, including Windows desktop and Windows server machines ■ Published desktops and published applications that are deployed on RDS hosts, where the RDS hosts are virtual machines or physical machines <p>This option is not selected by default. You must select the option to install it. If you select this option, you cannot select Virtual Printing.</p>

Table 3-1. Horizon Agent Custom Setup Options for an RDS Host in an IPv4 Environment (continued)

Option	Description
Hybrid Logon	Provides unauthenticated access users access to network resources without the need to enter credentials. This setup option is not installed by default. You must select the option to install it.
Geolocation Redirection	Enables the Geolocation Redirection feature. This option is not selected by default. You must select the option to install it.

In an IPv6 environment, the setup options are similar to IPv6.

Table 3-2. Horizon Agent Features That Are Installed Automatically on an RDS Host

Feature	Description
PCoIP Agent	Enables users to use the PCoIP display protocol to connect to applications and published desktops.
Windows Media Multimedia Redirection (MMR)	Provides multimedia redirection for published desktops. This feature delivers a multimedia stream directly to the client computer, which enables the multimedia stream to be processed on the client hardware instead of on the remote ESXi host.
Unity Touch	Enables tablet and smart phone users to interact with Windows applications that run on the remote desktop. Users can browse, search, and open Windows applications and files, choose favorite applications and files, and switch between running applications without using the Start menu or Taskbar.
PSG Agent	Installs the PCoIP Secure Gateway on RDS hosts to implement the PCoIP display protocol for desktop and application sessions that run on RDS hosts.
VMwareRDS	Provides the VMware implementation of Remote Desktop Services functionality.
HTML5 Multimedia Redirection	Redirects HTML5 multimedia content in a Chrome or Edge browser to the client for performance optimization.
Browser Redirection	Renders a website on the client system instead of the agent system, and displays the website over the remote browser's viewport, when a user uses the Chrome browser in a remote desktop.

In an IPv6 environment, the automatically installed features are PCoIP Agent, PSG Agent, and VMwareRDS.

For additional features that are supported on RDS hosts, see "Feature Support Matrix for Horizon Agent" in the *Horizon 7 Architecture Planning* document.

Silent Installation Properties for Horizon Agent

You can include specific properties when you silently install Horizon Agent from the command line. You must use a `PROPERTY=value` format so that Microsoft Windows Installer (MSI) can interpret the properties and values. A silent upgrade uses the same install commands.

The following table shows the Horizon Agent silent installation properties that you can use at the command-line.

Table 3-3. MSI Properties for Silently Installing Horizon Agent

MSI Property	Description	Default Value
INSTALLDIR	<p>Path and folder in which the Horizon Agent software is installed.</p> <p>For example:</p> <p>INSTALLDIR=""D:\abc\my folder""</p> <p>The sets of two double quotes that enclose the path permit the MSI installer to ignore the space in the path.</p> <p>This MSI property is optional.</p>	%ProgramFiles%\VMware\VMware View Agent
RDP_CHOICE	<p>Determines whether to enable Remote Desktop Protocol (RDP) on the desktop.</p> <p>A value of 1 enables RDP. A value of 0 leaves the RDP setting disabled.</p> <p>This MSI property is optional.</p>	1
SUPPRESS_RUNONCE_CHECK	<p>Ignores pending Windows Update tasks scheduled at the next operating system reboot in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\RunOnce and RunOnceEx keys. Using this flag allows concurrent installation but does not guarantee the installation outcome when the system updates affect the Horizon Agent run-time dependencies.</p> <p>This MSI property is optional.</p>	None
URL_FILTERING_ENABLED	<p>Specifies whether the URL Content Redirection feature is installed.</p> <p>A value of 1 installs the feature. You must use group policy settings to configure which URLs to redirect. See "Configuring URL Content Redirection in the <i>Configuring Remote Desktop Features in Horizon 7</i> document.</p> <p>This MSI property is optional.</p>	0
VDM_SKIP_BROKER_REGISTRATION	<p>A value of 1 skips unmanaged desktops.</p>	None
VDM_VC_MANAGED_AGENT	<p>Determines whether vCenter Server manages the virtual machine on which Horizon Agent is installed.</p> <p>A value of 1 configures the desktop as a vCenter Server-managed virtual machine.</p> <p>A value of 0 configures the desktop as unmanaged by vCenter Server.</p> <p>This MSI property is required.</p> <p>Note The installer repair option is not supported for an unmanaged installation. Repairing such an installation will result in an installation of a managed Horizon Agent.</p>	None
VDM_SERVER_NAME	<p>Host name or IP address of the Connection Server instance on which the Horizon Agent installer registers an unmanaged desktop. This property applies to unmanaged desktops only. For example:</p> <p>VDM_SERVER_NAME=10.123.01.01</p> <p>This MSI property is required for unmanaged desktops.</p> <p>Do not use this MSI property for virtual desktops that are managed by vCenter Server.</p>	None

Table 3-3. MSI Properties for Silently Installing Horizon Agent (continued)

MSI Property	Description	Default Value
VDM_SERVER_USERNAME	User name of the administrator on the Connection Server instance. This MSI property applies only to unmanaged desktops. For example: VDM_SERVER_USERNAME=domain\username This MSI property is required for unmanaged desktops. Do not use this MSI property for virtual desktops that are managed by vCenter Server.	None
VDM_SERVER_PASSWORD	Connection Server administrator user password. For example: VDM_SERVER_PASSWORD=secret This MSI property is required for unmanaged desktops. Do not use this MSI property for virtual desktops that are managed by vCenter Server.	None
VDM_IP_PROTOCOL_USAGE	Specifies the IP version that Horizon Agent uses. Valid values are IPv4 and IPv6.	IPv4
VDM_FIPS_ENABLED	Specifies whether to enable or disable FIPS mode. A value of 1 enables FIPS mode. A value of 0 disables FIPS mode. If this property is set to 1 and Windows is not in FIPS mode, the installer will abort.	0
VDM_FLASH_URL_REDIRECTION	Determines whether Horizon Agent can install the Flash URL redirection feature. Specify 1 to enable installation or 0 to disable installation. This MSI property is optional.	0
VDM_FORCE_DESKTOP_AGENT	If you install Horizon Agent on a Windows Server machine and configure it as a single-user Horizon 7 desktop rather than as an RDS host, set the value to 1. This requirement applies to machines that are managed by vCenter Server and unmanaged machines. For non-server Windows guests that host application sessions, set the value to 0. This MSI property is optional.	0
INSTALL_VDISPLAY_DRIVER	Configures the Horizon WDDM display driver. A value of 1 enables the driver installation. A value of 0 or empty disables the driver installation.	0

In a silent installation command, you can use the ADDLOCAL property to specify options that the Horizon Agent installer configures.

The following table shows the Horizon Agent options that you can type at the command line. These options have corresponding setup options that you can deselect or select during an interactive installation.

For more information about the custom setup options, see [Horizon Agent Custom Setup Options for an RDS Host](#).

When you do not use the ADDLOCAL property at the command line, Horizon Agent installs all of the options that are installed by default during an interactive installation, if they are supported on the guest operating system. When you use ADDLOCAL=ALL, Horizon Agent installs all of the following options, both on-by-default and off-by-default, if they are supported on the guest operating system, except NGVC. NGVC and SVIAgent are mutually exclusive. To install NGVC, you must specify it explicitly.

For more information, see the ADDLOCAL table entry in "Microsoft Windows Installer Command-Line Options" in *Setting Up Virtual Desktops in Horizon 7*

Table 3-4. Horizon Agent Silent Installation Options and Interactive Custom Setup Options

Silent Installation Option	Custom Setup Option in an Interactive Installation	Installed by Default Interactively or When ADDLOCAL Is Not Used
Core	Core	Yes
USB	USB Redirection	No
SVIAgent	View Composer Agent	Yes
NGVC	Instant Clone Agent	No
RTAV	Real-Time Audio-Video	Yes
ClientDriveRedirection	Client Drive Redirection	Yes
SerialPortRedirection	Serial Port Redirection	No
ScannerRedirection	Scanner Redirection	No
FlashURLRedirection	Flash URL Redirection This feature is hidden unless you use the VDM_FLASH_URL_REDIRECTION=1 property on the command line.	No
GEOREDİR	Geolocation Redirection	No
ThinPrint	Virtual Printing	Yes
V4V	vRealize Operations Desktop Agent	Yes
VPA	View Persona Management	Yes
SmartCard	PCoIP Smartcard This feature is not installed by default in an interactive installation.	No
VmwVaudio	VMware Audio (virtual audio driver)	Yes
VmVideo	VMware Video (virtual video driver)	No
VmwVdisplay		
VmwVidd		
TSMMR	Windows Media Multimedia Redirection (MMR)	Yes
RDP	Enables RDP in the registry if you use the RDP_CHOICE=1 property on the command line or select RDP as the default display protocol when you create or edit a desktop pool. This feature is hidden during interactive installations.	Yes

Table 3-4. Horizon Agent Silent Installation Options and Interactive Custom Setup Options (continued)

Silent Installation Option	Custom Setup Option in an Interactive Installation	Installed by Default Interactively or When ADDLOCAL Is Not Used
VMWMediaProviderProxy	VMware Virtualization Pack for Skype for Business	No
RDSH3D	3D rendering on RDS hosts	No
BlastUDP		
HTML5MMR		
CIT (64 bit only)	Client IP Transparency. Only exists in the 64bit installer. If you try to install the feature through the command line with the 32bit installer, MSI will return an error.	No
SdoSensor	SDO Sensor Redirection	No
PerfTracker	Horizon Performance Tracker	No
HelpDesk	Horizon Help Desk Tool	No
PrintRedir	VMware Integrated Printing	No

If you use ADDLOCAL to specify features individually (you do not specify ADDLOCAL=ALL), you must always specify Core.

Table 3-5. Horizon Agent Silent Installation Features That Are Installed Automatically

Silent Installation Feature	Description
Core	The core Horizon Agent functions. If you specify ADDLOCAL=ALL, the Core features are installed.
BlastProtocol	VMware Blast
PCoIP	PCoIP Protocol Agent
VmVideo	Virtual video driver
UnityTouch	Unity Touch
PSG	This feature sets a registry entry that tells Connection Server whether Horizon Agent is using IPv4 or IPv6.

You install the Flash URL Redirection feature by using the VDM_FLASH_URL_REDIRECTION=1 property in a silent installation. This feature is not installed during an interactive installation or by using ADDLOCAL=ALL in a silent installation. For example:

```
VMware-Horizon-Agent-x86-y.y-y-xxxxxx.exe /s /v"/qn VDM_VC_MANAGED_AGENT=1
VDM_FLASH_URL_REDIRECTION=1
ADDLOCAL=Core,SVIAgent,ThinPrint,USB,FlashURLRedirection,RTAV"
```

Printing From a Remote Application Launched Inside a Nested Session

When you enable the Virtual Printing option during Horizon Agent installation, users can print from remote applications that they launch from Horizon Client inside remote desktops (nested sessions) to printers on their local client machine.

Beginning with Horizon 7 version 7.0.2, users can print from remote applications launched inside a nested session to printers connected to the remote desktop machine rather than to printers connected to their local client machine. To enable this feature, change the Thinprint session-in-session mode on the remote desktop machine by changing the value of `SiSActive` to 0 in `HKEY_LOCAL_MACHINE\SOFTWARE\ThinPrint\TPClnRDP`.

Note When `SiSActive` is set to 0 on the remote desktop machine, users can no longer print from remote applications launched inside nested sessions to printers connected to their local client machine. To reenable the default ThinPrint session-in-session mode, change the value of `SiSActive` to 1 in `HKEY_LOCAL_MACHINE\SOFTWARE\ThinPrint\TPClnRDP` on the remote desktop machine.

For information about enabling the Virtual Printing option during Horizon Agent installation, see [Horizon Agent Custom Setup Options for an RDS Host](#).

Enable Time Zone Redirection for Published Desktop and Application Sessions

If an RDS host is in one time zone and a user is in another time zone, by default, when the user connects to a published desktop, the desktop displays time that is in the time zone of the RDS host. You can enable the Time Zone Redirection group policy setting to make the published desktop display time in the local time zone. This policy setting applies to application sessions as well.

Prerequisites

- Verify that the Group Policy Management feature is available on your Active Directory server.
The steps for opening the Group Policy Management Console differ in the Windows 2012, Windows 2008, and Windows 2003 Active Directory versions. See "Create GPOs for Horizon Group Policies" in the *Configuring Remote Desktop Features in Horizon 7* document.
- Verify that the Horizon 7 RDS ADMX files are added to Active Directory. See "Add the Remote Desktop Services ADMX Files to Active Directory" in the *Configuring Remote Desktop Features in Horizon 7* document.
- Familiarize yourself with the group policy settings. See "RDS Device and Resource Redirection Settings" in the *Configuring Remote Desktop Features in Horizon 7* document.

Procedure

- 1 On the Active Directory server, open the Group Policy Management Console.
- 2 Expand your domain and **Group Policy Objects**.
- 3 Right-click the GPO that you created for the group policy settings and select **Edit**.

- 4 In the Group Policy Management Editor, navigate to **Computer Configuration > Policies > Administrative Templates > Windows Components > Remote Desktop Services > Remote Desktop Session Host > Device and Resource Redirection**.
- 5 Enable the setting **Allow time zone redirection**.

Enable Windows Basic Theme for Applications

If a user has never connected to a desktop on an RDS host, and the user launches an application that is hosted on the RDS host, the Windows basic theme is not applied to the application even if a GPO setting is configured to load the Aero-styled theme. Horizon 7 does not support the Aero-styled theme but supports the Windows basic theme. To make the Windows basic theme apply to the application, you must configure another GPO setting.

Prerequisites

- Verify that the Group Policy Management feature is available on your Active Directory server.
The steps for opening the Group Policy Management Console differ in the Windows 2012, Windows 2008, and Windows 2003 Active Directory versions. See "Create GPOs for Horizon 7 Group Policies" in the *Configuring Remote Desktop Features in Horizon 7* document.

Procedure

- 1 On the Active Directory server, open the Group Policy Management Console.
- 2 Expand your domain and **Group Policy Objects**.
- 3 Right-click the GPO that you created for the group policy settings and select **Edit**.
- 4 In the Group Policy Management Editor, navigate to **User Configuration > Policies > Administrative Templates > Control Panel > Personalization**.
- 5 Enable the setting **Force a specific visual style file or force Windows classic** and set the Path to Visual Style as `%windir%\resources\Themes\Aero\ aero.msstyles`.

Configure Group Policy to Start Runonce.exe

By default, some applications that rely on the Explorer.exe file may not run in an application session. To avoid this issue, you must configure a GPO setting to start runonce.exe.

Prerequisites

- Verify that the Group Policy Management feature is available on your Active Directory server.
The steps for opening the Group Policy Management Console differ in the Windows 2012, Windows 2008, and Windows 2003 Active Directory versions. See "Create GPOs for Horizon 7 Group Policies" in the *Configuring Remote Desktop Features in Horizon 7* document.

Procedure

- 1 On the Active Directory server, open the Group Policy Management Console.
- 2 Expand your domain and **Group Policy Objects**.

- 3 Right-click the GPO that you created for the group policy settings and select **Edit**.
- 4 In the Group Policy Management Editor, navigate to **User Configuration > Policies > Windows Settings > Scripts (Logon/Logoff)**.
- 5 Double-click **Logon** and click **Add**.
- 6 In the Script Name box, type **runonce.exe**.
- 7 In the Script Parameters box, type **/AlternateShellStartup**.

RDS Host Performance Options

You can optimize Windows for either foreground programs or background services by setting performance options. By default, Horizon 7 disables certain performance options for RDS hosts for all supported versions of Windows Server.

The following table shows the performance options that are disabled by Horizon 7.

Table 3-6. Performance Options Disabled by Horizon 7

Performance Options Disabled by Horizon 7
Animate windows when minimizing and maximizing
Show shadows under mouse pointer
Show shadows under windows
Use drop shadow for icon labels on the desktop
Show windows contents while dragging

The five performance options that are disabled by Horizon 7 correspond to four Horizon 7 settings in the registry. The following table shows the Horizon 7 settings and their default registry values. The registry values are all located in the registry subkey HKEY_LOCAL_MACHINE\Software\VMware, Inc.\VMware VDM\Agent\Configuration. You can re-enable the performance options by setting one or more of the Horizon 7 registry values to **false**.

Table 3-7. Horizon 7 Settings Related to Windows Performance Options

Horizon 7 Setting	Registry Value
Disable cursor shadow	DisableMouseShadows
Disable full window drag	DisableFullWindowDrag
Disable ListView shadow	DisableListViewShadow
Disable Window Animation	DisableWindowAnimation

Configuring 3D Graphics for RDS Hosts

With 3D graphics configured for RDS hosts, both applications in application pools and applications running on published desktops can display 3D graphics.

The following 3D graphics options are available:

NVIDIA GRID vGPU (shared GPU hardware acceleration)	A physical GPU on an ESXi host is shared among multiple virtual machines. Requires ESXi 6.0 or later.
AMD Multiuser GPU using vDGA	A physical GPU on an ESXi host is shared among multiple virtual machines. Requires ESXi 6.0 or later.
Virtual Dedicated Graphics Acceleration (vDGA)	A physical GPU on an ESXi host is dedicated to a single virtual machine. Requires ESXi 5.5 or later.

Note Some Intel vDGA cards require a certain vSphere 6 version. See the VMware Hardware Compatibility List at <http://www.vmware.com/resources/compatibility/search.php>. Also, for Intel vDGA, the Intel integrated GPU is used rather than discrete GPUs, as is the case with other vendors.

With vDGA, you allocate an entire GPU to a single machine for maximum performance. The RDS host must be in a manual farm.

With AMD Multiuser GPU using vDGA, you can share an AMD GPU between multiple RDS hosts by making it appear as multiple PCI passthrough devices. The RDS host must be in a manual farm.

With NVIDIA GRID vGPU, each graphics card can support multiple RDS hosts and the RDS hosts must be in a manual farm. If an ESXi host has multiple physical GPUs, you can also configure the way the ESXi host assigns virtual machines to the GPUs. By default, the ESXi host assigns virtual machines to the physical GPU with the fewest virtual machines already assigned. This is called performance mode. You can also choose consolidation mode, where the ESXi host assign virtual machines to the same physical GPU until the maximum number of virtual machines is reached before placing virtual machines on the next physical GPU. To configure consolidation mode, edit the `/etc/vmware/config` file on the ESXi host and add the following entry:

```
vGPU.consolidation = "true"
```

3D graphics is only supported when you use the PCoIP or VMware Blast protocol. Therefore, the farm must use PCoIP or VMware Blast as the default protocol and users must not be allowed to choose the protocol.

Overview of Steps for Configuring 3D Graphics

This overview describes tasks that you must perform in vSphere and Horizon 7 to configure 3D graphics. For more information about setting up NVIDIA GRID vGPU, see the document [NVIDIA GRID vGPU Deployment Guide for VMware Horizon 6.1](#). For more information about setting up vDGA, see the document [Graphics Acceleration in View Virtual Desktops](#). For more information about setting up AMD Multiuser GPU using vDGA, see the *Setting Up Virtual Machine Desktops in Horizon 7* guide.

- 1 Set up an RDS host virtual machine. For more information, see [Chapter 3 Setting Up Remote Desktop Services Hosts](#).

- 2 Add the graphics PCI device to the virtual machine. See "Other Virtual Machine Device Configuration" in the chapter "Configuring Virtual machine Hardware" in the *vSphere Virtual Machine Administration* document. Be sure to click **Reserve all memory** when adding the device.
- 3 On the virtual machine, install the device driver for the graphics card.
- 4 Add the RDS host to a manual farm, create a published desktop pool, connect to the desktop using PCoIP, and activate the display adapter.

You do not need to configure 3D graphics for RDS hosts in Horizon Console. Selecting the option **3D RDSH** when you install Horizon Agent is sufficient. By default, this option is not selected and 3D graphics is disabled.

Understanding RDS Per-Device Client Access Licensing in Horizon 7

When a Windows client device connects to a published desktop or application on an RDS host, it receives an RDS Per-Device Client Access License (CAL), if the Per-Device licensing mode is configured on the RDS host.

By default, the CAL is stored only on the client device.

Note Storage of Per-Device CALs is supported only on Windows clients. Windows Zero clients, and non-Windows clients, do not support this feature. For clients that do not support this feature, CALs are stored only on the Connection Server host.

Storing the CAL makes CAL use more efficient in RDS deployments and prevents the following problems.

- If you deploy multiple license servers, and users run multiple sessions from a client device that connects to different RDS hosts that use different license servers, each license server can potentially issue a separate RDS Per-Device CAL to the same client device. If a license server services both Windows Server 2008 R2 RDS hosts and Windows Server 2012 or Windows Server 2012 R2 RDS hosts (issuing both Windows Server 2008 R2 CALs and Windows Server 2012 or 2012 R2 CALs), a single client device can use up as many as two CALs for each license server in your deployment.
- If you have Windows 2012 or 2012 R2 CALs installed on a Windows Server 2012 license server, a client device that makes a PCoIP or VMware Blast connection to a Windows Server 2008 R2 RDS host is always issued a temporary license, even after multiple connections are made. A permanent license is never issued for the client.

Considerations for Cloud Pod Architecture Environments

A typical Cloud Pod Architecture environment consists of multiple pods. Each pod can point to a different license server, and a single client device can use published desktops and applications on different pods in the pod federation.

Beginning with Horizon Client for Windows 4.9, if the client device has a license, it always presents that license. Windows clients that have Horizon Client 4.8 or earlier present a license only if they have a license for the specific pod. If the client device does not present a license, the most up-to-date license that can be found on any pod involved in the published desktop or application launch is used. If a license cannot be found on any pod involved in the launch, the client device's ID is presented to the license server and a license is issued.

Important VMware recommends that you upgrade to the latest Windows client and server software for the best handling of RDS licensing.

Creating Farms in Horizon Console

4

A farm is a group of Windows Remote Desktop Services (RDS) hosts. You can create published desktops associated with a farm. You can also deliver a published application to many users by creating application pools. The published applications in application pools run on a farm of RDS hosts.

Farms simplify the task of managing RDS hosts, published desktops, and applications in an enterprise. You can create manual or automated farms to serve groups of users that vary in size or have different desktop or application requirements.

A manual farm consists of RDS hosts that already exist. The RDS hosts can be physical or virtual machines. You manually add the RDS hosts when you create the farm.

An automated farm consists of RDS hosts that are instant-clone virtual machines in vCenter Server.

Connection Server creates the instant-clone virtual machines based on the parameters that you specify when you create the farm. Instant clones share a virtual disk of a parent VM and therefore consume less storage than full virtual machines. In addition, instant clones share the memory of a parent VM and are created using the vmFork technology.

When you create an application pool or a published desktop pool, you must specify one and only one farm. The RDS hosts in a farm can host published desktops, applications, or both. A farm can support at most one published desktop pool, but it can support multiple application pools. A farm can support both types of pools simultaneously.

For more information on farms, see the *Horizon 7 Administration* document.

This chapter includes the following topics:

- [Preparing a Parent Virtual Machine for an Automated Farm](#)
- [Worksheet for Creating a Manual Farm in Horizon Console](#)
- [Create a Manual Farm in Horizon Console](#)
- [Worksheet for Creating an Automated Instant-Clone Farm in Horizon Console](#)
- [Create an Automated Instant-Clone Farm in Horizon Console](#)
- [Worksheet for Creating an Automated Linked-Clone Farm in Horizon Console](#)
- [Create an Automated Linked-Clone Farm in Horizon Console](#)

Preparing a Parent Virtual Machine for an Automated Farm

To create an automated farm, you must first prepare a parent virtual machine. Composer or Connection Server uses this parent virtual machine to create linked-clone or instant-clone virtual machines, which are the RDS hosts in the farm.

- [Prepare an RDS Host Parent Virtual Machine](#)

Both Connection Server and Composer require a parent virtual machine from which you generate a base image for creating instant clones or linked clones.

- [Activating Windows on Linked-Clone RDS Hosts](#)

To make sure that Composer properly activates Windows Server operating systems on linked-clone RDS hosts, you must use Microsoft volume activation on the parent virtual machine. The volume-activation technology requires a volume license key.

- [Disable Windows Hibernation in the Parent Virtual Machine](#)

The Windows hibernation feature creates a hidden system file, `Hiberfil.sys` and uses this file to store information that is needed for hybrid sleep. Disabling hibernation reduces the size of an instant clone's or a View Composer linked clone's virtual disk.

Prepare an RDS Host Parent Virtual Machine

Both Connection Server and Composer require a parent virtual machine from which you generate a base image for creating instant clones or linked clones.

Prerequisites

- Verify that an RDS host virtual machine is set up. See [Chapter 3 Setting Up Remote Desktop Services Hosts](#). To set up the RDS host, be sure not to use a virtual machine that was previously registered to Connection Server.

A parent virtual machine that you use for Composer must either belong to the same Active Directory domain as the domain that the linked-clone machines will join or be a member of the local WORKGROUP.

- Verify that the virtual machine was not converted from a Composer linked clone. A virtual machine that is converted from a linked clone has the clone's internal disk and state information. A parent virtual machine cannot have state information.

Important Linked clones and virtual machines that were converted from linked clones are not supported as parent virtual machines.

- To create an automated instant-clone farm, you must select the **Instant Clone** option when you install Horizon Agent on the parent virtual machine. See [Install Horizon Agent on a Remote Desktop Services Host](#).
- Verify that the virtual switch that the instant-clone VMs connect to has enough ports to support the expected number of VMs. Each network card on a VM requires one port.

- Verify that you added an instant-clone domain administrator in Horizon Console.
- To create an automated linked-clone farm, you must select the **View Composer Agent** option when you install Horizon Agent on the parent virtual machine.

To update Horizon Agent in a large environment, you can use standard Windows update mechanisms such as Altiris, SMS, LanDesk, BMC, or other systems management software. You can also use the recompose operation to update Horizon Agent.

Note Do not change the log on account for the VMware View Composer Guest Agent Server service in a parent virtual machine. By default, this is the Local System account. If you change this account, the linked clones created from the parent do not start.

- To deploy Windows machines, configure a volume license key and activate the parent virtual machine's operating system with volume activation. See "Activating Windows on Instant Clones and Composer Linked Clones" in the *Setting Up Virtual Desktops in Horizon Console* document.
- Familiarize yourself with the procedure for disabling searching Windows Update for device drivers. See the Microsoft Technet article, "Disable Searching Windows Update for Device Drivers" at [http://technet.microsoft.com/en-us/library/cc730606\(v=ws.10\).aspx](http://technet.microsoft.com/en-us/library/cc730606(v=ws.10).aspx).
- To implement the RDS host load balancing feature, modify the RDS host parent virtual machine as described in "Configuring Load Balancing for RDS Hosts" in the *Horizon 7 Administration* document.

Procedure

- ◆ Remove the DHCP lease on the parent virtual machine to avoid copying a leased IP address to the linked clones in the farm.
 - On the parent virtual machine, open a command prompt.
 - Type the **ipconfig /release** command.

- ◆ Verify that the system disk contains a single volume.

You cannot deploy linked clones from a parent virtual machine that contains more than one volume. The View Composer service does not support multiple disk partitions. Multiple virtual disks are supported.

- ◆ Verify that the virtual machine does not contain an independent disk.

An independent disk is excluded when you take a snapshot of the virtual machine. Linked clones that are created or recomposed from the virtual machine will not contain the independent disk.

- ◆ Disable the hibernation option to reduce the size of linked-clone OS disks that are created from the parent virtual machine.
- ◆ Before you take a snapshot of the parent virtual machine, disable searching Windows Update for device drivers.

This Windows feature can interfere with the customization of linked-clone machines. As each linked clone is customized, Windows might search for the best drivers on the Internet for that clone, resulting in repeated searches and customization delays.

- ◆ In vSphere Client, disable the vApp Options setting on the parent virtual machine.
- ◆ On Windows Server 2008 R2 and Windows Server 2012 R2 machines, disable the scheduled maintenance task that recovers disk space by removing unused features.

For example: `Schtasks.exe /change /disable /tn "\\Microsoft\\Windows\\AppxDeploymentClient\\Pre-staged app cleanup"`

If left enabled, this maintenance task can remove the Sysprep customization script after the linked clones are created, which would cause subsequent recompose operations to fail with customization operation timeout errors. For more information, see the Microsoft KB article available at <http://support.microsoft.com/kb/2928948>.

- ◆ On Windows Server 2012 machines, apply the Microsoft hotfix available at <https://support.microsoft.com/en-us/kb/3020396>.

This hotfix allows Sysprep to customize a Windows Server 2012 virtual machine that has the RDS role enabled. Without the hotfix, Sysprep customization will fail on the Windows Server 2012 linked-clone machines that are deployed in an automated farm.

What to do next

Use vSphere Client or vSphere Web Client to take a snapshot of the parent virtual machine in its powered-down state. This snapshot is used as the baseline configuration for the first set of linked-clone machines that are anchored to the parent virtual machine.

Important Before you take a snapshot, completely shut down the parent virtual machine by using the **Shut Down** command in the guest operating system.

Activating Windows on Linked-Clone RDS Hosts

To make sure that Composer properly activates Windows Server operating systems on linked-clone RDS hosts, you must use Microsoft volume activation on the parent virtual machine. The volume-activation technology requires a volume license key.

To activate Windows with volume activation, you use Key Management Service (KMS), which requires a KMS license key. See your Microsoft dealer to acquire a volume license key and configure volume activation.

Note Composer does not support Multiple Activation Key (MAK) licensing.

Before you create linked-clone machines with Composer, you must use volume activation to activate the operating system on the parent virtual machine.

When a linked-clone machine is created, and each time the linked clone is recomposed, the Composer agent uses the parent virtual machine's KMS server to activate the operating system on the linked clone.

For KMS licensing, Composer uses the KMS server that is configured to activate the parent virtual machine. The KMS server treats an activated linked clone as a computer with a newly issued license.

Disable Windows Hibernation in the Parent Virtual Machine

The Windows hibernation feature creates a hidden system file, `Hiberfil.sys` and uses this file to store information that is needed for hybrid sleep. Disabling hibernation reduces the size of an instant clone's or a View Composer linked clone's virtual disk.

Caution When you make hibernation unavailable, hybrid sleep does not work. Users can lose data if a power loss occurs.

Procedure

- 1 In vSphere Client, select the parent virtual machine and select **Open Console**.
- 2 Log in as an administrator.
- 3 Disable the hibernation option.
 - a Click **Start** and type `cmd` in the **Start Search** box.
 - b In the search results list, right-click **Command Prompt** and click **Run as Administrator**.
 - c At the **User Account Control** prompt, click **Continue**.
 - d At the command prompt, type `powercfg.exe /hibernate off` and press Enter.
 - e Type `exit` and press Enter.

Worksheet for Creating a Manual Farm in Horizon Console

When you create a manual farm, you can configure certain farm settings.

Table 4-1. Worksheet: Configuration Settings for Creating a Manual Farm

Setting	Description	Fill in Your Value Here
ID	Unique name that identifies the farm.	
Description	Description of this farm.	
Access group	Select an access group for the farm, or leave the farm in the default root access group.	
Default display protocol	Select VMware Blast , PCoIP or Microsoft RDP . Microsoft RDP applies to desktop pools only. The display protocol for application pools is always VMware Blast or PCoIP . If you select Microsoft RDP and you plan to use this farm to host application pools, you must set Allow users to choose protocol to Yes . The default is PCoIP .	
Allow users to choose protocol	Select Yes or No . This setting applies to published desktop pools only. If you select Yes , users can choose the display protocol when they connect to a published desktop from Horizon Client. The default is Yes .	

Table 4-1. Worksheet: Configuration Settings for Creating a Manual Farm (continued)

Setting	Description	Fill in Your Value Here
Pre-launch session timeout (applications only)	<p>Determines the amount of time that an application configured for pre-launch is kept open. The default is 10 minutes.</p> <p>If the end-user does not start any application in Horizon Client, the application session is disconnected if the idle session times out or if pre-launch session times out.</p> <p>If you want to end the pre-launch session after timeout, you must set the Log off disconnected session option to Immediate.</p>	
Empty session timeout (applications only)	<p>Determines the amount of time that an empty application session is kept open. An application session is empty when all the applications that run in the session are closed. While the session is open, users can open applications faster. You can save system resources if you disconnect or log off empty application sessions. Select Never, Immediate, or set the number of minutes as the timeout value. The default is After 1 minute. If you select Immediate, the session logs off or disconnects within 30 seconds.</p> <p>You can further reduce the time the session logs off or disconnects by editing a registry key on the RDS Host on which Horizon Agent is installed. Navigate to HKEY_LOCAL_MACHINE\SOFTWARE\VMware, Inc.\VMware VDM\Plugins\wssm\applaunchmgr\Params and set a value for WindowCheckInterval. The default value is 20000. This means that the poll for the empty session check is every 20 seconds, which sets the maximum time between the last application session close and session log off to 40 seconds. You can change this value to 2500. This means that the poll for the empty session check is every 2.5 seconds, which sets the maximum time between the last application close and session log off to 5 seconds.</p>	
When timeout occurs	Determines whether an empty application session is disconnected or logged off after the Empty session timeout limit is reached. Select Disconnect or Log off . A session that is logged off frees up resources, but opening an application takes longer. The default is Disconnect .	
Log off disconnected session	Determines when a disconnected session is logged off. This setting applies to both desktop and application sessions. Select Never , Immediate , or After ... minutes . Use caution when you select Immediate or After ... minutes . When a disconnected session is logged off, the session is lost. The default is Never .	
Allow HTML Access to desktops and applications on this farm	Determines whether HTML Access to published desktops and applications is allowed. Check the Enabled box to allow HTML Access to published desktops and applications. When you edit this setting after a farm is created, the new value applies to existing desktops and applications as well as new ones.	
Allow Session Collaboration	Select Enabled to allow users of desktop pools based on this farm to invite other users to join their remote desktop sessions. Session owners and collaborators must use the VMware Blast protocol.	

Create a Manual Farm in Horizon Console

Create a manual farm as part of the process to give users access to published applications or desktops.

Prerequisites

- Set up the RDS hosts that belong to the farm. See [Chapter 3 Setting Up Remote Desktop Services Hosts](#).
- Verify that all the RDS hosts have the Available status. In Horizon Console, select **Settings > Registered Machines** and check the status of each RDS host on the RDS Hosts tab.
- Gather the configuration information you must provide to create the farm. See [Worksheet for Creating a Manual Farm in Horizon Console](#).

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Click **Add**.
- 3 Select **Manual Farm**.
- 4 Follow the prompts in the wizard to create the farm.

Use the configuration information you gathered in the worksheet. You can go directly back to any wizard page by clicking the page name in the navigation pane.

- 5 Select the RDS hosts to add to the farm and click **Next**.
- 6 Click **Finish**.

What to do next

Create a published application or desktop pool.

Worksheet for Creating an Automated Instant-Clone Farm in Horizon Console

When you create an automated instant-clone farm, you can configure certain settings.

Table 4-2. Worksheet: Configuration Settings for Creating an Automated Instant-Clone Farm

Setting	Description	Fill in Your Value Here
ID	Unique name that identifies the farm.	
Description	Description of this farm.	
Access group	Select an access group for the farm, or leave the farm in the default root access group.	
Default display protocol	Select VMware Blast , PCoIP or Microsoft RDP . Microsoft RDP applies to desktop pools only. The display protocol for application pools is always VMware Blast or PCoIP . If you select Microsoft RDP and you plan to use this farm to host application pools, you must set Allow users to choose protocol to Yes . The default is PCoIP .	
Allow users to choose protocol	Select Yes or No . This setting applies to published desktop pools only. If you select Yes , users can choose the display protocol when they connect to a published desktop from Horizon Client. The default is Yes .	

Table 4-2. Worksheet: Configuration Settings for Creating an Automated Instant-Clone Farm (continued)

Setting	Description	Fill in Your Value Here
3D Renderer	<p>Select 3D graphics rendering for desktops.</p> <p>3D rendering is supported on Windows 2008, Windows 2012, and Windows 2016 guests running on VMs with virtual hardware version 11 or later. The hardware-based renderer is supported (at minimum) on virtual hardware version 11 and above in a vSphere 6.0 U1 and above environment. The software renderer is supported (at minimum) on virtual hardware version 11 in a vSphere 6.0 U1 and above environment.</p> <p>On ESXi 5.0 hosts, the renderer allows a maximum VRAM size of 128MB. On ESXi 5.1 and later hosts, the maximum VRAM size is 512MB. On hardware version 11 (HWv11) virtual machines in vSphere 6.0, the VRAM value (video memory) has changed. Select the Manage Using vSphere Client option and configure video memory for these machines in vSphere Web Client. For details, see "Configuring 3D Graphics" in the vSphere Virtual Machine Administration guide.</p> <p>3D rendering is disabled if you select Microsoft RDP as the default display protocol and do not allow users to choose a display protocol.</p> <ul style="list-style-type: none"> ■ NVIDIA GRID vGPU. 3D rendering is enabled for NVIDIA GRID vGPU. The ESXi host reserves GPU hardware resources on a first-come, first-served basis as virtual machines are powered on. You cannot use vSphere Distributed Resource Scheduler (DRS) when you select this option. <p>To use NVIDIA GRID vGPU for an instant-clone farm, the recommendation is to select VMware Blast as a protocol and not allow the user to choose their own display protocols.</p> <ul style="list-style-type: none"> ■ Manage using vSphere Client. The 3D Renderer option that is set in vSphere Web Client (or vSphere Client in vSphere 5.1 or later) for a virtual machine determines the type of 3D graphics rendering that takes place. Horizon 7 does not control 3D rendering. In the vSphere Web Client, you can configure the Automatic, Software, or Hardware options. These options have the same effect as they do when you set them in Horizon Console. Use this setting when configuring vDGA and AMD Multiuser GPU Using vDGA. This setting is also an option for vSGA. When you select the Manage using vSphere Client option, the Configure VRAM for 3D Guests, Max number of monitors, and Max resolution of any one monitor settings are inactive in Horizon Console. You can configure the amount of memory in vSphere Web Client. ■ Disabled. 3D rendering is inactive. Default is disabled. 	
Pre-launch session timeout (applications only)	<p>Determines the amount of time that an application configured for pre-launch is kept open. The default is 10 minutes.</p> <p>If the end-user does not start any application in Horizon Client, the application session is disconnected if the idle session times out or if pre-launch session times out.</p> <p>If you want to end the pre-launch session after timeout, you must set the Log off disconnected session option to Immediate.</p>	

Table 4-2. Worksheet: Configuration Settings for Creating an Automated Instant-Clone Farm (continued)

Setting	Description	Fill in Your Value Here
Empty session timeout (applications only)	<p>Determines the amount of time that an empty application session is kept open. An application session is empty when all the applications that run in the session are closed. While the session is open, users can open applications faster. You can save system resources if you disconnect or log off empty application sessions. Select Never, Immediate, or set the number of minutes as the timeout value. The default is After 1 minute. If you select Immediate, the session logs off or disconnects within 30 seconds.</p> <p>You can further reduce the time the session logs off or disconnects by editing a registry key on the RDS Host on which Horizon Agent is installed. Navigate to HKEY_LOCAL_MACHINE\SOFTWARE\VMware, Inc.\VMware VDM\Plugins\wsm\applaunchmgr\Params and set a value for WindowCheckInterval. The default value is 20000. This means that the poll for the empty session check is every 20 seconds, which sets the maximum time between the last application session close and session log off to 40 seconds. You can change this value to 2500. This means that the poll for the empty session check is every 2.5 seconds, which sets the maximum time between the last application close and session log off to 5 seconds.</p>	
When timeout occurs	Determines whether an empty application session is disconnected or logged off after the Empty session timeout limit is reached. Select Disconnect or Log off . A session that is logged off frees up resources, but opening an application takes longer. The default is Disconnect .	
Log off disconnected session	Determines when a disconnected session is logged off. This setting applies to both desktop and application sessions. Select Never , Immediate , or After ... minutes . Use caution when you select Immediate or After ... minutes . When a disconnected session is logged off, the session is lost. The default is Never .	
Allow HTML Access to desktops and applications on this farm	Determines whether HTML Access to published desktops and applications is allowed. Check the Enabled box to allow HTML Access to published desktops and applications. When you edit this setting after a farm is created, the new value applies to existing desktops and applications as well as new ones.	
Allow Session Collaboration	Select Enabled to allow users of desktop pools based on this farm to invite other users to join their remote desktop sessions. Session owners and session collaborators must use the VMware Blast display protocol.	
Max sessions per RDS server	Determines the maximum number of sessions that an RDS host can support. Select Unlimited or No More Than The default is Unlimited .	
Enable provisioning	Select this checkbox to enable provisioning after you finish this wizard. This box is checked by default.	
Stop provisioning on error	Select this checkbox to stop provisioning when a provisioning error occurs. This box is checked by default.	

Table 4-2. Worksheet: Configuration Settings for Creating an Automated Instant-Clone Farm (continued)

Setting	Description	Fill in Your Value Here
Naming pattern	<p>Specify a prefix or a name format. Horizon 7 will append or insert an automatically generated number starting with 1 to form the machine name. If you want the number at the end, simply specify a prefix. Otherwise, specify {n} anywhere in a character string and {n} will be replaced by the number. You can also specify {n:fixed=<number of digits>}, where fixed=<number of digits> indicates the number of digits to be used for the number. For example, specify vm-{n:fixed=3}-sales and the machine names will be vm-001-sales, vm-002-sales, and so on.</p> <p>Note Each machine name, including the automatically generated number, has a 15-character limit.</p>	
Max number of machines	The number of machines to be provisioned.	
Minimum number of ready (provisioned) machines during Instant Clone maintenance operations	This setting lets you keep the specified number of machines available to accept connection requests while Connection Server performs maintenance operations on the machines in the farm. This setting is not honored if you schedule immediate maintenance.	
Use VMware vSAN	Specify whether to use VMware vSAN, if available. vSAN is a software-defined storage tier that virtualizes the local physical storage disks available on a cluster of ESXi hosts.	
Select separate datastores for replica and OS disks	<p>(Available only if you do not use vSAN) You can place replica and OS disks on different datastores for performance or other reasons.</p> <p>If you select this option, you can select the options to select one or more instant-clone datastores or replica disk datastores.</p>	
Parent VM	Select a parent virtual machine from the list. Be aware that the list includes virtual machines that do not have View Composer Agent installed. You must not select any of those machines because View Composer Agent is required. A good practice is to use a naming convention that indicates whether a virtual machine has View Composer Agent installed.	
Snapshot	<p>Select the snapshot of the parent virtual machine to use as the base image for the farm.</p> <p>Do not delete the snapshot and parent virtual machine from vCenter Server, unless no instant clones in the farm use the default image, and no more instant clones will be created from this default image. The system requires the parent virtual machine and snapshot to provision new instant clones in the farm, according to farm policies. The parent virtual machine and snapshot are also required for Connection Server maintenance operations.</p>	
VM folder location	Select the folder in vCenter Server in which the farm resides.	

Table 4-2. Worksheet: Configuration Settings for Creating an Automated Instant-Clone Farm (continued)

Setting	Description	Fill in Your Value Here
Cluster	<p>Select the ESXi host or cluster on which the desktop virtual machines run.</p> <p>With vSAN datastores (a vSphere 5.5 Update 1 feature), you can select a cluster with up to 20 ESXi hosts. With Virtual Volumes datastores (a vSphere 6.0 feature), you can select a cluster with up to 32 ESXi hosts.</p> <p>In vSphere 5.1 or later, you can select a cluster with up to 32 ESXi hosts if the replicas are stored on VMFS5 or later datastores or NFS datastores. If you store replicas on a VMFS version earlier than VMFS5, a cluster can have at most eight hosts.</p> <p>In vSphere 5.0, you can select a cluster with more than eight ESXi hosts if the replicas are stored on NFS datastores. If you store replicas on VMFS datastores, a cluster can have at most eight hosts.</p>	
Resource pool	Select the vCenter Server resource pool in which the farm resides.	
Datastores	<p>Select one or more datastores on which to store the farm.</p> <p>A table on the Select Instant Clone Datastores page of the Add Farm wizard provides high-level guidelines for estimating the farm's storage requirements. These guidelines can help you determine which datastores are large enough to store the instant-clones. The Storage Overcommit value is always set to Unbounded and is not configurable.</p> <hr/> <p>Note If you use vSAN, select only one datastore.</p>	
Replica disk datastores	<p>Select one or more replica disk datastores on which to store the instant-clones. This option appears if you select separate datastores for replica and OS disks.</p> <p>A table on the Select Replica Disk Datastores page of the Add Farm wizard provides high-level guidelines for estimate the farm's storage requirements. These guidelines can help you determine which replica disk datastores are enough to store the instant-clones.</p>	
Networks	<p>Select the networks to use for the automated instant-clone farm. You can select multiple vLAN networks to create a larger instant-clone desktop farm. The default setting uses the network from the current parent VM image.</p> <p>The Select Networks wizard provides a list of networks based on the parent VM network type: DVS, NSX-t, and Standard. To use multiple networks, you must unselect Use network from current parent VM image and then select the networks to use with the instant-clone farm. The Show All Networks switch shows or hides (greys out) incompatible networks within the selected network type. By default, only compatible networks are shown. If you select an incompatible network, such as vmcNetworks, you see this error message: This network belongs to VMC internal network.</p> <p>The wizard also provides the list of ports and port bindings that are available to use: static (early binding) and dynamic (ephemeral). Instant-clones only support static port group types even though dynamic port bindings are also listed.</p>	

Table 4-2. Worksheet: Configuration Settings for Creating an Automated Instant-Clone Farm (continued)

Setting	Description	Fill in Your Value Here
Domain	<p>Select the Active Directory domain and user name.</p> <p>Connection Server requires certain user privileges to farm. The domain and user account are used by ClonePrep to customize the instant-clone machines.</p> <p>You specify this user when you configure Connection Server settings for vCenter Server. You can specify multiple domains and users when you configure Connection Server settings. When you use the Add Farm wizard to create a farm, you must select one domain and user from the list.</p>	
AD container	<p>Provide the Active Directory container relative distinguished name.</p> <p>For example: CN=Computers</p> <p>When you run the Add Farm wizard, you can browse your Active Directory tree for the container. You can cut, copy, or paste in the container name.</p>	
Allow reuse of pre-existing computer accounts	<p>Select this option to use existing computer accounts in Active Directory when the virtual machine names of new instant clones match the existing computer account names.</p> <p>When an instant clone is created, if an existing AD computer account name matches the instant-clone virtual machine name, Horizon 7 uses the existing computer account. Otherwise, a new computer account is created.</p> <p>The existing computer accounts must be located in the Active Directory container that you specify with the AD container setting.</p> <p>When this option is disabled, a new AD computer account is created when Horizon 7 creates an instant clone. This option is disabled by default.</p>	
Image Publish Computer Account	<p>Publishing instant-clones requires an additional computer account in the same AD domain as the clones. If you want to use pre-created computer accounts instead of auto-created computer accounts, you must also create the additional computer account and specify its name here. Then you do not need to delegate Create and Delete of computer objects to the provisioning account.</p>	
Use ClonePrep	<p>Provide a ClonePrep customization specification to customize the virtual machines.</p> <ul style="list-style-type: none"> ■ Power-off script name. Name of the customization script that ClonePrep runs on instant-clone machines before they are powered off. Provide the path to the script on the parent virtual machine. ■ Power-off script parameters. Provide parameters that ClonePrep can use to run a customization script on instant-clone machines before they are powered off. For example, use p1. ■ Post-synchronization script name. Name of the customization script that ClonePrep runs on instant-clone machines after they are created or an image has been pushed to them. Provide the path to the script on the parent virtual machine. ■ Post-synchronization script parameters. Provide parameters for the script that ClonePrep runs on instant-clone machines after they are created or an image has been pushed to them. For example, use p2. 	
Ready to Complete	Review the settings for the automated instant-clone farm.	

Create an Automated Instant-Clone Farm in Horizon Console

You create an automated instant-clone farm as part of the process to give users access to published applications or published desktops.

Prerequisites

- Verify that Connection Server is installed. See the *Horizon 7 Installation* document.
- Verify that Connection Server settings for vCenter Server are configured in Horizon Console. See the *VMware Horizon Console Administration* document.
- Verify that you have a sufficient number of ports on the ESXi virtual switch that is used for the virtual machines that are used as remote desktops. The default value might not be sufficient if you create large desktop pools.
- Verify that you prepared a parent virtual machine. Horizon Agent must be installed on the parent virtual machine. See [Preparing a Parent Virtual Machine for an Automated Farm](#).
- Take a snapshot of the parent virtual machine in vCenter Server. You must shut down the parent virtual machine before you take the snapshot. Connection Server uses the snapshot as the base image from which the clones are created.
- Gather the configuration information you must provide to create the farm. See [Worksheet for Creating an Automated Instant-Clone Farm in Horizon Console](#).

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Click **Add**.
- 3 Select **Automated Farm**.
- 4 Select **Instant clone**.
- 5 Follow the prompts in the wizard to create the farm.

Use the configuration information that you gathered in the worksheet. You can go directly back to any wizard page that you completed by clicking the page name in the navigation panel.

What to do next

Create a published application pool or a published desktop pool. See [Chapter 5 Creating Published Desktop Pools in Horizon Console](#) or [Chapter 6 Creating Application Pools in Horizon Console](#).

Worksheet for Creating an Automated Linked-Clone Farm in Horizon Console

When you create an automated linked-clone farm, you can configure certain settings.

Table 4-3. Worksheet: Configuration Settings for Creating an Automated Linked-Clone Farm

Setting	Description	Fill in Your Value Here
ID	Unique name that identifies the farm in Horizon Console.	
Description	Description of this farm.	
Access group	Access group in which to place all the pools in this farm. For more information about access groups, see the role-based delegated administration chapter in the <i>Horizon 7 Administration</i> document.	
Default display protocol	Select VMware Blast , PCoIP or RDP . RDP applies to desktop pools only. The display protocol for application pools is always VMware Blast or PCoIP . If you select RDP and you plan to use this farm to host application pools, you must set Allow users to choose protocol to Yes . The default is PCoIP .	
Allow users to choose protocol	Select Yes or No . This setting applies to RDS desktop pools only. If you select Yes , users can choose the display protocol when they connect to an RDS desktop from Horizon Client. The default is Yes .	
Pre-launch session timeout (applications only)	Determines the amount of time that an application configured for pre-launch is kept open. The default is 10 minutes . If the end-user does not start any application in Horizon Client, the application session is disconnected if the idle session times out or if pre-launch session times out. If you want to end the pre-launch session after timeout, you must set the Log off disconnected session option to Immediate .	
Empty session timeout (applications only)	Determines the amount of time that an empty application session is kept open. An application session is empty when all the applications that run in the session are closed. While the session is open, users can open applications faster. You can save system resources if you disconnect or log off empty application sessions. Select Never , Immediate , or set the number of minutes as the timeout value. The default is After 1 minute . If you select Immediate , the session logs off or disconnects within 30 seconds. You can further reduce the time the session logs off or disconnects by editing a registry key on the RDS Host on which Horizon Agent is installed. Navigate to HKEY_LOCAL_MACHINE\SOFTWARE\VMware, Inc.\VMware VDM\Plugins\wssm\applaunchmgr\Params and set a value for WindowCheckInterval. The default value is 20000. This means that the poll for the empty session check is every 20 seconds, which sets the maximum time between the last application session close and session log off to 40 seconds. You can change this value to 2500. This means that the poll for the empty session check is every 2.5 seconds, which sets the maximum time between the last application close and session log off to 5 seconds.	
When timeout occurs	Determines whether an empty application session is disconnected or logged off after the Empty session timeout limit is reached. Select Disconnect or Log off . A session that is logged off frees up resources, but opening an application takes longer. The default is Disconnect .	
Log off disconnected session	Determines when a disconnected session is logged off. This setting applies to both desktop and application sessions. Select Never , Immediate , or After ... minutes . Use caution when you select Immediate or After ... minutes . When a disconnected session is logged off, the session is lost. The default is Never .	

Table 4-3. Worksheet: Configuration Settings for Creating an Automated Linked-Clone Farm (continued)

Setting	Description	Fill in Your Value Here
Allow HTML Access to desktops and applications on this farm	Determines whether HTML Access to RDS desktops and applications is allowed. Check the Enabled box to allow HTML Access to RDS desktops and applications. When you edit this setting after a farm is created, the new value applies to existing desktops and applications as well as new ones.	
Allow Session Collaboration	Select Enabled to allow users of desktop pools based on this farm to invite other users to join their remote desktop sessions. Session owners and session collaborators must use the VMware Blast protocol.	
Max sessions per RDS server	Determines the maximum number of sessions that an RDS host can support. Select Unlimited or No More Than The default is Unlimited .	
Enable provisioning	Select this checkbox to enable provisioning after you finish this wizard. This box is checked by default.	
Stop provisioning on error	Select this checkbox to stop provisioning when a provisioning error occurs. This box is checked by default.	
Naming pattern	<p>Specify a prefix or a name format. Horizon 7 will append or insert an automatically generated number starting with 1 to form the machine name. If you want the number at the end, simply specify a prefix. Otherwise, specify {n} anywhere in a character string and {n} will be replaced by the number. You can also specify {n:fixed=<number of digits>}, where fixed=<number of digits> indicates the number of digits to be used for the number. For example, specify vm-{n:fixed=3}-sales and the machine names will be vm-001-sales, vm-002-sales, and so on.</p> <p>Note Each machine name, including the automatically generated number, has a 15-character limit.</p>	
Max number of machines	The number of machines to be provisioned.	
Minimum number of ready (provisioned) machines during View Composer maintenance operations	This setting lets you keep the specified number of machines available to accept connection requests while View Composer recomposes the machines in the farm.	
Use VMware vSAN	Specify whether to use VMware vSAN, if available. vSAN is a software-defined storage tier that virtualizes the local physical storage disks available on a cluster of ESXi hosts. For more information, see "Using vSAN for High-Performance Storage and Policy-Based Management" in the <i>Setting Up Virtual Desktops in Horizon 7</i> document.	
Select separate datastores for replica and OS disks	(Available only if you do not use vSAN) You can place replica and OS disks on different datastores for performance or other reasons.	
Parent VM	Select a parent virtual machine from the list. Be aware that the list includes virtual machines that do not have View Composer Agent installed. You must not select any of those machines because View Composer Agent is required. A good practice is to use a naming convention that indicates whether a virtual machine has View Composer Agent installed.	

Table 4-3. Worksheet: Configuration Settings for Creating an Automated Linked-Clone Farm (continued)

Setting	Description	Fill in Your Value Here
Snapshot	<p>Select the snapshot of the parent virtual machine to use as the base image for the farm.</p> <p>Do not delete the snapshot and parent virtual machine from vCenter Server, unless no linked clones in the farm use the default image, and no more linked clones will be created from this default image. The system requires the parent virtual machine and snapshot to provision new linked clones in the farm, according to farm policies. The parent virtual machine and snapshot are also required for View Composer maintenance operations.</p>	
VM folder location	Select the folder in vCenter Server in which the farm resides.	
Cluster	<p>Select the ESXi host or cluster on which the desktop virtual machines run. With vSAN datastores (a vSphere 5.5 Update 1 feature), you can select a cluster with up to 20 ESXi hosts. With Virtual Volumes datastores (a vSphere 6.0 feature), you can select a cluster with up to 32 ESXi hosts.</p> <p>In vSphere 5.1 or later, you can select a cluster with up to 32 ESXi hosts if the replicas are stored on VMFS5 or later datastores or NFS datastores. If you store replicas on a VMFS version earlier than VMFS5, a cluster can have at most eight hosts.</p> <p>In vSphere 5.0, you can select a cluster with more than eight ESXi hosts if the replicas are stored on NFS datastores. If you store replicas on VMFS datastores, a cluster can have at most eight hosts.</p>	
Resource pool	Select the vCenter Server resource pool in which the farm resides.	
Datastores	<p>Select one or more datastores on which to store the farm.</p> <p>A table on the Select Linked Clone Datastores page of the Add Farm wizard provides high-level guidelines for estimating the farm's storage requirements. These guidelines can help you determine which datastores are large enough to store the linked-clone disks. For details, see "Storage Sizing for Instant-Clone and Linked-Clone Desktop Pools" in the <i>Setting Up Virtual Desktops in Horizon 7</i> document.</p> <p>You can use shared or local datastores for an individual ESXi host or for ESXi clusters. If you use local datastores in an ESXi cluster, you must consider the vSphere infrastructure constraints that are imposed on your desktop deployment. For details, see "Storing Linked Clones on Local Datastores" in the <i>Setting Up Virtual Desktops in Horizon 7</i> document..</p> <p>Note If you use vSAN, select only one datastore.</p>	
Storage Overcommit	<p>Determine the storage-overcommit level at which linked-clones are created on each datastore.</p> <p>As the level increases, more linked clones fit on the datastore and less space is reserved to let individual clones grow. A high storage-overcommit level lets you create linked clones that have a total logical size larger than the physical storage limit of the datastore. For details, see "Storage Overcommit for View Composer Linked-Clone Virtual Machines" in the <i>Setting Up Virtual Desktops in Horizon 7</i> document.</p> <p>Note This setting has no effect if you use vSAN.</p>	

Table 4-3. Worksheet: Configuration Settings for Creating an Automated Linked-Clone Farm (continued)

Setting	Description	Fill in Your Value Here
Use native NFS snapshots (VAAI)	<p>(Available only if you do not use vSAN) If your deployment includes NAS devices that support the vStorage APIs for Array Integration (VAAI), you can use native snapshot technology to clone virtual machines.</p> <p>You can use this feature only if you select datastores that reside on NAS devices that support native cloning operations through VAAI.</p> <p>You cannot use this feature if you store replicas and OS disks on separate datastores. You cannot use this feature on virtual machines with space-efficient disks.</p> <p>This feature is supported on vSphere 5.0 and later.</p> <p>For details, see "Using VAAI Storage for View Composer Linked Clones" in the <i>Setting Up Virtual Desktops in Horizon 7</i> document..</p>	
Reclaim VM disk space	<p>(Available only if you do not use vSAN or Virtual Volumes) Determine whether to allow ESXi hosts to reclaim unused disk space on linked clones that are created in space-efficient disk format. The space reclamation feature reduces the total storage space required for linked-clone desktops.</p> <p>This feature is supported on vSphere 5.1 and later. The linked-clone virtual machines must be virtual hardware version 9 or later.</p> <p>For details, see "Reclaim Disk Space on Linked-Clone Virtual Machines" in the <i>Setting Up Virtual Desktops in Horizon 7</i> document.</p>	
Initiate reclamation when unused space on VM exceeds:	<p>(Available only if you do not use vSAN or Virtual Volumes) Type the minimum amount of unused disk space, in gigabytes, that must accumulate on a linked-clone OS disk to trigger space reclamation. When the unused disk space exceeds this threshold, Horizon 7 initiates the operation that directs the ESXi host to reclaim space on the OS disk.</p> <p>This value is measured per virtual machine. The unused disk space must exceed the specified threshold on an individual virtual machine before Horizon 7 starts the space reclamation process on that machine.</p> <p>For example: 2 GB.</p> <p>The default value is 1 GB.</p>	
Blackout Times	<p>Configure days and times during which the reclamation of virtual machine disk space do not take place.</p> <p>To ensure that ESXi resources are dedicated to foreground tasks when necessary, you can prevent the ESXi hosts from performing these operations during specified periods of time on specified days.</p> <p>For details, see "Set Storage Accelerator and Space Reclamation Blackout Times for View Composer Linked Clones" in the <i>Setting Up Virtual Desktops in Horizon 7</i> document.</p>	

Table 4-3. Worksheet: Configuration Settings for Creating an Automated Linked-Clone Farm (continued)

Setting	Description	Fill in Your Value Here
Transparent Page Sharing Scope	<p>Select the level at which to allow transparent page sharing (TPS). The choices are Virtual Machine (the default), Farm, Pod, or Global. If you turn on TPS for all the machines in the farm, pod, or globally, the ESXi host eliminates redundant copies of memory pages that result if the machines use the same guest operating system or applications.</p> <p>Page sharing happens on the ESXi host. For example, if you enable TPS at the farm level but the farm is spread across multiple ESXi hosts, only virtual machines on the same host and within the same farm will share pages. At the global level, all machines managed by Horizon 7 on the same ESXi host can share memory pages, regardless of which farm the machines reside in.</p> <p>Note The default setting is not to share memory pages among machines because TPS can pose a security risk. Research indicates that TPS could possibly be abused to gain unauthorized access to data in very limited configuration scenarios.</p>	
Domain	<p>Select the Active Directory domain and user name.</p> <p>View Composer requires certain user privileges to farm. The domain and user account are used by Sysprep to customize the linked-clone machines.</p> <p>You specify this user when you configure View Composer settings for vCenter Server. You can specify multiple domains and users when you configure View Composer settings. When you use the Add Farm wizard to create a farm, you must select one domain and user from the list.</p> <p>For information about configuring View Composer, see the <i>Horizon 7 Administration</i> document.</p>	
AD container	<p>Provide the Active Directory container relative distinguished name.</p> <p>For example: CN=Computers</p> <p>When you run the Add Farm wizard, you can browse your Active Directory tree for the container.</p>	
Allow reuse of pre-existing computer accounts	<p>Select this setting to use existing computer accounts in Active Directory for linked clones that are provisioned by View Composer. This setting lets you control the computer accounts that are created in Active Directory.</p> <p>When a linked clone is provisioned, if an existing AD computer account name matches the linked clone machine name, View Composer uses the existing computer account. Otherwise, a new computer account is created.</p> <p>The existing computer accounts must be located in the Active Directory container that you specify with the Active Directory container setting.</p> <p>When this setting is disabled, a new AD computer account is created when View Composer provisions a linked clone. This setting is disabled by default.</p> <p>For details, see "Use Existing Active Directory Computer Accounts for Linked Clones" in the <i>Setting Up Virtual Desktops in Horizon 7</i> document.</p>	
Use a customization specification (Sysprep)	<p>Provide a Sysprep customization specification to customize the virtual machines.</p>	

Create an Automated Linked-Clone Farm in Horizon Console

You create an automated linked-clone farm as part of the process to give users access to published applications or published desktops.

Prerequisites

- Verify that the View Composer service is installed. See the *Horizon 7 Installation* document.
- Verify that Composer settings for vCenter Server are configured. See the *VMware Horizon Console Administration* document.
- Verify that you have a sufficient number of ports on the ESXi virtual switch that is used for the virtual machines that are used as remote desktops. The default value might not be sufficient if you create large desktop pools. The number of virtual switch ports on the ESXi host must equal or exceed the number of virtual machines multiplied by the number of virtual NICs per virtual machine.
- Verify that you prepared a parent virtual machine. Both Horizon Agent and View Composer Agent must be installed on the parent virtual machine. See, the *VMware Horizon Console Administration* document.
- Take a snapshot of the parent virtual machine in vCenter Server. You must shut down the parent virtual machine before you take the snapshot. Composer uses the snapshot as the base image from which the clones are created.

Note You cannot create a linked-clone farm from a virtual machine template.

- Gather the configuration information you must provide to create the farm. See [Worksheet for Creating an Automated Linked-Clone Farm in Horizon Console](#).

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Click **Add**.
- 3 Select **Automated Farm**.
- 4 Select **View Composer linked clones**.
- 5 Follow the prompts in the wizard to create the farm.

Use the configuration information that you gathered in the worksheet. You can go directly back to any wizard page that you completed by clicking the page name in the navigation panel.

In Horizon Console, you can now view the farm by clicking **Inventory > Farms**.

What to do next

Create a published application pool or a published desktop pool. See [Chapter 5 Creating Published Desktop Pools in Horizon Console](#) or [Chapter 6 Creating Application Pools in Horizon Console](#).

Creating Published Desktop Pools in Horizon Console

5

One of the tasks that you perform to give users remote access to session-based desktops is to create a published desktop pool. A published desktop pool runs on a farm of RDS hosts and has properties that can satisfy some specific needs of a remote desktop deployment.

This chapter includes the following topics:

- [Understanding Published Desktop Pools](#)
- [Published Desktop Pools Settings](#)
- [Create a Published Desktop Pool in Horizon Console](#)
- [Troubleshooting Instant Clones in the Internal VM Debug Mode](#)

Understanding Published Desktop Pools

A published desktop pool is one of three types of desktop pools that you can create. This type of pool was known as a Microsoft Terminal Services pool in previous Horizon 7 releases.

A published desktop pool and a published desktop have the following characteristics:

- A published desktop pool is associated with a farm, which is a group of RDS hosts. Each RDS host is a Windows server that can host multiple published desktops.
- A published desktop is based on a session to an RDS host. In contrast, a desktop in an automated desktop pool is based on a virtual machine, and a desktop in a manual desktop pool is based on a virtual or physical machine.
- A published desktop supports the RDP, PCoIP, and VMware Blast display protocols. To enable HTML Access, see "Prepare Desktops, Pools, and Farms for HTML Access," in the "Setup and Installation" chapter in the *Using HTML Access* document, available from <https://docs.vmware.com/en/VMware-Horizon-Client/index.html>.
- A published desktop pool is only supported on Windows Server operating systems that support the RDS role and are supported by Horizon 7. See "System Requirements for Guest Operating Systems" in the *Horizon 7 Installation* document.
- Horizon 7 provides load balancing of the RDS hosts in a farm by directing connection requests to the RDS host that has the least number of active sessions.

- Because a published desktop pool provides session-based desktops, it does not support operations that are specific to a linked-clone desktop pool, such as refresh, recompose, and rebalance.
- If an RDS host is a virtual machine that is managed by vCenter Server, you can use snapshots as base images. You can use vCenter Server to manage the snapshots. The use of snapshots on RDS host virtual machines is transparent to Horizon 7.
- Published desktops do not support Horizon 7 Persona Management.
- The copy and paste feature is disabled by default for HTML Access. To enable the feature, see "HTML Access Group Policy Settings" in the chapter "Configuring HTML Access for End Users" in the *Using HTML Access* document, available from <https://docs.vmware.com/en/VMware-Horizon-Client/index.html>.

Published Desktop Pools Settings

You can specify certain pool settings when you create a published desktop pool that run on a farm of RDS hosts. Not all pool settings apply to all types of desktop pools. These settings are specific to published desktop pools.

Table 5-1. Settings for a Published Desktop Pool

Setting	Description	Default Value
State	<ul style="list-style-type: none"> ■ Enabled. After being created, the desktop pool is enabled and ready for immediate use. ■ Disabled. After being created, the desktop pool is disabled and unavailable for use, and provisioning is stopped for the pool. This is an appropriate setting if you want to conduct post deployment activities such as testing or other forms of baseline maintenance. <p>When this state is in effect, remote desktops are unavailable for use.</p>	Enabled
Connection Server restrictions	<p>You can restrict access to the desktop pool to certain Connection Servers by clicking Browse and selecting one or more Connection Servers.</p> <p>If you intend to provide access to desktops through VMware Identity Manager, and you configure Connection Server restrictions, the VMware Identity Manager application might display desktops to users when those desktops are actually restricted. VMware Identity Manager users will be unable to launch these desktops.</p>	None
Category Folder	Specifies the name of the category folder that contains a Start menu shortcut for the desktop pool entitlement on Windows client devices.	Disabled

Table 5-1. Settings for a Published Desktop Pool (continued)

Setting	Description	Default Value
Client Restrictions	<p>Select whether to restrict access to entitled desktop pools from certain client computers.</p> <p>You must add the names of the computers that are allowed to access the desktop pool in an Active Directory security group. You can select this security group when you add users or groups to the desktop pool entitlement.</p>	Disabled
Allow user to initiate separate sessions from different client devices	<p>When you enable this setting, users that connect to the same desktop pool from different client devices receive different desktop sessions. To reconnect to an existing desktop session, users must use the same device from which that session was initiated. If you do not select this setting, users are always reconnected to their existing desktop sessions, regardless of the client device that they use. The RDP display protocol is not supported if you select this setting.</p> <p>Default is No.</p> <hr/> <p>Note If you enable this policy, all the desktop pools in the global entitlement must also support multiple sessions per user.</p> <hr/> <p>For more information about understanding the multiple sessions per user policy for global desktop entitlements, see the <i>Administering Cloud Pod Architecture in Horizon 7</i> document.</p>	

Create a Published Desktop Pool in Horizon Console

You create a published desktop pool as part of the process to give users access to desktops that run on a farm of RDS hosts.

Prerequisites

- Set up RDS hosts. See [Chapter 3 Setting Up Remote Desktop Services Hosts](#).
- Create a farm that contains the RDS hosts. See [Chapter 4 Creating Farms in Horizon Console](#).
- Decide how to configure the pool settings. See [Published Desktop Pools Settings](#).

Procedure

- 1 In Horizon Console, select **Inventory > Desktops**.
- 2 Click **Add**.
- 3 Select **RDS Desktop Pool** and click **Next**.

- 4 Provide a pool ID, display name, and description.

The pool ID is the unique name that identifies the pool in Horizon Console. The display name is the name of the published desktop pool that users see when they log in to Horizon Client. If you do not specify a display name, it will be the same as the pool ID.

- 5 Select pool settings.
- 6 Select or create a farm for this pool.

What to do next

Entitle users to access the pool.

Troubleshooting Instant Clones in the Internal VM Debug Mode

You can use the internal VM debug mode to troubleshoot internal virtual machines in instant-clone farms. With the internal VM debug mode, you can analyze failed internal virtual machines before these virtual machines are deleted. You must enable the internal VM debug mode before you create an instant-clone farm.

Procedure

- 1 In the vSphere Web Client, select the master VM, and click **Manage > Configure > VM Options > Edit > VM Options > Advanced > Edit Configuration**.

The **Configuration Parameters** window displays a list of parameter names and values.

- 2 In the **Configuration Parameters** window, search for the `cloneprep.debug.mode` parameter.

If the master VM does not have the `cloneprep.debug.mode` parameter, you must add `cloneprep.debug.mode` as the parameter name and add a value of ON or OFF. If the master VM has the `cloneprep.debug.mode` parameter, you can change the value of the parameter to ON or OFF.

- 3 Enable or disable the internal VM debug mode for internal VMs.
 - To enable the internal VM debug mode, set the value of `cloneprep.debug.mode` to ON. If you enable the internal VM debug mode, the internal VMs are not locked and cannot be deleted by Connection Server.
 - To disable the internal VM debug mode, set the value of `cloneprep.debug.mode` to OFF. If you disable the internal VM debug mode, the internal VMs are locked and can be deleted by Connection Server.

For instant-clone actions such as prime, provision, resync, or unprime, the internal virtual machines use the value set in the master virtual machine. If you do not disable the internal VM debug mode, then the VMs remain in vSphere till you delete the VMs. For further debugging on instant-clone actions, you can also log in to the internal VM and view the instant-clone logs. You can also see the following VMware Knowledge Base articles for further debugging on instant-clone actions:

- <https://kb.vmware.com/s/article/2150925>
- <https://kb.vmware.com/s/article/2151745>
- <https://kb.vmware.com/s/article/51154>
- <https://kb.vmware.com/s/article/53654>
- <https://kb.vmware.com/s/article/2003797>
- <https://kb.vmware.com/s/article/2150495>

Creating Application Pools in Horizon Console

6

One of the tasks that you perform to give users remote access to an application is to create an application pool. Users who are entitled to an application pool can access the application remotely from a variety of client devices.

With application pools, you can deliver a single application to many users. The application runs on a farm of RDS hosts or a desktop pool.

When you create an application pool, you deploy an application in the data center that users can access from anywhere on the network.

An application pool has a single application and is associated with a single farm or desktop pool. To avoid errors, you must install the application on all of the RDS hosts in the farm or desktop pool.

When you create an application pool, Horizon 7 automatically displays the applications that are available to all users rather than individual users from the **Start** menu on all the RDS hosts in the farm or desktop pool. You can select one or more applications from the list. If you select multiple applications from the list, a separate application pool is created for each application. You can also manually specify an application that is not on the list. If an application that you want to manually specify is not already installed, Horizon 7 displays a warning message.

When you create an application pool, you cannot specify the access group in which to place the pool. For published application and desktop pools, you specify the access group when you create a farm or desktop pool.

An application supports the PCoIP and VMware Blast display protocols. To enable HTML Access, see the *VMware Horizon HTML Access Installation and Setup Guide* document.

This chapter includes the following topics:

- [Worksheet for Creating an Application Pool Manually in Horizon Console](#)
- [Create an Application Pool in Horizon Console](#)

Worksheet for Creating an Application Pool Manually in Horizon Console

When you create an application pool and manually specify an application, you can add information about the application. It is not a requirement that the application is already installed on any RDS host.

Table 6-1. Worksheet: Application Properties for Creating an Application Pool Manually

Property	Description	Fill in Your Value Here
Select an RDS Farm or Desktop Pool	Select a farm or a desktop pool from the list of desktops with supported session type Application or Application and Desktop.	
ID	Unique name that identifies the pool in Horizon Administrator. This field is required.	
Display Name	Pool name that users see when they log in to Horizon Client. If you do not specify a display name, it will be the same as ID .	
Version	Version of the application.	
Publisher	Publisher of the application.	
Path	Full pathname of the application. For example, C:\Program Files\app1.exe. This field is required.	
Start Folder	Full pathname of the starting directory for the application.	
Parameters	Parameters to pass to the application when it starts. For example, you can specify <code>-username user1 -loglevel 3</code> .	
Description	Description of this application pool.	
Pre-launch	<p>Select this option to configure an application so that an application session is launched before a user opens the application in Horizon Client. When a published application is launched, the application opens more quickly in Horizon Client.</p> <p>If you enable this option, the configured application session is launched before a user opens the application in Horizon Client regardless of how the user connects to the server from Horizon Client.</p> <hr/> <p>Note This setting is not supported for applications based on a desktop pool.</p> <hr/> <p>Note Application sessions can be disconnected when the Pre-launch session timeout (applications only) option is set when you add or edit the application farm.</p> <hr/>	
Connection Server Restrictions	<p>You can restrict access to the application pool to certain Connection Servers by clicking Browse and selecting one or more Connection Servers.</p> <p>If you intend to provide access to desktops through VMware Identity Manager, and you configure Connection Server restrictions, the VMware Identity Manager application might display desktops to users when those desktops are actually restricted. VMware Identity Manager users will be unable to launch these desktops.</p>	

Table 6-1. Worksheet: Application Properties for Creating an Application Pool Manually (continued)

Property	Description	Fill in Your Value Here
Category Folder	Specifies the name of the category folder that contains a Start menu shortcut for the application pool entitlement on Windows client devices.	

Table 6-1. Worksheet: Application Properties for Creating an Application Pool Manually (continued)

Property	Description	Fill in Your Value Here
Client Restrictions	<p>Select whether to restrict access to entitled application pools from certain client computers.</p> <p>You must add the names of the computers that are allowed to access the application pool in an Active Directory security group. You can select this security group when you add users or groups to the application pool entitlement.</p>	
Multi-Session Mode	<p>You can start published application sessions in the following modes:</p> <p>Single-session: If the user opens a published application on client A in single-session mode, and then opens the same published application or another published application based on the same farm on client B then, the session on client A is disconnected and reconnected on client B.</p> <p>Multi-session: If the user opens a published application on client A in multi-session mode, and then opens the same published application or another published application based on the same farm on client B, the published application remains open on client A and a new session of the published application opens on client B. Such sessions are logged off on disconnect. You cannot enable the session pre-launch feature when multi-session mode is enabled.</p> <p>The multi-session mode has the following values:</p> <ul style="list-style-type: none"> ■ Disabled. Multi-session mode is not supported. ■ Enabled (Default Off). Multi-session mode is supported, but it is disabled by default. To use multi-session mode, users must enable the Multi-Launch setting in Horizon Client 4.10 or later. If the user has an earlier version of Horizon Client, the application is always started in single-session mode. ■ Enabled (Default On). Multi-session mode is supported, and it is enabled by default. Users can disable multi-session mode by disabling the Multi-Launch setting in Horizon Client 4.10 or later. If the user has an earlier version of Horizon Client, the application is always started in single-session mode. ■ Enabled (Enforced). Multi-session mode is always enabled. Users cannot disable it in any version of Horizon Client and the application is always launched in multi-session mode. If the 	

Table 6-1. Worksheet: Application Properties for Creating an Application Pool Manually (continued)

Property	Description	Fill in Your Value Here
	<p>user has an earlier version of Horizon Client, users get the following error message: "This application does not support the requested launch mode."</p> <p>When multi-session mode is enabled you can also configure the max-sessions count setting. This sets the maximum number of concurrent multi-sessions that can be started by a user for the same published application from different client devices.</p> <p>You can open a published application from a client in both the single-session mode and multi-session mode, which is based on the multi-session mode configuration. In this case, the client has one single-session and one multi-session.</p> <p>For more information about using the Multi-Launch setting, see the Horizon Client 4.10 documentation.</p> <hr/> <p>Note This setting is not supported for applications based on a desktop pool.</p>	

Create an Application Pool in Horizon Console

You create an application pool as part of the process to give users access to an application that runs on RDS hosts or a desktop pool.

Prerequisites

- Set up RDS hosts. See [Chapter 3 Setting Up Remote Desktop Services Hosts](#).
- Create a farm that contains the RDS hosts. See [Chapter 4 Creating Farms in Horizon Console](#).
- If you plan to add the application pool manually, gather information about the application. See [Worksheet for Creating an Application Pool Manually in Horizon Console](#)

Procedure

- 1 In Horizon Console, select **Inventory > Applications**.
- 2 Click **Add**.
- 3 Follow the prompts in the wizard to create the pool.

If you choose to add an application pool manually, use the configuration information you gathered in the worksheet. If you select applications from the list that Horizon Console displays, you can select multiple applications. A separate pool is created for each application.

What to do next

Entitle users to access the pool.

Make sure that your end users have access to Horizon Client 3.0 or later software, which is required to support published applications.

If you need to ensure that Connection Server launches the application only on RDS hosts that have sufficient resources to run the application, configure an anti-affinity rule for the application pool.

Note For applications running on desktop pools, the anti-affinity rule is supported only for applications created from floating desktop pools, and not from dedicated desktop pools.

See [Configure an Anti-Affinity Rule for an Application Pool in Horizon Console](#).

Managing Application Pools, Farms, and RDS Hosts

7

In Horizon Console, you can perform management operations such as configuring or deleting desktop pools, farms, or RDS hosts.

This chapter includes the following topics:

- [Managing Application Pools in Horizon Console](#)
- [Managing Farms in Horizon Console](#)
- [Managing RDS Hosts in Horizon Console](#)
- [Manage Published Desktop and Application Sessions in Horizon Console](#)
- [Configuring Load Balancing for RDS Hosts in Horizon Console](#)
- [Configure an Anti-Affinity Rule for an Application Pool in Horizon Console](#)

Managing Application Pools in Horizon Console

You can add, edit, delete, or entitle application pools in Horizon Console.

Edit an Application Pool in Horizon Console

You can edit an existing application pool to configure settings such as display name, version, publisher, path, start folder, parameters, and description. You cannot change the ID or access group of an application pool.

Prerequisites

- Familiarize yourself with the settings of an application pool.
- You might need to configure an anti-affinity rule to ensure that Connection Server launches the application only on RDS hosts that have sufficient resources to run the application.

Procedure

- 1 In Horizon Console, select **Inventory > Applications**.
- 2 Select a pool and click **Edit**.
- 3 Make changes to the pool settings.

- 4 Click **OK**.

Delete an Application Pool in Horizon Console

When you delete an application pool, users can no longer launch the application in the pool.

You can delete an application pool even if users are currently accessing the application. After the users close the application, they can no longer access the application.

Procedure

- 1 In Horizon Console, select **Inventory > Applications**.
- 2 Select one or more application pools and click **Delete**.
- 3 Click **OK** to confirm.

Duplicate an Application Pool in Horizon Console

You can duplicate an application pool to create multiple applications that are similar to each other.

When you duplicate an application pool, you can change the application pool ID and description to create a new application pool.

Note If there is an icon for the original application pool, the icon does not get associated with the duplicate application pool. However, you can assign the original icon to the duplicate application pool.

Note If there are user entitlements for the original application pool, the duplicate application pool does not get these entitlements and you must entitle users to the duplicate application pool again.

Procedure

- 1 In Horizon Console, select **Inventory > Applications**.
- 2 Select an application pools and click **Duplicate**.
- 3 Enter an application pool ID.
- 4 (Optional) Enter a display name and a description.
- 5 Click **OK**.

What to do next

Entitle users to the duplicate application pool. See [Add Entitlements to a Desktop or Application Pool in Horizon Console](#).

Change the Icon of a Published Application

You can customize the icons for published applications for end users. When you change the icon for a published application, the new application icon is available for the end user to view on the published desktop.

Prerequisites

- Verify that the icon is available in the .PNG file format.

Procedure

- 1 In Horizon Console, select **Inventory > Applications**.
- 2 Select an application pool or multiple application pools and click **Application Icon > Associate Application Icon**.

- 3 To upload an icon, click **Upload Icon File** and browse for an icon in the .PNG format.

The icon file must be between 16x16 pixels and 256x256 pixels.

- 4 Click **OK**.

The icon appears for the published application on the published desktop.

Remove the Icon of a Published Application

You can remove the icon of a published application to replace it with another icon. When you remove the icon for a published application, the published application is replaced with the default icon on the published desktop. You can remove icons from multiple published applications only if all published applications have the same icon. You cannot select multiple published applications that have different icons to remove an icon.

Procedure

- 1 In Horizon Console, select **Inventory > Applications**.
- 2 Select an application pool or multiple application pools and click **Application Icon > Remove Application Icon**.

The published application is replaced with the default icon on the published desktop.

Managing Farms in Horizon Console

In Horizon Console, you can add, edit, delete, enable, and disable farms.

After you create a farm, you can add or remove RDS hosts to support more or fewer users.

Edit a Farm in Horizon Console

For an existing farm, you can make changes to the configuration settings.

Prerequisites

Familiarize yourself with the settings of a farm.

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Select a farm and click **Edit**.

- 3 Make changes to the farm settings.
- 4 Click **OK**.

Delete a Farm in Horizon Console

You can delete a farm if you no longer need it or if you want to create a new one with different RDS hosts. You can only delete a farm that is not associated with published desktop or application pool.

Prerequisites

Verify that the farm is not associated with any published desktop pool or application pool.

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Select one or more farms and click **Delete**.
- 3 Click **OK** to confirm.

Disable or Enable a Farm in Horizon Console

When you disable a farm, users can no longer launch published desktops or applications from the published desktop pools and the application pools that are associated with the farm. Users can continue to use published desktops and applications that are currently open.

You can disable a farm if you plan to do maintenance on the RDS hosts in the farm or on the published desktop and application pools that are associated with the farm. After you disable a farm, some users might still be using published desktops or applications that they opened before you disable the farm.

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Select one or more farms and click **More Commands**.
- 3 Click **Enable** or **Disable**.
- 4 Click **OK** to confirm.

You can view the status of the pools by selecting **Inventory > Desktops** or **Inventory > Applications**.

Schedule Maintenance for an Automated Instant-Clone Farm in Horizon Console

With the maintenance operation, you can schedule recurring or immediate maintenance of all the RDS hosts in an automated instant-clone farm. During each maintenance cycle, all the RDS hosts are refreshed from the parent virtual machine.

You can make changes to the parent virtual machine without affecting the RDS host instant clones because the snapshot of the current parent VM is used for maintenance. The instant clones created in the automated farm use the information in the parent VM for their system configuration.

You can schedule maintenance on an automated farm but not on individual RDS hosts in the farm.

If possible, schedule maintenance operations during off-peak hours to ensure all that RDS hosts have finished maintenance and are available during peak hours.

Prerequisites

- Decide when to schedule the maintenance operation. By default, Connection Server starts the operation immediately.

You can schedule an immediate maintenance or recurring maintenance or both for a farm. You can schedule maintenance operations on multiple farms concurrently.

- Decide whether to force all users to log off when the maintenance operation begins or wait for each user to log off before refreshing that user's machine.

If you force users to log off, Horizon 7 notifies users before they are disconnected and allows them to close their applications and log off.

- Decide the minimum farm size. The minimum farm size is the number of RDS hosts that are kept available at all times to allow users to continue to use the farm. For example, if the farm size is ten and the minimum farm size is two, then maintenance will be performed on eight RDS hosts. As each RDS host becomes available again then the remaining hosts will go through maintenance. All RDS hosts are managed individually, so as one host becomes available then one of the remaining hosts will be put into maintenance.

However, if you schedule immediate maintenance, then all the RDS hosts in the farm will be put into maintenance.

All RDS hosts will also be subject to policy and will wait for logoff or force users to logoff depending upon what policy is configured.

- Decide whether to stop provisioning at first error. If you select this option and an error occurs when Connection Server provisions an instant-clone, provisioning stops. You can select this option to ensure that resources such as storage are not consumed unnecessarily.

Selecting the **Stop at first error** option does not affect customization. If a customization error occurs on an instant-clone, other clones continue to be provisioned and customized.

- Verify that provisioning is enabled. When provisioning is disabled, Horizon 7 stops the machines from being customized after they are refreshed.
- If your deployment includes replicated Connection Server instances, verify that all instances are the same version.

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Click the pool ID of the farm for which you want to schedule a maintenance.
- 3 Click **Maintain > Schedule**.

4 In the **Schedule Recurring Maintenance** wizard, choose a maintenance mode.

Option	Action
Recurring	<p>Schedules periodic maintenance of all the RDS host servers in a farm.</p> <ul style="list-style-type: none"> ■ Select a date and time from which the maintenance is effective. ■ Select a maintenance period. You can select daily, monthly, or weekly maintenance periods. ■ Select a repeat interval in days for the maintenance operation to recur. <p>If an immediate maintenance is scheduled on a farm, then the immediate maintenance date becomes the effective date for any recurring maintenance. If you cancel the immediate maintenance, then the current date becomes the effective date for recurring maintenance.</p>
Immediate	<p>Schedules immediate maintenance of all the RDS host servers in a farm. Immediate maintenance creates a one-time maintenance schedule for immediate or near future maintenance. Use immediate maintenance to refresh the farm from a new parent VM image or snapshot when you want to apply urgent security patches.</p> <p>Select an immediate maintenance configuration.</p> <ul style="list-style-type: none"> ■ Select Start Now to start the maintenance operation instantly. ■ Select Start at to start the maintenance operation at a near future date and time. Enter the date and Web browser local time. <p>Note Recurring maintenance will be put on hold until immediate maintenance is complete.</p>

5 Click **Next**.

6 (Optional) Click **Change** to change the parent virtual machine.

7 Select a snapshot.

You cannot select a different snapshot unless you clear the **Use current parent VM image** checkbox.

8 (Optional) Click **Snapshot Details** to display details about the snapshot.

9 Click **Next**.

10 (Optional) Specify whether to force users to log off or wait for users to log off.

The option to force users to log off is selected by default.

11 (Optional) Specify whether to stop provisioning at first error.

This option is selected by default.

12 Click **Next**.

The **Ready to Complete** page is displayed.

13 Click **Finish**.

Managing RDS Hosts in Horizon Console

You can manage RDS hosts that you set up manually and RDS hosts that are created automatically when you add an automated farm.

When you manually set up an RDS host, it automatically registers with Horizon Connection Server. You cannot manually register an RDS host with Connection Server. For an RDS host that you set up manually, you can perform the following management tasks:

- Edit the RDS host.
- Add the RDS host to a manual farm.
- Remove the RDS host from a farm.
- Enable the RDS host.
- Disable the RDS host.

For an RDS host that is created automatically when you add an automated farm, you can perform the following management tasks:

- Remove the RDS host from a farm.
- Enable the RDS host.
- Disable the RDS host.

Edit an RDS Host in Horizon Console

You can change the number of connections that an RDS host can support. This setting is the only one that you can change. The default value is 150. You can set it to any positive number, or to unlimited.

You can only edit an RDS host that you set up manually, but not an RDS host that is in an automated farm.

Procedure

- 1 In Horizon Console, select **Settings > Registered Machines**.
- 2 Select an RDS host and click **Edit**.
- 3 Specify a value for the setting **Number of connections**.
- 4 Click **OK**.

Add an RDS Host to a Manual Farm in Horizon Console

You can add an RDS host that you set up manually to a manual farm to increase the scale of the farm or for other reasons. You can only add RDS hosts to a manual farm.

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Click the farm ID.
- 3 Select the **RDS Hosts** tab.
- 4 Click **Add**.
- 5 Select one or more RDS hosts.
- 6 Click **OK**.

Remove an RDS Host from a Farm in Horizon Console

You can remove an RDS host from a manual farm to reduce the scale of the farm, to perform maintenance on the RDS host, or for other reasons. As a best practice, disable the RDS host and ensure that users are logged off from active sessions before you remove a host from a farm.

If users have application or desktop sessions on hosts that you remove, the sessions remain active, but Horizon 7 does not track them. A user who disconnects from a session will be unable to reconnect to it, and any unsaved data might be lost.

You can also remove an RDS host from an automated farm. One possible reason might be that the RDS host is in an unrecoverable error state.

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Click the farm ID.
- 3 Select the **RDS Hosts** tab.
- 4 Select one or more RDS hosts.
- 5 Click **Remove from farm**.
- 6 Click **OK**.

Remove an RDS Host from Horizon 7

You can remove from Horizon 7 an RDS host that you set up manually and that you no longer plan to use. The RDS host must not currently be in a manual farm.

Prerequisites

Verify that the RDS host does not belong to a farm.

Procedure

- 1 In Horizon Console, select **Settings > Registered Machines**.
- 2 Select an RDS host and click **Remove**.
- 3 Click **OK**.

After you remove an RDS host, to use it again, you must reinstall Horizon Agent.

Disable or Enable an RDS Host in Horizon Console

When you disable an RDS host, Horizon 7 no longer uses it to host new published desktops or applications. Users can continue to use published desktops and applications that are currently open.

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Click the farm ID.
- 3 Select the **RDS Hosts** tab.
- 4 Select an RDS host and click **More Commands**.
- 5 Click **Enable** or **Disable**.
- 6 Click **OK**.

If you enable the RDS host, a check mark appears in the Enabled column, and Available appears in the Status column. If you disable the RDS host, the Enabled column is empty and Disabled appears in the Status column.

Monitor RDS Hosts in Horizon Console

You can monitor the status and view the properties of RDS hosts in Horizon Console.

Procedure

- ◆ In Horizon Console, navigate to the page that displays the properties that you want to view.

Properties	Action
DNS Name, Type, Image, Pending Image, Task, Max Number of Connections, Sessions, Agent Version, Enabled, Status	<ul style="list-style-type: none"> ■ In Horizon Console, select Inventory > Farms. ■ Select a farm and click the RDS Hosts tab.
RDS Host, Farm, Desktop Pool, Agent Version, Sessions, Status	<ul style="list-style-type: none"> ■ In Horizon Console, select Inventory > Machines. ■ Click the RDS Hosts tab.
DNS Name, Type, RDS Farm, Max Number of Connections, Sessions, Agent Version, Enabled, Status	<ul style="list-style-type: none"> ■ In Horizon Console, select Settings > Registered Machines. ■ Click the RDS Hosts tab.

The properties are displayed and have the following meanings:

Property	Description
RDS Host	Name of the RDS host.
Farm	Farm to which the RDS host belongs.
Desktop Pool	Published desktop pool associated with the farm.
Agent Version	Version of Horizon Agent that runs on the RDS host.

Property	Description
Sessions	Number of client sessions.
DNS Name	DNS name of the RDS host.
Type	Version of Windows Server that runs on the RDS host.
RDS Farm	Farm to which the RDS host belongs.
Image	Image of the RDS host on the farm.
Pending Image	Pending image of the RDS host on the farm.
Task	Task being performed on the RDS host of the farm.
Max Number of Connections	Maximum number of connections that the RDS host can support.
Enabled	Whether the RDS host is enabled.
Status	State of the RDS host. See Status of RDS Hosts in Horizon Console for a description of the possible states.

Status of RDS Hosts in Horizon Console

An RDS host can be in various states from the time that it is initialized. As a best practice, check that RDS hosts are in the state that you expect them to be in before and after you perform tasks or operations on them.

Table 7-1. Status of an RDS Host

Status	Description
Startup	Horizon Agent has started on the RDS host, but other required services such as the display protocol are still starting. The agent startup period also allows other processes such as protocol services to start up.
Disable in progress	RDS host is in the process of being disabled while sessions are still running on the host. When the sessions end, the status changes to Disabled.
Disabled	Process of disabling the RDS host is complete.
Validating	Occurs after Connection Server first becomes aware of the RDS host, typically after Connection Server is started or restarted, and before the first successful communication with Horizon Agent on the RDS host. Typically, this state is transient. This state is not the same as the Agent unreachable state, which indicates a communication problem.
Agent disabled	Occurs if Connection Server disables Horizon Agent. This state ensures that a new desktop or application session cannot be started on the RDS host.
Agent unreachable	Connection Server cannot establish communication with Horizon Agent on an RDS host.
Invalid IP	Subnet mask registry setting is configured on the RDS host, and no active network adapters have an IP address within the configured range.
Agent needs reboot	Horizon 7 component was upgraded, and the RDS host must be restarted to allow Horizon Agent to operate with the upgraded component.
Protocol failure	The RDP display protocol is not running correctly. If RDP is not running and PCoIP is running, clients cannot connect using either RDP or PCoIP. However, if RDP is running and PCoIP is not running, clients can connect using RDP.

Table 7-1. Status of an RDS Host (continued)

Status	Description
Domain failure	RDS host encountered a problem reaching the domain. The domain server was not accessible, or the domain authentication failed.
Configuration error	RDS role is not enabled on the server.
Unknown	RDS host is in an unknown state.
Available	RDS host is available. If the host is in a farm, and the farm is associated with a published desktop or application pool, it will be used to deliver published desktops or applications to users.

Manage Published Desktop and Application Sessions in Horizon Console

When a user launches a published desktop or application, a session is created. You can disconnect and log off sessions, send messages to clients, reset, and restart virtual machines.

Procedure

- 1 In Horizon Console, navigate to where session information is displayed.

Session Type	Navigation
Remote desktop sessions	<p>Select Inventory > Desktops, click a pool's ID, and click the Sessions tab. The Sessions column also appears on the Desktop Pools page for all desktops.</p> <p>Select Inventory > Farms, click a farm's ID, and click the Sessions tab. You can also view the published applications associated with a session. The Application Names column displays the published applications associated with a session.</p> <p>The Sessions column also appears on the Farms page for all farms.</p> <p>Select Settings > Registered Machines, and view the Sessions column.</p>
Remote desktop and application sessions	Select Monitor > Sessions .
Sessions associated with a user or user group	<ul style="list-style-type: none"> ■ Select Users and Groups. ■ Click a user's name or a user group's name. ■ Click on the Sessions tab.

- 2 Select a session.

To send a message to users, you can select multiple sessions. You can perform the other operations on only one session at a time. You can perform a log off operation only on a session that is not connected from a vSphere console.

- 3 Choose whether to disconnect, log off, send a message, restart a desktop, or reset a virtual machine.

Option	Description
Disconnect Session	Disconnects the user from the session.
Logoff Session	Logs the user off the session. Data that is not saved is lost.

Option	Description
Send Message	Send a message to Horizon Client. You can label the message as Info , Warning , or Error .
Restart Desktop	Performs a restart operation on a virtual desktop, which performs a graceful operating system restart of the virtual machine. Note This option is not available for instant-clone farms.
Reset Virtual Machine	Performs a reset operation on a virtual machine without the graceful operating system restart, which performs a hard power-off and power-on of the virtual machine. Note This option is not available for instant-clone farms.

4 Click **OK**.

Configuring Load Balancing for RDS Hosts in Horizon Console

You can configure load balancing for RDS hosts by configuring load balancing settings in Horizon Console or by creating and configuring load balancing scripts.

By default, Connection Server uses the following formula to balance the placement of published desktop and application sessions on RDS hosts:

$$(\text{connected sessions} + \text{pending sessions} + \text{disconnected sessions}) / (\text{maximum session count})$$

If the maximum session count is configured as unlimited, load balancing falls back to using the absolute number of the total session count which includes connected, pending and disconnected sessions.

Load Balancing Settings in Horizon Console You can configure load balancing settings for a farm in Horizon Console to control the placement of published desktop and application sessions. See, [Load Balancing Settings](#).

Load Balancing Scripts You can also override the default behavior of the load balancing settings and control the placement of new published desktop and application sessions by writing and configuring load balancing scripts.

You can write your own custom load balancing scripts, or you can use one of the sample load balancing scripts provided with Horizon Agent. To use custom load balancing scripts, you must select the **Use Custom Script** load balancing setting in Horizon Console.

You can run these scripts on your own schedule or run these scripts with Horizon 7. For more information on configuring load balancing scripts in Horizon 7, see [Configure a Load Balancing Script on an RDS Host](#).

Configuring load balancing scripts involves enabling the VMware Horizon View Script Host service and setting a registry key on each RDS host in a farm.

Load balancing scripts must write the load index to the CustomLoadValue registry key with the REG_DWORD registry setting in the following location:

```
HKLM\Software\VMware Inc.\VMware VDM\Performance Stats
\CustomLoadValue
```

The value must be between 0-100.

Horizon 7 calculates the raw performance metrics that are written to the Performance Stats registry key in the following location:

```
HKLM\Software\VMware Inc.\VMware VDM\Performance Stats
```

You can use the raw performance metrics and combine these with your custom index factor for writing custom scripts.

Configure Load Balancing Settings on an RDS Host in Horizon Console

You can configure load balancing settings in Connection Server to control the placement of published desktop and application sessions on RDS hosts.

Procedure

- 1 In Horizon Console, select **Inventory > Farms**.
- 2 Click **Add** and follow the prompts to the **Load Balancing Settings** page.
- 3 Configure the load balancing settings. See, [Load Balancing Settings](#).
- 4 Follow the prompts to complete the wizard and click **Submit**.

Load Balancing Settings

Horizon 7 calculates the Server Load Index based on the load balancing settings you configure in Horizon Console. The Server Load Index indicates the load on the server. The Server Load Index can range from 0 to 100, where 0 represents no load and 100 represents full load. A Server Load Index of -1 indicates that load balancing is disabled. You can view the Server Load Index in the Horizon Console dashboard.

Follow the best practice of including the session count with other metrics when you configure load balancing settings. If the session count is not included, then, during load balancing, one of the RDS hosts gets considerably more session requests than other RDS hosts when a large number of users logon to the farm within 30 seconds. This occurs because the sampling interval is 30 seconds and the CPU, Memory, or Disk statistics are not collected in the last 30 seconds. As a result, all session requests in the last 30 seconds go to the RDS host that reports the lowest load index even though this RDS host, after a few sessions, gets a higher load than the other hosts.

To mitigate this issue, you can also reduce the sampling interval to collect the CPU, Memory, and Disk statistics more frequently than every 30 seconds. You can reduce the sampling interval to a minimum of 5 seconds however, this can affect performance on the RDS host. You can alter the sampling interval by configuring the **CPU and Memory Sampling Interval in Seconds** global policy setting. For more information on configuring global policy settings, see the *VMware Horizon Console Administration* document.

Table 7-2. Load Balancing Settings in Horizon Console

Option	Description
Use custom script	Select this setting to use a custom script for load balancing. If this setting is enabled, Horizon 7 does not consider other load balancing settings and reads the CustomLoadValue registry key in the following location to get the server load index: HKLM\Software\VMware Inc.\VMware VDM\Performance Stats\CustomLoadValue. See, Writing a Load Balancing Script for an RDS Host .
Include session count	Select this setting to include the session count on the RDS host for load balancing. If none of the settings are selected for load balancing and if the custom script setting is not selected, Horizon 7 uses the session count by default. Disable this setting if you do not need to consider the session count for load balancing.
CPU usage threshold	Threshold value for the CPU usage in percentage. Horizon 7 uses the configured CPU threshold to calculate the CPU load index factor. You can set a value from 0 to 100. The recommended value is 90. By default, this setting is not considered for load balancing. The default value is 0.
Memory usage threshold	Threshold value for the memory in percentage. Horizon 7 uses the configured memory threshold to calculate the Memory Load Index factor. You can set a value from 0 to 100. The recommended value is 90. By default, this setting is not considered for load balancing. The default value is 0.
Disk queue length threshold	Threshold of the average number of both read and write requests that were queued for the selected disk during the sample interval. Horizon 7 uses the configured threshold to calculate the Disk Load Index factor. You can set the value to any positive integer. By default, this setting is not considered for load balancing.
Disk read latency threshold	Threshold of the average time of read of data from the disk in milliseconds. Horizon 7 uses the configured threshold to calculate the Disk Load Index factor. You can set the value to any positive integer. By default, this setting is not considered for load balancing. The default value is 0.
Disk write latency threshold	Threshold of the average time of write of data to the disk in milliseconds. Horizon 7 uses the configured threshold to calculate the Disk Load Index factor. You can set the value to any positive integer. By default, this setting is not considered for load balancing. The default value is 0.

Writing a Load Balancing Script for an RDS Host

You can write a load balancing script to generate a load value based on any RDS host metric that you want to use for load balancing.

Your load balancing script must write the load index value to the CustomLoadValue registry key in the following location: HKLM\Software\VMware Inc.\VMware VDM\Performance Stats\CustomLoadValue. This value must be between 0-100.

If at least one RDS host in the farm returns a valid load value, the Connection Server assumes a load value of 25 for the other RDS hosts in farm until their load balancing scripts return valid values. If no RDS host in the farm returns a valid load value, the load balancing feature is disabled for the farm.

Note The Horizon Console dashboard shows -1 for those RDS hosts that do not report a load index. Connection Server only uses the value of 25 for internal load balancing logic.

If your load balancing script writes an invalid load value to the CustomLoadValue registry key, the value is capped at 100 and returned as the load index to the Connection Server. If the script is unable to create the CustomLoadValue registry key, the default value of 0 is sent as the load index to the Connection Server. If the custom script does not finish running within 10 seconds, Horizon 7 terminates the script after 10 seconds and uses stale values from the CustomLoadValue registry key as the load index.

Copy your load balancing script to the Horizon Agent scripts directory (C:\Program Files\VMware\VMware View\Agent\scripts) on each RDS host in the farm. You must copy the same script to every RDS host in the farm.

For an example how to write a load balancing script, see the sample scripts in the Horizon Agent scripts directory. For more information, see [Sample Load Balancing Scripts for RDS Hosts](#).

Upgrading Load Balancing Scripts

After a Connection Server and Horizon Agent upgrade to version 7.8 and later, earlier versions of custom scripts must write the custom load index to the CustomLoadValue registry key in the following location: HKLM\Software\VMware Inc.\VMware VDM\Performance Stats\CustomLoadValue. This value must be between 0-100. Custom scripts written to work with Connection Server and Horizon Agent versions earlier than 7.8 returned a number between 0-3.

You must also select the **Use custom script** setting in Horizon Console to enable load balancing settings for the farm. For more information on load balancing settings, see [Load Balancing Settings](#).

Note If you upgraded Horizon Agent to version 7.8 and later but did not upgrade Connection Server to version 7.8 and later, you cannot use custom scripts for load balancing. In this case, Horizon 7 load-balances the desktop and application sessions in the farm using the default option when no load balance settings are configured in Horizon Console.

Sample Load Balancing Scripts for RDS Hosts

When you install Horizon Agent on an RDS host, the installer places sample load balancing scripts in the Horizon Agent scripts directory (C:\Program Files\VMware\VMware View\Agent\scripts).

Table 7-3. Sample Load Balancing Scripts

Name	Description
cpuutilisation.vbs	Reads the percentage of CPU that has been utilized from the registry and writes it to the CustomLoadValue registry key.
memoryutilisation.vbs	Reads the percentage of memory that has been utilized from the registry and writes it to the CustomLoadValue registry key.

Enable the VMware Horizon View Script Host Service on an RDS Host

You must enable the VMware Horizon View Script Host service on an RDS host before you configure a load balancing script. The VMware Horizon View Script Host service is disabled by default.

Procedure

- 1 Log in to the RDS host as an administrator.
- 2 Start Server Manager.
- 3 Select **Tools > Services** and navigate to the VMware Horizon View Script Host service.
- 4 Right-click **VMware Horizon View Script Host** and select **Properties**.
- 5 In the Properties dialog box, select **Automatic** from the **Startup type** drop-down menu and click **OK** to save your changes.
- 6 Right-click **VMware Horizon View Script Host** and select **Start** to start the VMware Horizon View Script Host service.

The VMware Horizon View Script Host service restarts automatically each time the RDS host starts.

What to do next

Configure your load balancing script on each RDS host in the farm. See [Configure a Load Balancing Script on an RDS Host](#).

Configure a Load Balancing Script on an RDS Host

You must configure the same load balancing script on every RDS host in the farm. Configuring a load balancing script involves setting a registry key on the RDS host.

If you are using an automated farm, you perform this procedure on the parent virtual machine for the automated farm.

Important You must configure the load balancing script on all of the RDS hosts in a farm or on none of the RDS hosts in a farm. If you configure a load balancing script on only some of the RDS hosts in a farm, Horizon Console sets the status of the farm to red.

Prerequisites

- Write a load balancing script and copy the same script to the Horizon Agent scripts directory on each RDS host in the farm. See [Writing a Load Balancing Script for an RDS Host](#).
- Enable the VMware Horizon View Script Host service on the RDS host. See [Enable the VMware Horizon View Script Host Service on an RDS Host](#).

Procedure

- 1 Log in to the RDS host as an administrator.
- 2 Start Server Manager.

- 3 Select **Tools > System Configuration**, click the **Tools** tab, and launch the Registry Editor.
- 4 In the registry, navigate to HKEY_LOCAL_MACHINE\SOFTWARE\VMware, Inc.\VMware VDM\ScriptEvents.
- 5 In the navigation area, select the **RdshLoad** key.

The values for the **RdshLoad** key, if any, appear in the topic area (the right pane).
- 6 Right-click in the topic area for the **RdshLoad** key, select **New > String Value**, and create a new string value.

As a best practice, use a name that represents the load balancing script to be run, for example, **cpuutilisationScript** for the `cpuutilisation.vbs` script.
- 7 Right-click the entry for the new string value you created and select **Modify**.
- 8 In the **Value data** text box, type the command line that invokes your load balancing script and click **OK**.

Type the full path to your load balancing script.
For example: `cscript.exe "C:\Program Files\VMware\VMware View Agent\scripts\cpuutilisation.vbs"`
- 9 Restart the Horizon Agent service on the RDS host to make your changes take effect.

Your load balancing script begins to run on the RDS host.

What to do next

Repeat this procedure on each RDS host in the farm. If you performed this procedure on the parent virtual machine for an automated farm, provision the automated farm.

To verify that your load balancing script is working correctly, see [Verify a Load Balancing Script](#).

Verify a Load Balancing Script

You can verify that your load balancing script is working correctly by viewing RDS farm and RDS host information in Horizon Console.

Procedure

- 1 In Horizon Console, navigate to **Monitor > Dashboard**.
- 2 In the **Issues** pane, click **View**.
- 3 Click **RDS Farms** and click the name of each RDS host to view its load index.

The Server load field in the details dialog box shows the server load index reported by Horizon Agent. The value should be between 0-100.

The status of the farm should be green. If a load balancing script is configured on only some of the RDS hosts in a farm, Horizon Console sets the status of the farm to yellow. You must configure the load balancing script on all of the RDS hosts in a farm or on none of the RDS hosts in a farm.

What to do next

If load balancing is not working as you expected, verify the content of your load balancing script. If the script is written correctly, it should update the `CustomLoadValue` registry key on Horizon Agent with the expected load index. The `CustomLoadValue` registry key is located in the following location: `HKLM\Software\VMware Inc.\VMware VDM\Performance Stats\CustomLoadValue`. Verify that this registry key is updated correctly. If you use Horizon 7 to run your scripts, verify that the VMware Horizon View Script Host service is running. Also, verify that the same load balancing script is configured on each RDS host in the farm.

Configure an Anti-Affinity Rule for an Application Pool in Horizon Console

When you configure an anti-affinity rule for an application pool, Horizon Connection Server attempts to launch the application only on RDS hosts that have sufficient resources to run the application. This feature can be useful for controlling applications that consume large amounts of CPU or memory resources.

An anti-affinity rule consists of an application matching pattern and a maximum count. For example, the application matching pattern might be `autocad.exe` and the maximum count might be 2.

Connection Server sends the anti-affinity rule to Horizon Agent on an RDS host. If any applications running on the RDS host have process names that match the application matching pattern, Horizon Agent counts the current number of instances of those applications and compares the number to the maximum count. If the maximum count is exceeded, Connection Server skips that RDS host when it selects an RDS host to run new sessions of the application.

Prerequisites

- Create the application pool. See [Create an Application Pool in Horizon Console](#).
- Become familiar with the constraints of the anti-affinity feature. See [Anti-Affinity Feature Constraints](#).

Procedure

- 1 In Horizon Console, select **Inventory > Applications**.
- 2 Select the pool to modify and click **Edit**.
- 3 In the **Anti-Affinity Patterns** text box, type a comma-separated list of patterns to match against the process names of other applications running on RDS hosts.

The pattern string can include the asterisk (*) and question mark (?) wildcard characters. An asterisk matches zero or more characters and a question mark matches any single character.

For example, `*pad.exe,*notepad.???` matches `wordpad.exe`, `notepad.exe`, and `notepad.bat`, but it does not match `wordpad.bat` or `notepad.script`.

Note Horizon 7 counts multiple patterns that match for an application in a single session as a single match.

- 4 In the **Anti-Affinity Count** text box, type the maximum number of other applications that can be running on the RDS host before the RDS host is rejected for new application sessions.

The maximum count can be an integer from 1 to 20.

- 5 Click **Submit** to save your changes.

Anti-Affinity Feature Constraints

The anti-affinity feature has certain constraints.

- Anti-affinity rules affect new application sessions only. An RDS host that contains sessions in which a user has previously run an application is always reused for the same application. This behavior overrides reported load preferences and anti-affinity rules.
- Anti-affinity rules do not affect application launches from within an RDS desktop session.
- RDS session limits prevent application sessions from being created, regardless of anti-affinity rules.
- In certain circumstances, the instances of applications on the RDS host might not be restricted to the maximum count that you specify. For example, Horizon 7 cannot determine the exact instance count if other applications for other pending sessions are in the process of being launched.
- Inter-application anti-affinity rules are not supported. For example, large application classes, such as Autocad and Visual Studio instances, cannot be counted in a single rule.
- Do not use anti-affinity rules in environments where end-users use Horizon Client on mobile clients. Anti-affinity rules can result in multiple sessions in the same farm for an end user. Reconnecting to multiple sessions on mobile clients can result in indeterminate behavior.
- Anti-Affinity rules consider only the connected number of sessions for load balancing. However, load balancing for RDS hosts considers the sum of the connected, pending, and disconnected sessions for load balancing.

Entitling Users and Groups in Horizon Console

8

You configure entitlements to control which remote desktops and applications your users can access. You can configure the restricted entitlements feature to control desktop access based on the Horizon Connection Server instance that users connect to when they select remote desktops. You can also restrict access to a set of users outside the network from connecting to remote desktops and published applications within the network.

For information about configuring global entitlements in a Cloud Pod Architecture environment, see the *Administering Cloud Pod Architecture in Horizon 7* document.

Note Adding, removing, or reviewing entitlements is not supported for manual or linked-clone desktop pools.

This chapter includes the following topics:

- [Add Entitlements to a Desktop or Application Pool in Horizon Console](#)
- [Remove Entitlements from a Desktop or Application Pool in Horizon Console](#)
- [Review Desktop or Application Pool Entitlements](#)
- [Configuring Shortcuts for Entitled Pools](#)
- [Implementing Client Restrictions for Desktop and Application Pools](#)

Add Entitlements to a Desktop or Application Pool in Horizon Console

Before users can access remote desktops or applications, they must be entitled to use a desktop or application pool.

Prerequisites

Create a desktop or application pool.

Procedure

- 1 Select the desktop or application pool.

Option	Action
Add an entitlement for a desktop pool	In Horizon Console, select Inventory > Desktops and click the name of the desktop pool.
Add an entitlement for an application pool	In Horizon Console, select Inventory > Applications and click the name of the application pool.

- 2 Select **Add entitlement** from the **Entitlements** drop-down menu.
- 3 Click **Add**, select one or more search criteria, and click **Find** to find users or groups based on your search criteria.

Note Unauthenticated access users are filtered out of search results. Domain local groups are filtered out of search results for mixed-mode domains. You cannot entitle users in domain local groups if your domain is configured in mixed mode.

- 4 Select the users or groups you want to entitle to the desktops or applications in the pool and click **OK**.
- 5 Click **OK** to save your changes.

Remove Entitlements from a Desktop or Application Pool in Horizon Console

You can remove entitlements from a desktop or application pool to prevent specific users or groups from accessing a desktop or application.

Procedure

- 1 Select the desktop or application pool.

Option	Action
Add an entitlement for a desktop pool	In Horizon Console, select Inventory > Desktops and click the name of the desktop pool.
Add an entitlement for an application pool	In Horizon Console, select Inventory > Applications and click the name of the application pool.

- 2 Select **Remove entitlement** from the **Entitlements** drop-down menu.
- 3 Select the user or group whose entitlement you want to remove and click **Remove**.
- 4 Click **OK** to save your changes.

Review Desktop or Application Pool Entitlements

You can review the desktop or application pools to which a user or group is entitled.

Procedure

- 1 In Horizon Console, select **Users and Groups** and click the name of the user or group.
- 2 Click the **Entitlements** tab and review the desktop or application pools to which the user or group is entitled.

Option	Action
List the desktop pools to which the user or group is entitled	Click Desktop Entitlements .
List the application pools to which the user or group is entitled	Click Application Entitlements .

Configuring Shortcuts for Entitled Pools

You can configure shortcuts for entitled pools. When an entitled user connects to a Connection Server instance from a Windows client, Horizon Client for Windows places these shortcuts in the Start menu, on the desktop, or both, on the user's client device. You can configure a shortcut when you create or modify a pool.

You must select a category folder, or the root (/) folder, during shortcut configuration. You can add and name your own category folders. You can configure up to four folder levels. For example, you might add a category folder named Office and select that folder for all work-related apps, such as Microsoft Office and Microsoft PowerPoint.

For Start menu shortcuts, on Windows 7 client devices, Horizon Client places category folders and shortcuts in the VMware Applications folder in the Start menu. If you select the root (/) folder for a shortcut, Horizon Client places the shortcut directly in the VMware Applications folder. On Windows 8 and Windows 10 client devices, Horizon Client places category folders and shortcuts in the Apps list. If you select the root (/) folder for a shortcut, Horizon Client places the shortcut directly in the Apps list.

On Mac clients, if Horizon Client for Mac is configured to run published applications from the Applications folder and allow automatic shortcuts from the server, category folders for published applications appear in the Applications folder on the Mac client.

After you create a shortcut, a check mark appears in the **App Shortcut** column for the pool in Horizon Administrator and Horizon Console.

By default, Horizon Client for Windows prompts entitled users to install shortcuts the first time they connect to a server. You can configure Horizon Client for Windows to install shortcuts automatically, or to never install shortcuts, by modifying the **Automatically install shortcuts when configured on the Horizon server** group policy setting. For more information, see the *VMware Horizon Client for Windows Installation and Setup Guide* document.

By default, changes that you make to shortcuts are synchronized on a user's Windows client device each time the user connects to the server. Windows users can disable the shortcut synchronization feature in Horizon Client. For more information, see the *VMware Horizon Client for Windows Installation and Setup Guide* document.

For Windows users, this feature requires Horizon Client 4.6 for Windows or later on the client system. For Mac users, this feature requires Horizon Client 4.10 for Mac or later on the client system.

You can also configure a shortcut when you create or modify a global entitlement. For information about configuring global entitlements, see the *Administering Cloud Pod Architecture in Horizon 7* document.

Create Shortcuts for a Desktop Pool in Horizon Console

You can create shortcuts for an entitled desktop pool in Horizon Console so that the desktop pool appears in the Windows Start menu, on the Windows desktop, or both, on the user's Windows client device. You can specify up to four category folder levels for shortcuts. You can create shortcuts when you create a desktop pool. You can also create and modify shortcuts when you edit the desktop pool.

Prerequisites

Decide how to configure the pool settings based on the type of desktop pool that you want to create.

Procedure

- 1 In Horizon Console, click **Inventory > Desktops** and click **Add**.
- 2 In the **Add Pool** wizard, select the type of desktop pool you want to create, and click **Next**.
- 3 Follow the wizard prompts to the **Desktop Pool Settings** page.
- 4 Create shortcuts for the desktop pool.
 - a Click the Category Folder **Browse** button.
 - b Select the **Select a category folder from the folder list** option.
 - c Type a folder name in the **Select a category folder or create a new folder to place a shortcut to this pool in the client device** text box.

A folder name can be up to 64 characters long. To specify a subfolder, enter a backslash (\) character, for example, dir1\dir2\dir3\dir4. You can enter up to four folder levels. You cannot begin or end a folder name with a backslash, and you cannot combine two or more backslashes. For example, \dir1, dir1\dir2\, dir1\\dir2, and dir1\\\dir2 are invalid. You cannot enter Windows reserved keywords.

- d Select the shortcut creation method.

You can select one or both methods.

Option	Description
Start Menu/Launcher	Creates a Windows Start menu shortcut on the Windows client device.
Desktop	Creates a shortcut on the desktop on the Windows client device.

- e To save your changes, click **Submit**.
- 5 Follow the wizard prompts to the **Ready to Complete** page and select **Entitle users after this wizard finishes** and click **Submit**.

- 6 In the **Add Entitlements** wizard, click **Add**, select one or more search criteria, and click **Find** to find users or groups based on your search criteria, select the users or groups you want to entitle to the desktops in the pool and click **OK**.

A check mark appears in the **App Shortcut** column for the desktop pool on the **Desktop Pools** page.

Create Shortcuts for an Application Pool in Horizon Console

You can create shortcuts for entitled applications in Horizon Console so that the shortcuts appear in the Windows Start menu, on the Windows desktop, or both, on the user's Windows client device. You can specify up to four category folder levels for shortcuts. You can create shortcuts when you create an application pool. You can also create shortcuts when you edit the application pool.

On Mac clients, if Horizon Client for Mac is configured to run published applications from the Applications folder on the local system and allow folder settings from servers, category folders appear in the Applications folder on the Mac client device. For more information, see the *VMware Horizon Client for Mac Installation and Setup Guide* document.

Prerequisites

- Set up RDS hosts. See "Setting Up Remote Desktop Services Hosts," in the *Setting Up Desktop and Application Pools in Horizon 7* document.
- Create a farm that contains the RDS hosts. See [Chapter 4 Creating Farms in Horizon Console](#).
- If you plan to add the application pool manually, gather information about the application. See [Worksheet for Creating an Application Pool Manually in Horizon Console](#).
- Install Horizon Client 4.6 for Windows or later on the client device.

Procedure

- 1 In Horizon Console, click **Inventory > Applications** and click **Add**.
- 2 Select the type of application pool you want to create.

Option	Description
Add application pool manually	Enter the information about the application. See Worksheet for Creating an Application Pool Manually in Horizon Console .
Select installed applications	Filter to find applications by name, installed path, or application type, or select from a list of installed applications. For information about configuring additional options, see Worksheet for Creating an Application Pool Manually in Horizon Console .

- 3 In the **Add Application Pool** wizard, select an RDS farm, enter a pool ID, and the full pathname of the application.
- 4 Create a shortcut for the application pool.
 - a Click the Category Folder **Browse** button.
 - b Select the **Select a category folder from the folder list** option.

- c Select a category folder from the list, or type a folder name in the **Select a category folder or create a new folder to place a shortcut to this pool in the client device** text box.

A folder name can be up to 64 characters long. To specify a subfolder, enter a backslash (\) character, for example, dir1\dir2\dir3\dir4. You can enter up to four folder levels. You cannot begin or end a folder name with a backslash, and you cannot combine two or more backslashes. For example, \dir1, dir1\dir2\, dir1\\dir2, and dir1\\\dir2 are invalid. You cannot enter Windows reserved keywords.

Note If needed, non-Windows clients can translate the backslash to a forward slash.

- d Select the shortcut creation method.

You can select one or both methods.

Option	Description
Start Menu/Launcher	Creates a Windows Start menu shortcut on the Windows client device.
Desktop	Creates a shortcut on the desktop on the Windows client device.

- e To save your changes, click **Submit**.

5 Select **Entitle users after this wizard finishes**.

- 6 In the **Add Entitlements** wizard, click **Add**, select one or more search criteria, and click **Find** to find users or groups based on your search criteria, select the users or groups you want to entitle to the application in the pool and click **OK**.

A check mark appears in the **App Shortcut** column for the application pool on the **Application Pools** page.

Implementing Client Restrictions for Desktop and Application Pools

You can restrict access to entitled published desktop and application pools to specific client computers. To restrict access, you must add the names of the client computers that are allowed to access the published desktops or applications in an Active Directory security group and then entitle this group to a pool. The Active Directory security group can contain client computers that belong to any AD Organizational Units (OUs) or default Computer container.

The client restrictions features has certain requirements and limitations.

- You must enable the client restrictions policy when you create or modify the published desktop or application pool. By default, the client restrictions policy is disabled. For published desktop pool settings, see [Published Desktop Pools Settings](#). For application pool settings, see [Worksheet for Creating an Application Pool Manually in Horizon Console](#).
- When you create or modify entitlements for the published desktop or application pool, you must add the Active Directory security group that contains the names of the client computers that are allowed to access the published desktop or application pool.

- The client restrictions feature allows only specific client computers to access published desktop and application pools. It does not give users access to non-entitled desktop and application pools. For example, if a user is not included in an application pool entitlement (either as a user or as a member of a user group), the user cannot access the application pool, even if the user's client computer is part of the AD security group that is entitled to the application pool.
- The client restrictions feature is supported only with Windows client computers in this release. Horizon Client 4.6 for Windows or later is required on the client computers.
- When the client restrictions policy is enabled for published desktop or application pools, non-Windows clients, Windows clients running pre-4.6 versions of Horizon Client for Windows, and HTML Access clients cannot launch the desktops or applications from the restricted pools.
- The client restrictions feature only restricts new sessions from Windows clients. This feature does not restrict existing application session connections from previous user sessions.
- Horizon Client for Windows version 5.0 requires that the client computers belonging to an Active Directory security group be located in the default AD location "CN=Computers."